

Linux Command

❑ Linux Basic Command :

- 1) **sudo su** : It is used to switch user as a root user.

```
[ec2-user@ip-172-31-31-108 ~]$ sudo su
[root@ip-172-31-31-108 ec2-user]# |
```

- 2) **sudo i** : used to change folder or directory.

- 3) **tty** : check terminal type and number.

```
[root@ip-172-31-31-108 ec2-user]# tty
/dev/pts/1
[root@ip-172-31-31-108 ec2-user]#
```

- 4) **whoami** : used to show current login user.

```
/dev/pts/1
[root@ip-172-31-31-108 ec2-user]# whoami
root
[root@ip-172-31-31-108 ec2-user]#
```

- 5) **who am i** : show detailed information about current login user.

```
root
[root@ip-172-31-31-108 ec2-user]# who am i
ec2-user pts/1          2025-09-18 00:14 (103.151.234.91)
[root@ip-172-31-31-108 ec2-user]#
```

- 6) **cal** : to display calender.

```
[root@ip-172-31-31-108 ec2-user]# cal
      September 2025
Su Mo Tu We Th Fr Sa
    1  2  3  4  5  6
 7  8  9 10 11 12 13
14 15 16 17 18 19 20
21 22 23 24 25 26 27
28 29 30
```

- 7) **cal -3** : to display previous , current, next month calender.

```
[root@ip-172-31-31-108 ec2-user]# cal -3
      August 2025          September 2025          October 2025
Su Mo Tu We Th Fr Sa Su Mo Tu We Th Fr Sa Su Mo Tu We Th Fr Sa
    1 2              1 2 3 4 5 6              1 2 3 4
 3  4  5  6  7  8  9  7  8  9 10 11 12 13  5  6  7  8  9 10 11
10 11 12 13 14 15 16 14 15 16 17 18 19 20 12 13 14 15 16 17 18
17 18 19 20 21 22 23 21 22 23 24 25 26 27 19 20 21 22 23 24 25
24 25 26 27 28 29 30 28 29 30              26 27 28 29 30 31
31
[root@ip-172-31-31-108 ec2-user]#
```

8) **date** : To display date.

```
[root@ip-172-31-31-108 ec2-user]# date
Thu Sep 18 00:22:02 UTC 2025
[root@ip-172-31-31-108 ec2-user]#
```

9) **date -s** : set date and time (Syntax : YYYY/MM/DD “HH:MM:SS”)

❑ Command View system information :

1) **hostnamectl** : Used to display detail information about system.

```
[root@ip-172-31-31-108 ec2-user]# hostnamectl
Static hostname: ip-172-31-31-108.ec2.internal
Icon name: computer-vm
Chassis: vm
Machine ID: ec26a8cda45286cdb21a92b8a2cc19f9
Boot ID: 7346e60ed4294598be223d6755fd3be9
Virtualization: amazon
Operating System: Amazon Linux 2023.8.20250818
CPE OS Name: cpe:2.3:o:amazon:amazon_linux:2023
Kernel: Linux 6.1.147-172.266.amzn2023.x86_64
Architecture: x86-64
Hardware Vendor: Amazon EC2
Hardware Model: t3.micro
Firmware Version: 1.0
[root@ip-172-31-31-108 ec2-user]#
```

2) **Uname** : Used to display operating system.

```
Firmware version: 1.0
[root@ip-172-31-31-108 ec2-user]# uname
Linux
[root@ip-172-31-31-108 ec2-user]#
```

- 3) **Uname -r** : used to display version of the system(kernel).

```
[root@ip-172-31-31-108 ec2-user]# uname -r
6.1.147-172.266.amzn2023.x86_64
[root@ip-172-31-31-108 ec2-user]#
```

- 4) **Uname -a** : used to display static name,GNU project , date,time all details of the operating system.

```
[root@ip-172-31-31-108 ec2-user]# uname -a
Linux ip-172-31-31-108.ec2.internal 6.1.147-172.266.amzn2023.x86_64 #1 SMP PREEMPT_DYNAMIC Thu Aug 7 19:30:40 UTC 2025 x86_64 x86_64 x86_64 GNU/Linux
[root@ip-172-31-31-108 ec2-user]#
```

□ List Command :

- 1) **ls** : display all directory and file .

```
[root@ip-172-31-31-108 ec2-user]# ls
1 Demo Project Project1 Project2 Project3 Project4 Project5 dir f1 new newdir
[root@ip-172-31-31-108 ec2-user]#
```

- 2) **ls -l** : display directory and file in listing format.

```
[root@ip-172-31-31-108 ec2-user]# ls -l
total 4
drwxr-xr-x. 2 ec2-user ec2-user 6 Sep 8 13:39 1
-rw-r--r--. 1 ec2-user ec2-user 0 Sep 5 15:17 Demo
drwxr-xr-x. 2 ec2-user ec2-user 6 Sep 8 13:39 Project
drwxr-xr-x. 3 ec2-user ec2-user 22 Sep 8 13:40 Project1
drwxr-xr-x. 2 ec2-user ec2-user 6 Sep 8 13:38 Project2
drwxr-xr-x. 2 ec2-user ec2-user 6 Sep 8 13:38 Project3
drwxr-xr-x. 2 ec2-user ec2-user 6 Sep 8 13:38 Project4
drwxr-xr-x. 2 ec2-user ec2-user 6 Sep 8 13:38 Project5
-rw-r--r--. 1 ec2-user ec2-user 0 Sep 8 14:35 dir
-rw-r--r--. 1 root root 30 Sep 9 14:27 f1
drwxr-xr-x. 2 ec2-user ec2-user 6 Sep 5 15:18 new
drwxr-xr-x. 2 ec2-user ec2-user 6 Sep 8 13:32 newdir
[root@ip-172-31-31-108 ec2-user]#
```

- 3) **ls -r** : display file in recursive(reverce order).

```
[root@ip-172-31-31-108 ec2-user]# ls -r
newdir new f1 dir Project5 Project4 Project3 Project2 Project1 Project Demo 1
[root@ip-172-31-31-108 ec2-user]#
```

- 4) **ls -a** : display hidden files.

```
[root@ip-172-31-31-108 ec2-user]# ls -r
newdir new f1 dir Project5 Project4 Project3 Project2 Project1 Project Demo 1
[root@ip-172-31-31-108 ec2-user]# ls -a
. .bash_history .bash_profile .lessshst 1 Project Project2 Project4 dir new
.. .bash_logout .bashrc .ssh Demo Project1 Project3 Project5 f1 newdir
[root@ip-172-31-31-108 ec2-user]#
```

5) **ls -t** : sort file according to latest.

```
[root@ip-172-31-31-108 ec2-user]# ls -t
f1 dir Project1 1 Project Project2 Project3 Project4 Project5 newdir new Demo
[root@ip-172-31-31-108 ec2-user]#
```

6) **ls -s** : show file or directory with its size.

```
[root@ip-172-31-31-108 ec2-user]# ls -s
total 4
0 1 0 Demo 0 Project 0 Project1 0 Project2 0 Project3 0 Project4 0 Project5 0 dir 4 f1 0 new 0 newdir
[root@ip-172-31-31-108 ec2-user]#
```

□ Directory Commands :

1) **mkdir** : used to make directory.

```
[ec2-user@ip-172-31-31-108 ~]$ mkdir Ram
[ec2-user@ip-172-31-31-108 ~]$ ls
Ram new newdir
[ec2-user@ip-172-31-31-108 ~]$
```

2) **mkdir[directory name{.....}]** : used to make directory in sequence.

```
[ec2-user@ip-172-31-31-108 Ram]$ mkdir [Project{1,2,3,4,5}]
[ec2-user@ip-172-31-31-108 Ram]$ ls
'[Project1]' '[Project2]' '[Project3]' '[Project4]' '[Project5]'
[ec2-user@ip-172-31-31-108 Ram]$
```

3) **mkdir -p** : parent child relation.

```

[ec2-user@ip-172-31-31-108 ~]$ mkdir ram
[ec2-user@ip-172-31-31-108 ~]$ ls
new  newdir  ram
[ec2-user@ip-172-31-31-108 ~]$ cd ram
[ec2-user@ip-172-31-31-108 ram]$ mkdir -p sita
[ec2-user@ip-172-31-31-108 ram]$ ls
sita
[ec2-user@ip-172-31-31-108 ram]$

```

4) **mkdir -p dir1/dir2/dir3...** : Used to make multiple directory at a time.

```

rm: failed to remove sita: No such file or directory
[ec2-user@ip-172-31-31-108 ~]$ ls
new  newdir  ram
[ec2-user@ip-172-31-31-108 ~]$ cd ram
[ec2-user@ip-172-31-31-108 ram]$ ls
sita
[ec2-user@ip-172-31-31-108 ram]$ rmdir sita
[ec2-user@ip-172-31-31-108 ram]$ ls
[ec2-user@ip-172-31-31-108 ram]$ mkdir -p sita/kush/lav
[ec2-user@ip-172-31-31-108 ram]$ ls
sita
[ec2-user@ip-172-31-31-108 ram]$ cd sita
[ec2-user@ip-172-31-31-108 sita]$ la
bash: la: command not found
[ec2-user@ip-172-31-31-108 sita]$ ls
kush
[ec2-user@ip-172-31-31-108 sita]$ cd kush
[ec2-user@ip-172-31-31-108 kush]$ ls
lav
[ec2-user@ip-172-31-31-108 kush]$ cd lav
[ec2-user@ip-172-31-31-108 lav]$ ls
[ec2-user@ip-172-31-31-108 lav]$

```

5) **cd** : change directory.

```

rm: failed to remove sita: No such file or directory
[ec2-user@ip-172-31-31-108 ~]$ ls
new newdir ram
[ec2-user@ip-172-31-31-108 ~]$ cd ram
[ec2-user@ip-172-31-31-108 ram]$ ls
sita
[ec2-user@ip-172-31-31-108 ram]$ rmdir sita
[ec2-user@ip-172-31-31-108 ram]$ ls
[ec2-user@ip-172-31-31-108 ram]$ mkdir -p sita/kush/lav
[ec2-user@ip-172-31-31-108 ram]$ ls
sita
[ec2-user@ip-172-31-31-108 ram]$ cd sita
[ec2-user@ip-172-31-31-108 sita]$ la
bash: la: command not found
[ec2-user@ip-172-31-31-108 sita]$ ls
kush
[ec2-user@ip-172-31-31-108 sita]$ cd kush
[ec2-user@ip-172-31-31-108 kush]$ ls
lav
[ec2-user@ip-172-31-31-108 kush]$ cd lav
[ec2-user@ip-172-31-31-108 lav]$ ls
[ec2-user@ip-172-31-31-108 lav]$

```

- 6) **cd ..** : used for to go backward from current directory or backward to previous directory.

```

[ec2-user@ip-172-31-31-108 kush]$ cd lav
[ec2-user@ip-172-31-31-108 lav]$ ls
[ec2-user@ip-172-31-31-108 lav]$ cd ..
[ec2-user@ip-172-31-31-108 kush]$ ls
lav
[ec2-user@ip-172-31-31-108 kush]$

```

- 7) **cd ../../..** : used for multiple directory to go backward from current directory or backward to previous directory.

```

[ec2-user@ip-172-31-31-108 lav]$ ls
[ec2-user@ip-172-31-31-108 lav]$ cd ../../..
[ec2-user@ip-172-31-31-108 ram]$ cd sita/kush/lav
[ec2-user@ip-172-31-31-108 lav]$ cd ../../..
[ec2-user@ip-172-31-31-108 sita]$ ls
kush
[ec2-user@ip-172-31-31-108 sita]$

```

- 8) **rmdir** : Remove empty directory.

```

[ec2-user@ip-172-31-31-108 kush]$ ls
lav
[ec2-user@ip-172-31-31-108 kush]$ rmdir lav
[ec2-user@ip-172-31-31-108 kush]$ ls
[ec2-user@ip-172-31-31-108 kush]$

```

- 9) **rm -r** : remove non-empty directory.

```
[ec2-user@ip-172-31-31-108 sita]$ ls
kush
[ec2-user@ip-172-31-31-108 sita]$ rm -r kush
[ec2-user@ip-172-31-31-108 sita]$ ls
[ec2-user@ip-172-31-31-108 sita]$
```

- 10) **rm** : remove empty file.

```
[ec2-user@ip-172-31-31-108 ram]$ touch file
[ec2-user@ip-172-31-31-108 ram]$ ls
file sita
[ec2-user@ip-172-31-31-108 ram]$ rm file
[ec2-user@ip-172-31-31-108 ram]$ ls
sita
[ec2-user@ip-172-31-31-108 ram]$
```

- 11) **rm -f filename** : Remove file forcefully.

Document 3

```
[ec2-user@ip-172-31-31-108 ram]$ ls
file1 sita
[ec2-user@ip-172-31-31-108 ram]$ rm -f file1
[ec2-user@ip-172-31-31-108 ram]$ ls
sita
[ec2-user@ip-172-31-31-108 ram]$
```

- 12) **rm -rvf filename** : remove non-empty file and show which files are removed.

```
[ec2-user@ip-172-31-31-108 ~]$ ls
new newdir ram
[ec2-user@ip-172-31-31-108 ~]$ rm -rvf ram
removed directory 'ram/sita/kush/lav'
removed directory 'ram/sita/kush'
removed directory 'ram/sita'
removed directory 'ram'
[ec2-user@ip-172-31-31-108 ~]$
```

- 13) **rm -rf filename**: remove file forcefully

```
[ec2-user@ip-172-31-31-108 ~]$ mkdir -p ram/sita/kush/lav
[ec2-user@ip-172-31-31-108 ~]$ ls
new  newdir  ram
[ec2-user@ip-172-31-31-108 ~]$ rm -rf ram
[ec2-user@ip-172-31-31-108 ~]$ ls
new  newdir
[ec2-user@ip-172-31-31-108 ~]$
```