Table of Contents

About kode80 Clouds
kode80 Clouds License Details
Clouds Properties
Render
Target Camera
Sub Pixel Size
Max Iterations
Render Size
Fixed Width/Height
<u>Downsample</u>
<u>Coverage</u>
Cloud Coverage
Coverage Offset
Horizon Coverage Start/End
<u>Lighting</u>
Cloud Base/Top Color
Sun Light
Sun/Ambient Scalar
Sun Ray Length
Cone Radius
<u>Density</u>
Forward/Backward Scattering G
Dark Outline Scalar
<u>Animation</u>
Animation Scale
Coverage Offset Per Frame X/Y

Base Offset Per Frame X/Y/Z Detail Offset Per Frame X/Y/Z Modeling (Base) **Base Scale** Cloud Gradient 1/2/3 Sample Scalar Sample Threshold Cloud Bottom Fade Modeling (Detail) **Detail Scale Erosion Edge Size Cloud Distorion Cloud Distortion Scale Optimization LOD Distance Horizon Level Horizon Fade** Horizon Fade Start Alpha <u>Atmosphere</u> Horizon Distance Atmosphere Start/End Height Camera Position Scalar **Cloud Shadows Coverage Editor Editor Modes Editor Properties Editor Camera Brush Properties Cubemap Export**

About kode80 Clouds

kode80 Clouds is a realtime volumetric cloud rendering solution for Unity3D, offering fully dynamic, animated, 3D cloudscapes along with a custom editor for painting clouds directly into your scene. All properties; from cloud density and shape to sun and ambient lighting can be adjusted in realtime. Cloud coverage and type are controlled by a special coverage texture which can also be updated in realtime, opening the door for custom cloud animations and weather systems.

To get the most out of kode80 Clouds, please take a moment to read this manual and explore the included example scene.

If you have any questions, get in touch!

email: support@kode80.com

twitter: <u>@kode80</u>

kode80 Clouds License Details

kode80 Clouds for Unity3D is free to use for strictly **non-commercial** purposes. The full non-commercial license is included in the project root.

To use kode80 Clouds for Unity3D for **any commercial** purposes, or to support this & future kode80 development, **commercial licenses** are available for purchase from: http://kode80.com/

Clouds Properties

This is the page describing what each of the clouds properties do.

Render

Describes the render properties.

Target Camera

The camera used to render the clouds.

Sub Pixel Size

The number of frames a full resolution render is spread across using temporal reprojection.

Max Iterations

The maximum number of ray steps per pixel

Render Size

Either use camera pixel dimensions (with optional downsample) or a fixed resolution.

Note: for VR projects you should set Render Size to Fixed and Fixed Width/Height manually as Unity's native VR support does not currently report the correct per-eye resolution.

Fixed Width/Height

The dimensions of the cloud render, when Render Size is set to fixed.

Downsample

The amount to downsample the cloud render, when Render Size is set to Camera Dimensions

Coverage

Describes the cloud coverage properties.

Cloud Coverage

The coverage texture. This controls the coverage amount, type and position of clouds in your scene. For more details, read the <u>Coverage Editor</u> section.

Coverage Offset

The x/y offset from center of the cloud coverage. Use

this to *scroll* the clouds.

Horizon Coverage Start/End

The normalized distance from the camera that coverage starts to fade from the coverage map to full coverage.

Lighting

Describes the lighting properties.

Cloud Base/Top Color

The ambient light color for the bottom and top of clouds near the camera.

Sun Light

The Unity3D directional light used as the sun. The light's direction and color are used to render direct cloud lighting.

Sun/Ambient Scalar

Multiplier for sun/ambient light.

Sun Ray Length

Normalized length of sun rays when calculating cloud lighting.

Cone Radius

Normalized radius of sun ray cone when calculating cloud lighting.

Density

Cloud particle density when calculating cloud lighting. Higher values will give clouds a 'thicker' appearance.

Forward/Backward Scattering G

The Henyey-Greenstein G values for forward/backward scattering when calculating cloud lighting.

Dark Outline Scalar

Alpha value for cloud dark outline, when camera is facing along sun direction.

Animation

Describes clouds animation properties.

Animation Scale

Global time scalar for all animation properties.

Coverage Offset Per Frame X/Y

The amount to scroll the coverage map each frame.

Base Offset Per Frame X/Y/Z

The amount to scroll the low frequency noise 3D texture each frame.

Detail Offset Per Frame X/Y/Z

The amount to scroll the high frequency noise 3D texture each frame.

Modeling (Base)

Descrobes the modeling base properties.

Base Scale

The amount the low frequency noise 3D texture is scaled. Setting to 1 scales to fit the height of the atmosphere.

Cloud Gradient 1/2/3

The cloud gradients determine how the different frequencies of 3D noise are blended together based on height in atmosphere.

Sample Scalar

Scales the cloud particle alpha values *before* passing to cloud lighting calculations.

Sample Threshold

Determines the cutoff value for cloud particle values from the 3D noise textures when modeling the clouds.

Cloud Bottom Fade

The normalized height in the atmosphere that cloud bottom fading ends. Setting to higher values results in softer cloud bottoms.

Modeling (Detail)

Describes the detail cloud modeling properties.

Detail Scale

The amount the high frequency noise 3D texture is scaled. Setting to 8 matches the scale of the low

frequency noise.

Erosion Edge Size

A normalized value that determins how far in from the edges of the base cloud shape high frequency noise should erode.

Cloud Distorion

A normalized value that controls the level of curl distortion applied to the high frequency noise during cloud modeling.

Cloud Distortion Scale

Controls the scale of the curl noise distortion texture. Setting to 0.5 is a good default value.

Optimization

Describes the optimization properties.

LOD Distance

The normalized distance from the camera that raycasting switches to low level of detail (ignores high frequency noise modeling step).

Horizon Level

The normalized height of the horizon. Any clouds below the horizon level will not be rendered, this can be useful if the horizon is largely obscured by your scene's geometry since clouds will always be rendered regardless of occlusion. As an example, if in your scene the only time the clouds are viewable is by looking directly up through a skylight window, then you can set the Horizon Level property to a high value.

Horizon Fade

The normalized distance from the horizon to the camera over which clouds are faded to completely transparent.

Horizon Fade Start Alpha

The starting alpha value when blending clouds from the horizon. Useful for blending the horizon with another skybox.

Atmosphere

Describes the properties that control the atmosphere and by extension, the size of the planet.

Horizon Distance

The distance in world units from the camera to the horizon.

Atmosphere Start/End Height

The height in world units that the atmosphere starts and ends. i.e. End - Start = atmosphere *thickness*.

Camera Position Scalar

A multiplier that is applied to the Unity3D camera's world position when rendering the clouds.

Cloud Shadows

Using the kode80CloudShadows component, it is possible to add an extra level of realism by having the clouds cast shadows *onto* your scene geometry. To enable cloud shadows:

- 1. Add the kode80CloudShadows component to your directional light
- 2. Assign your kode80Clouds instance to the clouds property of the kode80CloudShadows component

Note: as with all shadows in Unity, the distance at which cloud shadows are rendered is controlled by the Shadow Distance property in your project's Quality settings.

Coverage Editor

This is page describes how to use the clouds editor.

Editor Modes

The Coverage Editor has 3 main modes; Camera, Coverage and Type. When in Camera mode you can navigate your scene using the mouse and WASD controls. When in Coverage or Type mode, you can paint directly into your scene using the mouse, holding down shift will negate the opacity value of the brush (allowing you to erase Coverage/Type data).

Editor Properties

Enable continuous update mode to view a continuous animated preview in the Coverage Editor.

Editor Camera

When opening the Coverage Editor, a special camera is automatically created by duplicating the clouds target camera, including image effects. This is useful for getting an accurate preview of the game's render directly in the Coverage Editor. Any image effect on

this camera can be manually disabled from the Editor Camera foldout in the Coverage Editor.

Brush Properties

When painting clouds in the Coverage Editor you can control the brush size, opacity and texture from the Brush Properties foldout. When the Blend Values toggle is checked, coverage painting will accumulate, when it is unchecked paint values will be constrained to the Brush Opacity value.

Cubemap Export

Clicking the Cubemap Export button in the Coverage Editor will render a new cubemap from the current camera and save it to your Assets folder.

Table of Contents

About kode80 Clouds	4
kode80 Clouds License Details	5
Clouds Properties	6
Render	6
Target Camera	6
Sub Pixel Size	6
Max Iterations	6
Render Size	6
Fixed Width/Height	7
Downsample	7
Coverage	7
Cloud Coverage	7
Coverage Offset	7
Horizon Coverage Start/End	8
Lighting	8
Cloud Base/Top Color	8
Sun Light	8
Sun/Ambient Scalar	8
Sun Ray Length	8
Cone Radius	9
Density	9
Forward/Backward Scattering G	9
Dark Outline Scalar	9

Animation	9
Animation Scale	9
Coverage Offset Per Frame X/Y	10
Base Offset Per Frame X/Y/Z	10
Detail Offset Per Frame X/Y/Z	10
Modeling (Base)	10
Base Scale	10
Cloud Gradient 1/2/3	10
Sample Scalar	11
Sample Threshold	11
Cloud Bottom Fade	11
Modeling (Detail)	11
Detail Scale	11
Erosion Edge Size	12
Cloud Distorion	12
Cloud Distortion Scale	12
Optimization	12
LOD Distance	12
Horizon Level	13
Horizon Fade	13
Horizon Fade Start Alpha	13
Atmosphere	13
Horizon Distance	13
Atmosphere Start/End Height	14
Camera Position Scalar	14

Cloud Shadows	15
Coverage Editor	16
Editor Modes	16
Editor Properties	16
Editor Camera	16
Brush Properties	17
Cubemap Export	17