tf.compat.v1.random_uniform_initializer Stay organized with collections Save and categorize content based on your preferences.

https://www.tensorflow.org/api_docs/python/tf/compat/v1/random_uniform_initializer

> *Initializer that generates tensors with a uniform distribution.*

Function Signatures

```
tf.compat.v1.random_uniform_initializer( minval=0.0,
maxval=None, seed=None, dtype=tf.dtypes.float32 )
```

Code Examples

```
tf.compat.v1.random_uniform_initializer(
minval=0.0,
maxval=None,
seed=None,
dtype=tf.dtypes.float32
)
```

```
tf.compat.v1.random_uniform_initializer(
minval=0.0,
maxval=None,
seed=None,
dtype=tf.dtypes.float32
)
```

```
tf.dtypes.float32
```

```
initializer = tf.compat.v1.random_uniform_initializer(
minval=minval,
maxval=maxval,
seed=seed,
dtype=dtype)
weight_one = tf.Variable(initializer(shape_one))
weight_two = tf.Variable(initializer(shape_two))
```

```
initializer = tf.compat.v1.random_uniform_initializer(
minval=minval,
maxval=maxval,
seed=seed,
dtype=dtype)
weight_one = tf.Variable(initializer(shape_one))
weight_two = tf.Variable(initializer(shape_two))
```

```
initializer = tf.initializers.RandomUniform(
minval=minval,
maxval=maxval,
seed=seed)
weight_one = tf.Variable(initializer(shape_one, dtype=dtype))
weight_two = tf.Variable(initializer(shape_two, dtype=dtype))
```

```
initializer = tf.initializers.RandomUniform(
minval=minval,
maxval=maxval,
seed=seed)
weight_one = tf.Variable(initializer(shape_one, dtype=dtype))
weight_two = tf.Variable(initializer(shape_two, dtype=dtype))
```

```
@classmethod
from_config(
config
)
```

Documentation

Initializer that generates tensors with a uniform distribution.

View aliases

Compat aliases for migration

See
Migration guide for
more details.

tf.compat.v1.initializers.random_uniform

Migrate to TF2

Although it is a legacy compat.v1 API, this symbol is compatible with eager execution and tf.function.

To switch to TF2, switch to using either

tf.initializers.RandomUniform or tf.keras.initializers.RandomUniform
(neither from compat.v1) and
pass the dtype when calling the initializer. Keep in mind that
the default minval, maxval and the behavior of fixed seeds have changed.

Structural Mapping to TF2

Before:

After:

How to Map Arguments

Description

Methods

from_config

View source

Instantiates an initializer from a configuration dictionary.

Example:

get_config

View source

Returns the configuration of the initializer as a JSON-serializable dict.

__call__

View source

Returns a tensor object initialized as specified by the initializer.