

tf.compat.v1.zeros_initializer Stay organized with collections Save and categorize content based on your preferences.

https://www.tensorflow.org/api_docs/python/tf/compat/v1/zeros_initializer

Initializer that generates tensors initialized to 0.

Function Signatures

```
tf.compat.v1.zeros_initializer( dtype=tf.dtypes.float32 )
```

Code Examples

```
tf.compat.v1.zeros_initializer(  
dtype=tf.dtypes.float32  
)
```

```
tf.compat.v1.zeros_initializer(  
dtype=tf.dtypes.float32  
)
```

```
tf.dtypes.float32
```

```
initializer = tf.compat.v1.zeros_initializer(dtype=tf.float32)
variable = tf.Variable(initializer(shape=[3, 3]))
```

```
initializer = tf.compat.v1.zeros_initializer(dtype=tf.float32)
variable = tf.Variable(initializer(shape=[3, 3]))
```

```
initializer = tf.zeros_initializer()
variable = tf.Variable(initializer(shape=[3, 3], dtype=tf.float32))
```

```
initializer = tf.zeros_initializer()
variable = tf.Variable(initializer(shape=[3, 3], dtype=tf.float32))
```

```
initializer = tf.compat.v1.zeros_initializer(dtype=tf.float32)
tf.Variable(initializer(shape=[3])).numpy()
array([0., 0., 0.], dtype=float32)
tf.Variable(initializer(shape=[3, 3])).numpy()
array([[0., 0., 0.],
       [0., 0., 0.],
       [0., 0., 0.]], dtype=float32)
initializer = tf.compat.v1.zeros_initializer()
tf.Variable(initializer(shape=[3], dtype=tf.float32)).numpy()
array([0., 0., 0.], dtype=float32)
tf.Variable(initializer(shape=[3, 3], dtype=tf.float32)).numpy()
array([[0., 0., 0.],
       [0., 0., 0.],
       [0., 0., 0.]], dtype=float32)
```

Documentation

Initializer that generates tensors initialized to 0.

View aliases

Compat aliases for migration

See

Migration guide for
more details.

`tf.compat.v1.initializers.zeros`

Migrate to TF2

`tf.compat.v1.zeros_initializer` is compatible with eager execution and `tf.function`.

To migrate to TF2, please use `tf.zeros_initializer` instead. The `dtype` argument in `tf.compat.v1.zeros_initializer.init_()` does not exist in `tf.zeros_initializer.init_()`. However, you can specify the `dtype` in `__call__()` in both cases.

Structural Mapping to TF2

Before:

After:

How to Map Arguments

Before & After Usage Example

Before:

After:

Description

Used in the notebooks

- Migrating model checkpoints

Methods

from_config

[View source](#)

Instantiates an initializer from a configuration dictionary.

Example:

get_config

[View source](#)

Returns the configuration of the initializer as a JSON-serializable dict.

__call__

[View source](#)

Returns a tensor object initialized as specified by the initializer.