

ParametrizationList#

<https://pytorch.org/docs/stable/generated/torch.nn.utils.parametrize.ParametrizationList.html>

Description:

A sequential container that holds and manages the original parameters or buffers of a parametrized `torch.nn.Module`. It is the type of `module.parametrize[tensor_name]` when `module[tensor_name]` has been parametrized with `register_parametrization()`. If the first registered parametrization has a `right_inverse` that returns one tensor or does not have a `right_inverse` (in which case we assume that `right_inverse` is the identity), it will hold the tensor under the name `original`. If it has a `right_inverse` that returns more than one tensor, these will be registered as `original0`, `original1`, ... This class is used internally by `register_parametrization()`. It is documented here for completeness. It shall not be instantiated by the user.

Function Signature

```
class  
torch.nn.utils.parametrize.ParametrizationList(modules,  
original, unsafe=False)[source]#
```

Parameters

```
right_inverse(value)[source]#
```

Parameters

Notes & Warnings

WARNING

Warning This class is used internally by `register_parametrization()`. It is documented here for completeness. It shall not be instantiated by the user.

Detailed Documentation

Documentation

A sequential container that holds and manages the original parameters or buffers of a parametrized `torch.nn.Module`.

It is the type of `module.parametrizations[tensor_name]` when `module[tensor_name]` has been parametrized with `register_parametrization()`.

If the first registered parametrization has a `right_inverse` that returns one tensor or does not have a `right_inverse` (in which case we assume that `right_inverse` is the identity), it will hold the tensor under the name `original`. If it has a `right_inverse` that returns more than one tensor, these will be registered as `original0`, `original1`, ...

This class is used internally by `register_parametrization()`. It is documented here for completeness. It shall not be instantiated by the user.

`modules (sequence)` – sequence of modules representing the parametrizations

`original (Parameter or Tensor)` – parameter or buffer that is parametrized

`unsafe (bool)` – a boolean flag that denotes whether the parametrization may change the dtype and shape of the tensor. Default: False Warning: the parametrization is not checked for consistency upon registration. Enable this flag at your own risk.

Call the `right_inverse` methods of the parametrizations in the inverse registration order.

Then, it stores the result in `self.original` if `right_inverse` outputs one tensor or in `self.original0`, `self.original1`, ... if it outputs several.

`value (Tensor)` – Value to which initialize the module