

torch.column_stack#

https://pytorch.org/docs/stable/generated/torch.column_stack.html

Description:

Creates a new tensor by horizontally stacking the tensors in tensors. Equivalent to `torch.hstack(tensors)`, except each zero or one dimensional tensor `t` in tensors is first reshaped into a `(t.numel(), 1)` column before being stacked horizontally. tensors (sequence of Tensors) – sequence of tensors to concatenate out (Tensor, optional) – the output tensor.

Function Signature

```
torch.column_stack(tensors, *, out=None) → Tensor#
```

Parameters

Keyword Arguments

Parameters

Keyword

out (Tensor, optional) – the output tensor.

Code Examples

```
>>> a = torch.tensor([1, 2, 3])
>>> b = torch.tensor([4, 5, 6])
>>> torch.column_stack((a, b))
tensor([[1, 4],
        [2, 5],
        [3, 6]])
>>> a = torch.arange(5)
>>> b = torch.arange(10).reshape(5, 2)
>>> torch.column_stack((a, b, b))
tensor([[0, 0, 1, 0, 1],
        [1, 2, 3, 2, 3],
        [2, 4, 5, 4, 5],
        [3, 6, 7, 6, 7],
        [4, 8, 9, 8, 9]])
```

Detailed Documentation

Documentation

Creates a new tensor by horizontally stacking the tensors in tensors.

Equivalent to `torch.hstack(tensors)`, except each zero or one dimensional tensor `t` in `tensors` is first reshaped into a `(t.numel(), 1)` column before being stacked horizontally.

`tensors` (sequence of Tensors) – sequence of tensors to concatenate

`out` (Tensor, optional) – the output tensor.

Creates a new tensor by horizontally stacking the tensors in tensors.

Equivalent to `torch.hstack(tensors)`, except each zero or one dimensional tensor `t` in `tensors` is first reshaped into a `(t.numel(), 1)` column before being stacked horizontally.

`tensors` (sequence of Tensors) – sequence of tensors to concatenate

`out` (Tensor, optional) – the output tensor.