

torch.randperm#

<https://pytorch.org/docs/stable/generated/torch.randperm.html#torch.randperm>

Description:

Returns a random permutation of integers from 0 to $n - 1$. n (int) – the upper bound (exclusive) generator (torch.Generator, optional) – a pseudorandom number generator for sampling out (Tensor, optional) – the output tensor. dtype (torch.dtype, optional) – the desired data type of returned tensor. Default: torch.int64.

Function Signature

```
torch.randperm(n, *, generator=None, out=None,
dtype=torch.int64, layout=torch.strided, device=None,
requires_grad=False, pin_memory=False) → Tensor#
```

Parameters

Keyword Arguments

Parameters

Keyword

generator (torch.Generator, optional) – a pseudorandom number generator for sampling out (Tensor, optional) – the output tensor. dtype (torch.dtype, optional) – the desired data type of returned tensor. Default: torch.int64. layout (torch.layout, optional) – the desired layout of returned Tensor. Default: torch.strided. device (torch.device, optional) – the desired device of returned tensor. Default: if None, uses the current device for the default tensor type (see torch.set_default_device()). device will be the CPU for CPU tensor types and the current CUDA device for CUDA tensor types. requires_grad (bool, optional) – If autograd should record operations on the returned tensor. Default: False. pin_memory (bool, optional) – If set, returned tensor would be allocated in the pinned memory. W

Code Examples

```
>>> torch.randperm(4)
tensor([2, 1, 0, 3])
```

Detailed Documentation

Documentation

Returns a random permutation of integers from 0 to $n - 1$.

`n` (int) – the upper bound (exclusive)

`generator` (torch.Generator, optional) – a pseudorandom number generator for sampling

`out` (Tensor, optional) – the output tensor.

`dtype` (torch.dtype, optional) – the desired data type of returned tensor. Default: torch.int64.

`layout` (torch.layout, optional) – the desired layout of returned Tensor. Default: torch.strided.

`device` (torch.device, optional) – the desired device of returned tensor. Default: if None, uses the current device for the default tensor type (see torch.set_default_device()). device will be the CPU for CPU tensor types and the current CUDA device for CUDA tensor types.

`requires_grad` (bool, optional) – If autograd should record operations on the returned tensor. Default: False.

`pin_memory` (bool, optional) – If set, returned tensor would be allocated in the pinned memory. Works only for CPU tensors. Default: False.

