

Totally Integrated Automation Portal

FC_OutputInterface [FC2]

FC_OutputInterface Properties

General

Name	FC_OutputInterface	Number	2	Type	FC	Language	LAD
Numbering	Manual						

Information

Title		Author		Comment		Family	
Version	0.1	User-defined ID					

Name	Data type	Default value	Comment
Input			
Output			
InOut			
Temp			
Constant			
▼ Return			
FC_OutputInterface	Void		

Network 1:

0001

// RB155 I/O

0002

0003

// Outputs

0004

"RB155_MotorFordward" := "DB_Global".RB155.ACT.MotorFordward;

0005

"RB155_MotorBackward" := "DB_Global".RB155.ACT.MotorBackward;

0006

0007

// RB156 I/O

0008

0009

// Drive output telegram

0010

"RB156_ControlWord" := "DB_Global".RB156.DRIVE.ControlWord;

0011

"RB156_SpeedReference" := "DB_Global".RB156.DRIVE.SpeedReference;

0012

0013

// RB157 I/O

0014

0015

// Outputs

0016

"RB157_MotorFordward" := "DB_Global".RB157.ACT.MotorFordward;

0017

"RB157_MotorBackward" := "DB_Global".RB157.ACT.MotorBackward;

0018

0019

// RB158 I/O

0020

0021

// Outputs

0022

"RB158_MotorFordward" := "DB_Global".RB158.ACT.MotorFordward;

0023

"RB158_MotorBackward" := "DB_Global".RB158.ACT.MotorBackward;

0024

0025

// E156 I/O

0026

0027

// Outputs

0028

"E156_CloseBlocks" := "DB_Global".E156.ACT.CloseBlocks;

0029

"E156_OpenBlocks" := "DB_Global".E156.ACT.OpenBlocks;

0030

0031

// Drive output telegram

0032

"DB_Global".E156.DRIVE.ControlWord := "E156_ControlWord";

0033

"DB_Global".E156.DRIVE.SetPosition := "E156_SetPosition";

0034

"DB_Global".E156.DRIVE.SpeedReference := "E156_SpeedReference";