

# PROCEDURE TO DEPLOY IMAGE(OPERATING SYSTEM) INTO COMPUTERS.

#### NEED TO ARRANGE BELOW TWO EQUIPMENT FOR TEMPORARY.



REQUIRED ONE WORKING SYSTEM.



REQUIRED ONE PEN DRIVE (MINIMUM 8 GB).

#### DOWNLOAD THE MEDIA CREATION TOOL FROM MENTIONED URL.


https://www.microsoft.com/en-us/software-download/windows10

#### Create Windows 10 installation media

To get started, you will first need to have a licence to install Windows 10. You can then download and run the media creation tool. For more information on how to use the tool, see the instructions below.

Download tool now







#### DOUBLE CLICK ON THIS TO OPEN THE SETUP.




#### CLICK ON ACCEPT.



## CHOOSE CREATE INSTALLATION MEDIA AND CLICK ON NEXT.




CHOOSE THE BELOW
DETAILS &
UNCHECK THE
RECOMMENDED
OPTION AND CLICK
ON NEXT.




CONNECT THE PEN DRIVE INTO TEMPORARY COMPUTER.



### CHOOSE USB FLASH DRIVE & CLICK ON NEXT.



### SELECT YOUR PEN DRIVE & THEN CLICK ON NEXT.



IT WILL TAKE FEW
MINUTES TO
DOWNLOAD THE
WINDOWS.

Back

Next

#### Downloading Windows 10

Feel free to keep using your PC.

Progress: 2%



#### NOW CLICK ON FINISH & EJECT THE PEN DRIVE.

Mindows 10 Setup

#### Your USB flash drive is ready

F:\



Support Legal

<u>B</u>ack

**Finish** 

#### DEFAULT FUNCTION KEY TO BOOT THE DEVICE FROM PEN DRIVE.

BUT GENERALLY, F12 KEY IS BEING USED TO ENTER THE BIOS SETUP FOR BOOT THE DEVICE BY PEN DRIVE.

Acer and Asus: F2 or Del

Dell: F2 or F12

• HP: ESC or F10

• Lenovo: F1, F2, or Fn + F2

Lenovo ThinkPads: Enter + F1.

MSI: DEL

Microsoft Surface Tablets: Press and hold the volume-up button.

Samsung and Toshiba: F2


• Sony: F1, F2, or F3

#### PRESS F2 FOR BIOS SETUP TO ENABLE THE USB BOOT.


- 1. GO TO BIOS SETUP AND SELECT BOOT TAB.
  2. SET BOOT DEVICE PRIORITY: REMOVABLE DRIVE.
- 3. SET BOOTING OPTION ENABLE SEE IN GIVEN SNAP

Main Advanced Performance Sec Boot Home Type Boot Device Priority	Mornall (Optical Drives) (Hard Disk Drives) (Removable Drive)	Normal allows yo to set boot priority based o type of device.Advanced
Hard Drive Order CD/DUD-ROM Drive Order Removable Drive Order	ISATA: ST1000DX001 ISATA: ST1000DX001 No Optical Drive IGeneric Compact 1 IGeneric SD/MMC 01 IGeneric microSD 1 IGeneric MS/MS-PRI	allows you to se boot priority fo each device regardless of category
Boot to Optical Devices Boot to Removable Devices Boot to Network USB Boot Boot USB Devices First UEFI Boot	(Enable) (Enable) (Disable) (Enable) (Enable) (Enable)	
		: Select Scre


NOW CONNECT THE PEN DRIVE INTO TARGET SYSTEM TO DEPLOY THE IMAGE & RESTART THE COMPUTER AND PRESS & RELEASE F12 KEY CONTINUOUSLY TILL TO ENTER THE BIOS SETUP.



NOW SELECT YOUR PEN DRIVE BY USING UP & DOWN ARROW IN KEYBOARD AND PRESS ENTER.




NOW WINDOWS ICON POPUP WILL COME TO BOOT THE COMPUTER BY PEN DRIVE.




### NOW VERIFY THE LANGUAGE & CLICK ON NEXT.



NOW CLICK ON INSTALL.




NOW ACCEPT AND CLICK ON NEXT, IF YOU ARE GETTING 2<sup>ND</sup>WINDOW THEN CLICK ON, I DON'T HAVE A PRODUCT KEY.








### NOW SELECT CUTOM: INSTALL WINDOWS ONLY (ADVANCED).




NOW SELECT ALL THE PARTITION & DELETE ONE BY ONE, YOU ARE GETTING POP TO CONFIRM THEN CLICK ON OK.









NOW SELECT THE UNALLOCATED PARTITION & CLICK ON NEW AND THEN APPLY TO CREATE DRIVE, IT'S GETTING POP TO CONFIRM THEN CLICK ON OK.






NOW SELECT THE PRIMARY PARTITION & CLICK ON FORMAT, IT'S GETTING POP TO CONFIRM THEN CLICK ON OK.

NOW SELECT THE PRIMARY PARTITION & CLICK ON NEXT TO INSTALL THE OPERATING SYSTEM.




NOW WINDOWS IS
INSTALLING, ONCE IT IS
COMPLETED THEN
SYSTEM WILL BE
RESTARTED
AUTOMATICALLY.




NOW IT WILL TAKE SOMETIMES TO GETTING READY, PLEASE WAIT TILL THE DEVICE READY.




NOW CHOOSE YOUR REGION & CLICK ON YES.




### NOW CHOOSE YOUR KEYBOARD LAYOUT & CLICK ON YES.




### NOW YOU CAN SKIP THE SECOND KEYBOARD LAYOUT.




IF YOU DON'T HAVE
INTERNET, THEN CLICK
ON "I DON'T HAVE
INTERNET" AND FOLLOW
THE SCREEN
INSTRUCTION.



NOW CLICK ON CONTINUE WITH LIMITED SETUP FROM LEFT PANE.




NOW CREATE YOUR NEW LOCAL USER & CLICK ON NEXT.



NOW CREATE & CONFIRM
THE PASSWORD FOR LOCAL
USER & CLICK ON NEXT.





NOW CREATE THE SECURITY QUESTION FOR THIS ACCOUNT & CLICK ON NEXT.







### NOW CLICK ON ACCEPT TO CONFIRM THE PRIVACY SETTING.



### NOW CLICK ON ACCEPT TO CONFIRM CORTANA SETTING.



NOW SYSTEM IS GETTING READY, IT WILL TAKE FEW MINUTES.



#### NOW YOUR DESKTOP IS READY.



NOTE: IF YOU HAVE
INTERNET
PLEASE
CONNECT WITH
WIFI NETWORK
AND CLICK ON
"NEXT".



SELECT THE TAB
SET UP FOR AN
ORGANIZATION,
CLICK NEXT




TYPE
DEVICEADMIN USER NAME
AND PASSWORD
UESR NAME:

DEVICEADMIN@QUICKPART S.COM

PASSWORD: ADMIN@8891, CLICK NEXT



ENTER PASSWORD CLICK NEXT



ONCE USER'S DEVICE IS
CONNECTED TO AZURE AD
BELOW APPLICATIONS WILL
BE INSTALLED
AUTOMATICALLY.

Azure VPN Client  Box for Office  Box Tools  Microsoft Office (32 bit)  Google Chrome	Quickparts Pre-Installed Applications for all Ma	achines
Box Tools Microsoft Office (32 bit) Google Chrome	Azure VPN Client	
Microsoft Office (32 bit) Google Chrome	Box for Office	
Google Chrome	Box Tools	
	Microsoft Office (32 bit)	
And within projection	Google Chrome	
Adobe Reader	Adobe Reader	
Box Drive	Box Drive	



YOU MAY CALL OR RAISE THE TICKET TO SERVICEDESK FOR ENROLL & REGISTERE THE DEVICE WITH AZURE ACTIVE DIRECOTRY.



SEND MAIL TO:itdesk@quickparts.com

#### THANK YOU...!

