

Entity	Attribute	Equivalence partitions
Account	Username	31-MAX INTEGER (Invalid)
		1-30 (Valid)
		0 (Invalid)

	Positive: List of test case values	1, 2, 15, 29, 30
	Negative: List of test case values	0, 31, 32, 100
	Edge cases	Null
		Empty string
		Blank space: " "
		Duplicate username

Entity	Attribute	Equivalence partitions
Footer	Header	51-MAX INTEGER (Invalid)
		4-50 (Valid)
		1-3 (Invalid)
		0 (Invalid)
	Positive: List of test case values	4, 5, 30, 49, 50
	Negative: List of test case values	0, 1, 2, 3, 51, 52, 75
	Edge cases	Null
		Empty string
		Blank space: " "

Entity	Attribute	Equivalence partitions
Game	Name	101-MAX INTEGER (Invalid)
		1-100 (Valid)
		0 (Invalid)
	Positive: List of test case values	1, 2, 25, 99, 100
	Negative: List of test case values	0, 101, 102, 150
	Edge cases	Null
		Empty string
		Blank space: " "
		Duplicate game name

Entity	Attribute	Equivalence partitions
Header	Text	81-MAX INTEGER (Invalid)
		1-80 (Valid)
		0 (Invalid)

	Positive: List of test case values	1, 2, 25, 79, 80
	Negative: List of test case values	0, 81, 82, 120
	Edge cases	Null
		Empty string
		Blank space: " "

Entity	Attribute	Equivalence partitions
Information	Description	501-MAX INTEGER (Invalid)
		10-500 (Valid)
		1-9 (Invalid)
		0 (Invalid)
	Positive: List of test case values	10, 11, 50, 499, 500
	Negative: List of test case values	0, 1, 2, 5, 8, 9, 501, 502, 600
	Edge cases	Null
		Empty string
		Blank space: " "

Entity	Attribute	Equivalence partitions
License	Username	31-MAX INTEGER (Invalid)
		1-30 (Valid)
		0 (Invalid)

	Positive: List of test case values	1, 2, 25, 29, 30
	Negative: List of test case values	0, 31, 32, 100
	Edge cases	Null
		Empty string
		Blank space: " "
		Duplicate license username

Entity	Attribute	Equivalence partitions
QA	Question	256-MAX INTEGER (Invalid)
		1-255 (Valid)
		0 (Invalid)
	Positive: List of test case values	1, 2, 25, 254, 255
	Negative: List of test case values	0, 256, 257, 300

	Edge cases	Null
		Empty string
		Blank space: " "
		Question mark only

Entity	Attribute	Equivalence partitions
Role	Name	VALID ENUM VALUES
		INVALID ENUM VALUES
	Positive: List of test case values	NONE, REGULAR, ADMIN
	Negative: List of test case values	admin, SUPER_ADMIN, USER
	Edge cases	Null
		Empty string
		Blank space: " "

Entity	Attribute	Equivalence partitions
Todo	Date	VALID LOCALDATE
		String (Invalid)
		Nonexistent month (Invalid)
		Nonexistent day (Invalid)
		Non-leap year date (Invalid)
	Positive: List of test case values	2009-01-01, 2026-05-05, 2099-12-12
	Negative: List of test case values	"02-02/2023", 2023-13-01, 2023-01-32, 2023-02-29
	Edge cases	Null
		Leap year valid: 2024-02-29
		Past date
		Future date

Test case values	Boundary values	Test case values
100	31, MAX INTEGER	30, 31, 32
15	1, 30	0, 1, 2, 29, 30, 31
0	0	0, 1

Test case values	Boundary values	Test case values
75	51, MAX INTEGER	50, 51, 52
30	4, 50	3, 4, 5, 49, 50, 51
2	1, 3	0, 1, 2, 2, 3, 4
0	0	0, 1

Test case values	Boundary values	Test case values
150	101, MAX INTEGER	100, 101, 102
25	1, 100	0, 1, 2, 99, 100, 101
0	0	0, 1

Test case values	Boundary values	Test case values
120	81, MAX INTEGER	80, 81, 82
25	1, 80	0, 1, 2, 79, 80, 81
0	0	0, 1

Test case values	Boundary values	Test case values
600	501, MAX INTEGER	500, 501, 502
50	10, 500	9, 10, 11, 499, 500, 501
5	1, 9	0, 1, 2, 8, 9, 10
0	0	0, 1

Test case values	Boundary values	Test case values
100	31, MAX INTEGER	30, 31, 32
25	1, 30	0, 1, 2, 29, 30, 31
0	0	0, 1

Test case values	Boundary values	Test case values
300	256, MAX INTEGER	255, 256, 257
25	1, 255	0, 1, 2, 254, 255, 256
0	0	0, 1

[illegible][illegible]

Entity	Attribute	Equivalence partitions
Account	Password	129-MAX INTEGER (Invalid)
		8-128 (Valid)
		1-7 (Invalid)
		0 (Invalid)
	Positive: List of test case values	8, 9, 25, 127, 128
	Negative: List of test case values	0, 1, 2, 4, 6, 7, 129, 130, 200
	Edge cases	Null
		Empty string
		Blank space: " "
		All spaces: " "

Entity	Attribute	Equivalence partitions
Footer	Description	256-MAX INTEGER (Invalid)
		10-255 (Valid)
		1-9 (Invalid)
		0 (Invalid)
	Positive: List of test case values	10, 11, 50, 254, 255
	Negative: List of test case values	0, 1, 2, 5, 8, 9, 256, 257, 300
	Edge cases	Null
		Empty string
		Blank space: " "

Entity	Attribute	Equivalence partitions
Information	ImportanceLevel	VALID ENUM VALUES
		INVALID ENUM VALUES

	Positive: List of test case values	LOW, MEDIUM, HIGH
	Negative: List of test case values	low, URGENT, CRITICAL
	Edge cases	Null
		Empty string
		Blank space: " "

Entity	Attribute	Equivalence partitions
License	Password	129-MAX INTEGER (Invalid)
		8-128 (Valid)
		1-7 (Invalid)
		0 (Invalid)
	Positive: List of test case values	8, 9, 25, 127, 128
	Negative: List of test case values	0, 1, 2, 4, 6, 7, 129, 130, 200
	Edge cases	Null
		Empty string
		Blank space: " "
		All spaces: " "

Entity	Attribute	Equivalence partitions
QA	Answer	1001-MAX INTEGER (Invalid)
		1-1000 (Valid)
		0 (Invalid)
	Positive: List of test case values	1, 2, 25, 999, 1000
	Negative: List of test case values	0, 1001, 1002, 1500

	Edge cases	Null
		Empty string
		Blank space: " "

Entity	Attribute	Equivalence partitions
Todo	Description	256-MAX INTEGER (Invalid)
		1-255 (Valid)
		0 (Invalid)

	Positive: List of test case values	1, 2, 25, 254, 255
	Negative: List of test case values	0, 256, 257, 300
	Edge cases	Null
		Empty string
		Blank space: " "

Test case values	Boundary values	Test case values
LOW	N/A	LOW, MEDIUM, HIGH
low	N/A	low, URGENT, CRITICAL

Test case values	Boundary values	Test case values
200	129, MAX INTEGER	128, 129, 130
25	8, 128	7, 8, 9, 127, 128, 129
4	1, 7	0, 1, 2, 6, 7, 8
0	0	0, 1

Test case values	Boundary values	Test case values
1500	1001, MAX INTEGER	1000, 1001, 1002
25	1, 1000	0, 1, 2, 999, 1000, 1001
0	0	0, 1

Entity	Attribute	Equivalence partitions
License	Email	255-MAX INTEGER (Invalid)
		6-254 (Valid)
		1-5 (Invalid)
		0 (Invalid)
	Positive: List of test case values	6, 7, 60, 253, 254
	Negative: List of test case values	0, 1, 2, 3, 4, 5, 255, 256, 300
	Edge cases	Null
		Empty string
		Blank space: " "
		Invalid email format
		Duplicate email

Entity	Attribute	Equivalence partitions
Todo	Status	VALID ENUM VALUES
		INVALID ENUM VALUES

	Positive: List of test case values	PENDING, IN_PROGRESS, COMPLETED
	Negative: List of test case values	pending, DONE, CANCELLED
	Edge cases	Null
		Empty string
		Blank space: " "

[illegible]

Entity	Attribute	Equivalence partitions
License	pcNumber	21-MAX INTEGER (Invalid)
		0-20 (Valid)
		MIN INTEGER-(-1) (Invalid)
	Positive: List of test case values	0, 1, 10, 19, 20
	Negative: List of test case values	-20, -2, -1, 21, 22, 100
	Edge cases	Null
		String
		Decimal
		Emoji

Entity	Attribute	Equivalence partitions
Todo	Source	VALID ENUM VALUES
		INVALID ENUM VALUES

	Positive: List of test case values	GAMEHUB, STORE
	Negative: List of test case values	gamehub, WEB, MOBILE
	Edge cases	Null
		Empty string
		Blank space: " "

[illegible]

Entity	Attribute	Equivalence partitions
Todo	DoneBy	31-MAX INTEGER (Invalid)
		1-30 (Valid)
		0 (Invalid)

	Positive: List of test case values	1, 2, 15, 29, 30
	Negative: List of test case values	0, 31, 32, 100
	Edge cases	Null
		Empty string
		Blank space: " "

