

Module 14 - chapter 2

Install Boto3 and connect to AWS

To install Boto3 we need to use **pip** because it is an external library -> <https://pypi.org/project/boto3/>

boto3 1.43.40

✓ Latest release

Released: Jul 3, 2026

The AWS SDK for Python

Navigation

Project description

Release history

Download files

Verified details

These details have been verified by PyPI

Maintainers

aws

Unverified details

These details have not been verified by PyPI

Project description

python 3.10 | 3.11 | 3.12 | 3.13 | 3.14

license Apache-2.0

Boto3 is the Amazon Web Services (AWS) Software Development Kit (SDK) for Python, which allows Python developers to write software that makes use of services like Amazon S3 and Amazon EC2. You can find the latest, most up to date, documentation at our [doc site](#), including a list of services that are supported.

Boto3 is maintained and published by [Amazon Web Services](#).

Boto (pronounced boh-toh) was named after the fresh water dolphin native to the Amazon river. The name was chosen by the author of the original Boto library, Mitch Garnaat, as a reference to the company.

Notices


On 2026-04-29, support for Python 3.9 ended for Boto3. This follows the Python Software Foundation [end of support](#) for the runtime which occurred on 2025-10-31.

For more information on deprecations, see this [blog post](#).

-> pip install boto3

```
Terminal zsh (/usr/local/bin/zsh) × + - AI Agents
> pip install boto3
Collecting boto3
  Downloading boto3-1.43.40-py3-none-any.whl.metadata (6.6 kB)
Collecting botocore<1.44.0,>=1.43.40 (from boto3)
  Downloading botocore-1.43.40-py3-none-any.whl.metadata (5.6 kB)
Collecting jmespath<2.0.0,>=0.7.1 (from boto3)
  Downloading jmespath-1.1.0-py3-none-any.whl.metadata (7.6 kB)
Collecting s3transfer<0.20.0,>=0.19.0 (from boto3)
  Downloading s3transfer-0.19.0-py3-none-any.whl.metadata (1.7 kB)
Collecting python-dateutil<3.0.0,>=2.1 (from botocore<1.44.0,>=1.43.40->boto3)
  Downloading python_dateutil-2.9.0.post0-py2.py3-none-any.whl.metadata (8.4 kB)
Collecting urllib3!=2.2.0,<3,>=1.25.4 (from botocore<1.44.0,>=1.43.40->boto3)
  Using cached urllib3-2.7.0-py3-none-any.whl.metadata (6.9 kB)
Collecting six>=1.5 (from python-dateutil<3.0.0,>=2.1->botocore<1.44.0,>=1.43.40->boto3)
  Downloading six-1.17.0-py2.py3-none-any.whl.metadata (1.7 kB)
Downloaded boto3-1.43.40-py3-none-any.whl (140 kB)
Downloaded botocore-1.43.40-py3-none-any.whl (15.3 MB)
15.3/15.3 MB 33.1 MB/s 0:00:00
Downloaded jmespath-1.1.0-py3-none-any.whl (20 kB)
Downloaded python_dateutil-2.9.0.post0-py2.py3-none-any.whl (229 kB)
Downloaded s3transfer-0.19.0-py3-none-any.whl (90 kB)
Using cached urllib3-2.7.0-py3-none-any.whl (131 kB)
Downloaded six-1.17.0-py2.py3-none-any.whl (11 kB)
Installing collected packages: urllib3, six, jmespath, python-dateutil, botocore, s3transfer, boto3
Successfully installed boto3-1.43.40 botocore-1.43.40 jmespath-1.1.0 python-dateutil-2.9.0.post0 s3transfer-0.19.0 six-1.17.0 urllib3-2.7.0
```

And we check the external libraries folder and there it is:



Next, we want to connect from python to AWS like we did with TF so we need to authenticate to AWS and for that we need to provide credentials




We will use the same 'admin' user as we did for TF. 'Admin' user has full permissions.

So when we configure aws using
-> aws configure

We got:

- credentials folder holding -> secret key-pair
- Config folder holding default region and output format (json)

```
nana@macbook /Users/nana
% ls ~/.aws
config      credentials
nana@macbook /Users/nana
% aws configure
```



So we are good to go!

Boti will automatically take these credentials and the default region to connect to AWS and authenticate with it.

```
nana@macbook /Users/nana
% ls ~/.aws
config      credentials
nana@macbook /Users/nana
% aws configure
```

