RUCKUS One Online Help (index.html)

Search Q

Adding and Managing a Custom Role

You can create a custom role and set various permissions to enable administrators to manage devices through the role. By default, system-defined roles are also available which can be assigned to administrators.

For more information, refer to the various administrator roles at *Understanding Administrator Roles* and *Privileges (GUID-1EB23842-21DF-4A2A-8017-2E70E99511A7.html)*.

To access this feature, you must enable Early-Access. Please refer to *Enabling or Disabling RUCKUS One Early Access Features (GUID-406F16F2-39F0-4426-AA80-C15B09CFF494.html)* for more information.

Create a customer role as follows:

- 1. On the RUCKUS One web interface, navigate to **Administration** > (and then)**Account Management** > (and then)**Users & Privileges**.
- 2. Click the Roles sub-tab.

The following information is displayed:

- Name: Displays the name of the role.
- Description: Displays a description of the role.
- Role Type: Displays whether the role is system-defined or custom.

Creating a Custom Role



3. Click Add Role.

The Add Admin Role page is displayed.

4. In the **General** section, type the role name and a short description for the role.

Note: You cannot create a custom role with the same name as a system-defined role.

- 5. Click Next.
- 6. In the **Permissions** section, select permissions to manage various devices such as **Wi-Fi**, **Wired**, and **RUCKUS Edge**.

Management Scope for Permissions

Wi-Fi	Venue Management Al Assurance Access Points Wi-Fi Networks Wireless Clients Wi-Fi Network Control Wi-Fi Reports Wi-Fi Version Management
Wired	Venue Management Switches Wired Clients Switch Network Control Switch Reports Switch Version Management


RUCKUS Edge	Venue Management RUCKUS Edge Devices
	RUCKUS Edge Network Control RUCKUS Edge Version Management

Hover your cursor over the icon for information on device management options. You can set

the following permissions for each device:

- Read (set by default): Allows the user to only view items.
- Create: Allows the user to create a new item.
- Update: Allows the user configure an existing item.
- Delete: Allows the user to delete an item.

Custom Role: Permissions for Device Management



7. Click Next.

The **Summary** section is displayed, providing details about the administrator role. Verify this information.

8. Click Add.

The newly created custom role is added to the list of roles in the **Roles** tab. A notification is displayed on the **Activities** page accessible via the corner of the RUCKUS

One web interface.

You can edit and delete custom roles by selecting the role and clicking **Edit** or **Delete**, respectively. You cannot edit or delete system-defined roles. A notification appears on the **Activities** page whenever a role is edited or deleted.

800-73730-001 Rev E 29 May 2025 © 2024 CommScope, Inc. All rights reserved.