
Object-Oriented Design

Design Patterns: Low Coupling, High Cohesion
& Controller

Zhiming Liu zhimingliu880swu.edu.cn


Centre for Research and Innovation of Software Engineering School of Computer and Information Science Southwest University, Chongqing, China

An Alternative Design?




No association between POST and Payment

No association between POST and Payment



No association between POST and Payment



Need to add an association between POST and Payment, but

Coupling

- ► Coupling is a measure of how strongly one class is connected to or relies upon other classes
- A class with low coupling is not dependent on too many other classes.
- ► High coupling is not desirable

Low Coupling Pattern

Pattern Name: Low Coupling

Solution: Assign a responsibility so that coupling remains low

Problem: How to support low dependency an increased reuse?


- Consider the classes Payment, CashDesk and Sale in POST
- Assume we need to create a *Payment* instance and associate it with the *Sale*.
- ▶ Who should be responsible for this, *CashDesk* or *Sale*?

If the CashDesk

In the slides, CashDesk is some times used for class POST in the course notes and the Conceptail Class Diagrams in the Requirements Analysis

If the CashDesk


In the slides, CashDesk is some times used for class POST in the course notes and the Conceptail Class Diagrams in the Requirements Analysis



We need an extra link from *POST* to *Payment* So *Sale* is a better choice!



How about?



CashDesk is the same as POST

Cohesion

Cohesion is a measure of how strongly related and focused the responsibilities of a class are.

- Classes with high cohesion have highly related functionalities, and does not do a tremendous amount of work
- ► They have a small number of methods with simple but highly related functionality
- Classes with low cohesion are not desirable

High Cohesion Pattern

Good OOD is to assign responsibilities to classes that

- ▶ Are naturally and strongly related to the responsibilities, and
- Every class has something to do but does not have too much to do.

Pattern Name: High Cohesion

Solution: Assign a responsibility so that cohesion remains high

Problem: How to keep complexity manageable?

High coupling also contributes to low cohesion!

Example

- CashDesk can take on part of the responsibility for carrying out the cashPay()
- ▶ But *CashDesk* is used as handling the interface methods, it would better if it does not act as the creator of *Payment*
- ► Thus, a design that delegates the payment creation responsibility to the *Sale* would more cohesive

Note: CashDesk here is POST in the Conceptual Class Diagram

Controller Pattern

Pattern Name: Controller

Solution: Assign the responsibility for handling an input to a class representing one of the following choices:

- Represents the "overall component" (facade controller).
- Represents the overall business (facade controller).
- Represents something in the real-world that is active that might be involved in the task (role controller).
- ► Represents an artificial handler of all input events of a use case, (use-case controller).

Problem: Who should be responsible for handling an external input event?

To design a project

1. Create a separate **object sequence diagram** for **each use case operation** whose **contracts** are defined:

For each use case op(), make a diagram with it as message to the **controller object**.

To design a project

1. Create a separate **object sequence diagram** for **each use case operation** whose **contracts** are defined:

For each use case op(), make a diagram with it as message to the **controller object**.

2. If the diagram gets complex, split it into smaller diagrams.

To design a project

1. Create a separate **object sequence diagram** for **each use case operation** whose **contracts** are defined:

For each use case op(), make a diagram with it as message to the **controller object**.

- 2. If the diagram gets complex, split it into smaller diagrams.
- 3. For some functionality, mostly outputs, may need to create a separate object sequence diagram, e.g. toto()

For these, we need

To design a project

1. Create a separate **object sequence diagram** for **each use case operation** whose **contracts** are defined:

For each use case op(), make a diagram with it as message to the **controller object**.

- 2. If the diagram gets complex, split it into smaller diagrams.
- 3. For some functionality, mostly outputs, may need to create a separate object sequence diagram, e.g. toto()

For these, we need

Use the contracts and conceptual class diagram, and apply the GRASP

To design a project

1. Create a separate **object sequence diagram** for **each use case operation** whose **contracts** are defined:

For each use case op(), make a diagram with it as message to the **controller object**.

- 2. If the diagram gets complex, split it into smaller diagrams.
- 3. For some functionality, mostly outputs, may need to create a separate object sequence diagram, e.g. toto()

For these, we need

- Use the contracts and conceptual class diagram, and apply the GRASP
- ► For each use case, we use a an **interface class** as the controller, following the Controller Pattern