Table des Codes POST : Afficheur 7-Segments Q-Code (55, 53, 0d, C5)

1. Contexte et Description Technique

Manuel de référence des codes hexadécimaux affichés sur l'écran de diagnostic à 7 segments des cartes mères haut de gamme lors de la séquence d'entraînement mémoire.

2. Symptômes Observés sur la Machine

Blocage de la séquence de démarrage sur les codes 55 (Memory Not Installed), 53 (Memory Initialization Error - pas de vitesse compatible), 0d ou C5.

3. Protocole de Diagnostic et Résolution

1. Code 55 : Réinsérer les barrettes ou vérifier la pression de serrage du refroidisseur CPU (trop de pression déforme le socket).

2. Code 53 / 0d : Incompatibilité du profil d'overclocking XMP/EXPO ; utiliser le bouton MemOK! ou FlashBIOS pour mettre à jour le microcode AGESA/ME.

4. Articles et Retours d'Expérience Extraits du Web

Extrait de [ASUS Motherboard Error Codes List Explained - blog.usro.net] :
ASUS Motherboard Error Codes List Explained If your ASUS motherboard is flashing mysterious error codes at you like it’s trying to speak in binary Morse code—don’t panic (yet). These error codes are part of the POST (Power-On Self-Test) diagnostic process built into your motherboard’s BIOS. Understanding them can save you hours of guesswork, unnecessary hardware swapping, or dramatic cries into your CPU cooler. Here’s your comprehensive ASUS motherboard error code list, broken down by categories and what you can do to fix them. ■ What Are ASUS Q-Codes? Q-Codes are two-digit hexadecimal diagnostic codes that appear on higher-end ASUS motherboards (like ROG, TUF, and ProArt lines). They provide real-time status updates during the boot process, helping identify failures quickly. ■ You’ll usually find the Q-Code LED on the motherboard near the 24-pin ATX connector or the bottom-right edge. ■■ Common ASUS Q-Code List ■ Debug LED Color Codes (Entry-Level Boards) If your board doesn’t have Q-Code displays, ASUS often includes Debug LEDs that indicate issues via glowing lights: ➡■ These lights stay on when there’s a problem with the respective component. Use the same process: reseat, swap,...

Extrait de [Troubleshooting ASUS Motherboard Error Q-Codes — Everything ...] :
TABLE OF CONTENTS Has your ASUS motherboard ever given you some numbers or letters (also known as error codes) on that tiny display that’s on there nestled in the corner? Have you ever wondered what it meant? Well, in this article, I’ll explain what they are, how they work, and what you need to look out for with them! What Are Motherboard Error/Debug/Post/Beep Codes? They’re simple codes that tell you if something is wrong with the motherboard or anything attached to it so that you can troubleshoot and fix the problem. They also generally help you figure out what the motherboard is currently doing. Most older or cheaper motherboards usually don’t have any sort of debug code displays, so they resort to beeps instead. Beep codes are usually sequences of high-pitched tones that indicate issues with the motherboard. E.g. 1 long beep and then 2 short beeps indicate a video card memory error on motherboards with American Megatrends (AMI) BIOS. What Are Q-Codes? Q-Codes are ASUS’s name for motherboard debug codes. Other manufacturers have different names for it, but they’re all just debug, or “Error” codes. Still, they aren’t all the same. A code that means one thing on an ASUS motherboar...

Sources Web Associées :

• [SOLVED] - Error 55 (ASUS) on new build | Tom's Hardware Forum (https://forums.tomshardware.com/threads/error-55-asus-on-new-build.3762189/)

• Q-Code "C5" Memory Error - Troubleshooting - Linus Tech Tips (https://linustechtips.com/topic/1580785-q-code-c5-memory-error/)

• Asus QCode Error 53 After Restart. (https://rog-forum.asus.com/t5/gaming-motherboards/asus-qcode-error-53-after-restart/td-p/931606)

Catalogue Visuel : 10 Photos Réelles (06_motherboard_qcode_display)

Ces 10 cas visuels issus du dataset illustrent les motifs caractéristiques de cette classe d'erreur :




Figure 01 — 06_motherboard_qcode_display (Échantillon #1)




Figure 02 — 06_motherboard_qcode_display (Échantillon #2)




Figure 03 — 06_motherboard_qcode_display (Échantillon #3)



Figure 04 — 06_motherboard_qcode_display (Échantillon #4)




Figure 05 — 06_motherboard_qcode_display (Échantillon #5)



Figure 06 — 06_motherboard_qcode_display (Échantillon #6)




Figure 07 — 06_motherboard_qcode_display (Échantillon #7)




Figure 08 — 06_motherboard_qcode_display (Échantillon #8)



Figure 09 — 06_motherboard_qcode_display (Échantillon #9)



Figure 10 — 06_motherboard_qcode_display (Échantillon #10)