

**TM111 Introduction to computing and information
technology 1**

Scratch installation guide

This publication forms part of the Open University module TM111 *Introduction to computing and information technology 1*. Details of this and other Open University modules can be obtained from Student Recruitment, The Open University, PO Box 197, Milton Keynes MK7 6BJ, United Kingdom (tel. +44 (0)300 303 5303; email general-enquiries@open.ac.uk).

Alternatively, you may visit the Open University website at www.open.ac.uk where you can learn more about the wide range of modules and packs offered at all levels by The Open University.

The Open University,
Walton Hall, Milton Keynes
MK7 6AA

First published 2017.

Copyright © 2023 The Open University

All rights reserved. No part of this publication may be reproduced, stored in a retrieval system, transmitted or utilised in any form or by any means, electronic, mechanical, photocopying, recording or otherwise, without written permission from the publisher or a licence from the Copyright Licensing Agency Ltd. Details of such licences (for reprographic reproduction) may be obtained from the Copyright Licensing Agency Ltd, Saffron House, 6–10 Kirby Street, London EC1N 8TS (website www.cla.co.uk).

Open University materials may also be made available in electronic formats for use by students of the University. All rights, including copyright and related rights and database rights, in electronic materials and their contents are owned by or licensed to The Open University, or otherwise used by The Open University as permitted by applicable law.

In using electronic materials and their contents you agree that your use will be solely for the purposes of following an Open University course of study or otherwise as licensed by The Open University or its assigns.

Except as permitted above you undertake not to copy, store in any medium (including electronic storage or use in a website), distribute, transmit or retransmit, broadcast, modify or show in public such electronic materials in whole or in part without the prior written consent of The Open University or in accordance with the Copyright, Designs and Patents Act 1988.

Edited and designed by The Open University.

1.2

Contents

Scratch installation guide	6
Introduction	6
Installing Scratch	6
Direct download.....	7
Download from Microsoft Store	9
After installation	10
Block 2 projects	11
Acknowledgements.....	13

Scratch installation guide

Introduction

Scratch is the programming environment in which you will work on TM111 Block 2 programs.

Once installed, the Scratch app will work without an internet connection. The Scratch software will work on Windows 10+, MacOS 10.13+, , ChromeOS and Android 6.0+ (tablets only).

Note that the figures in the steps illustrate Windows 10 screens; if you are using a different operating system then you may see slightly different screens

Installing Scratch

To install the Scratch app, go to the Scratch downloads page at <https://scratch.mit.edu/download>. The web page should detect your operating system correctly, but you may change this if necessary by clicking on 'Windows', 'macOS', 'ChromeOS' or 'Android'.

At the time of writing this guide, the current version of Scratch is 3.29.1. However, by the time you install Scratch a

newer version might be available. TM111 recommends you use the latest version of Scratch.

If you wish to install the ChromeOS or the Android version you will need to follow the link to the Google Play store. For the Windows or Mac installation you can follow the link to the relevant store to download the app or click on the 'Direct download' option. The module team recommend you use the 'Direct download' option as this will place a Scratch icon on your desktop. However, instructions are given for both methods.




Figure 1. Microsoft Windows download options

Direct download

- a. Click on the 'Direct download' link as shown in Figure 1 above.
- b. If prompted by your web browser, Click 'Save' and select a convenient location on your computer to save

- the file to. Note its whereabouts or accept your computer's default download folder.
- c. Once downloaded, locate the Scratch installer file 'Scratch 3.29.1 Setup' on your computer.
 - d. To run the installer, either double-click on the installer file or right-click and click 'Open'.
 - e. A dialogue box will appear and ask you to confirm you wish to run the program- select 'Run'.
 - f. A further dialogue box will then pop up and ask if you wish to install for all users of the computer or just the logged on user. If you share the laptop with others using different profiles, you may want to install the software only for your own profile. Otherwise, you can install for all users. Select an option and click on 'Install'.
 - g. The software will then install. Once completed, click on the 'Finish' button to launch Scratch.

A Scratch icon should have appeared on your desktop, as shown in Figure 2, which you can use from now on to open Scratch.



Figure 2. Scratch icon

You may now delete the installer file from your computer

Download from Microsoft Store

- a. On following the link to the Microsoft store, click on the 'Download' button as shown in Figure 3.




Figure 3. The Scratch Microsoft Store download screen

- b. If prompted, click 'Save' and select a convenient location on your computer to save the file to. Note its whereabouts or accept your computer's default download folder.
- c. Once downloaded, locate the Scratch installer file 'Scratch 3 Installer' on your computer.
- d. To run the installer, either double-click on the installer file or right-click and click 'Install'.

- e. A dialogue box will then appear with the information 'Starting Download...' and the software will automatically install.
- f. Once the installation has completed, the software will automatically launch. No icon will be automatically added to the desktop but you can run Scratch from the Windows menu.
- g. You may now delete the installer file from your computer.

After installation

- a. Once fully installed, Scratch should open automatically, though you may get some dialogue boxes to confirm settings depending on your computer's settings . The first time it is run, you may be asked if you want to share usage data with the Scratch team (Figure 4)




Figure 4. The Scratch launch screen

You can choose here whether you wish to share data or not.

- b. The Scratch window should then open as shown in Figure 5.

When you want to close Scratch, click on the cross at the top right of the window.




Figure 5. The Scratch starting window

Block 2 projects

Scratch programs are housed in *projects*. We have supplied projects for you to work on throughout Block 2.

Download and save the [TM111 Block 2 Scratch Projects](#) zip file.

Unzip and extract the files to any location you like, keeping a note of the location. When working through the Block 2 materials you will need to remember this location.

You must retain the folder structure, as shown in Figure 6.




Figure 6 Diagram of the folder structure for the Scratch project files

Each subfolder, Part 1, Part 2, etc., contains Scratch project files, each with the extension `.sb3`, for that part's study.

If you double-click on a `.sb3` file it should open automatically in Scratch.

Acknowledgements

Grateful acknowledgement is made to the following sources.

'Scratch is a project of the Scratch Foundation, in collaboration with the Lifelong Kindergarten Group at the MIT Media Lab. It is available for free at <https://scratch.mit.edu>'

Every effort has been made to contact copyright holders. If any have been inadvertently overlooked the publishers will be pleased to make the necessary arrangements at the first opportunity.