





```
QEMU (Linux-1)
Removing default gateway for Ethernet interface ..... [F]
shutting down Ethernet interface eth0 ..... [
shutting down loopback interface lo ..... [
bringing up loopback interface lo ..... [
bringing up Ethernet interface eth0 ..... [
set up default gateway ..... [

ifconfig
eth0 Link encap:Ethernet HWaddr 50:6D:F6:02:66:00
      inet addr:172.50.0.10 Bcast:172.50.255.255 Mask:255.255.0.0
      UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
      RX packets:25 errors:0 dropped:0 overruns:0 frame:0
      TX packets:23 errors:0 dropped:0 overruns:0 carrier:0
      collisions:0 txqueuelen:1000
      RX bytes:7845 (7.6 KiB) TX bytes:7406 (7.2 KiB)

lo Link encap:Local Loopback
     inet addr:127.0.0.1 Mask:255.0.0.0
     UP LOOPBACK RUNNING MTU:16436 Metric:1
     RX packets:0 errors:0 dropped:0 overruns:0 frame:0
     TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
     collisions:0 txqueuelen:0
     RX bytes:0 (0.0 B) TX bytes:0 (0.0 B)
```



```
QEMU (Linux-1)
QEMU (Linux-2)
shutting down Ethernet interface eth0 ..... [ OK ]
shutting down loopback interface lo ..... [ OK ]
bringing up loopback interface lo ..... [ OK ]
bringing up Ethernet interface eth0 ..... [ OK ]
set up default gateway ..... [ OK ]

ifconfig
eth0 Link encap:Ethernet HWaddr 50:9A:C2:02:67:00
      inet addr:172.50.0.20 Bcast:172.50.255.255 Mask:255.255.0.0
      UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
      RX packets:42 errors:0 dropped:0 overruns:0 frame:0
      TX packets:42 errors:0 dropped:0 overruns:0 carrier:0
      collisions:0 txqueuelen:1000
      RX bytes:13257 (12.9 KiB) TX bytes:13524 (13.2 KiB)

lo Link encap:Local Loopback
     inet addr:127.0.0.1 Mask:255.0.0.0
     UP LOOPBACK RUNNING MTU:16436 Metric:1
     RX packets:0 errors:0 dropped:0 overruns:0 frame:0
     TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
     collisions:0 txqueuelen:0
     RX bytes:0 (0.0 B) TX bytes:0 (0.0 B)
```

```
R1#
*Sep 15 12:49:15.326: %SYS-5-CONFIG_I: Configured from console by console
R1#sh access-list
Standard IP access list 10
  10 permit 10.0.0.10
R1#
R1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#access-list 10 permit 10.0.0.20 0.0.0.0
R1(config)#
R1(config)#
R1(config)#^Z
R1#co
*Sep 15 12:58:11.667: %SYS-5-CONFIG_I: Configured from console by console
R1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#no access-list 10
R1(config)#int e0/0
R1(config-if)#no access-group 10 in
^
% Invalid input detected at '^' marker.
R1(config-if)#no ip access-group 10 in
R1(config-if)#sh access-list
```

* Ambiguous command: "a"

R1(config)#

R1(config)#

R1(config)# 100 permit icmp 10.0.0.0 0.255.255.255 172.50.0.0 0.0.255.255

R1(config)# 100 permit icmp 10.0.0.10 0.255.255.255 172.50.0.0 0.0.255.255

R1(config)# 100 permit icmp 10.0.0.10 0.0.0.0 172.50.0.0 0.0.255.255

R1(config)# 100 permit icmp 10.0.0.10 0.0.0.0 172.50.0.10 0.0.0.0

R1(config)#

