Links

- Docs Home
- Config Ref. Home
- FAQ
- User Comments

Top Level Elements

- Server
- Service

Executors

Executor

Connectors

- HTTP
- AJP

Containers

- Context
- Engine
- Host
- Cluster

Nested Components

- Global Resources
- JarScanner
- Listeners
- Loader
- Manager
- Realm
- Resources
- Valve

Cluster Elements

- Cluster
- Manager
- Channel
- Channel/Membership
- Channel/Sender
- Channel/Receiver
- Channel/Interceptor
- Valve
- Deployer
- ClusterListener

web.xml

Overview

Overview

This manual contains reference information about all of the configuration directives that can be included in a <code>conf/server.xml</code> file to configure the behavior of the Tomcat 7 Servlet/JSP container. It does not attempt to describe which configuration directives should be used to perform specific tasks for that, see the various *HOW-TO* documents on the main index page.

Tomcat configuration files are formatted as schemaless XML; elements and attributes are case-sensitive. Apache Ant-style variable substitution is supported; a system property with the name propname may be used in a configuration file using the syntax \${propname}. All system properties are available including those set using the -D syntax, those automatically made available by the JVM and those configured in the \$CATALINA_BASE/conf/catalina.properties file.

The configuration element descriptions are organized into the following major categories:

- **Connectors** Represent the interface between external clients sending requests to (and receiving responses from) a particular Service.
- Containers Represent components whose function is to process incoming requests, and create the corresponding responses. An Engine handles all requests for a Service, a Host handles all requests for a particular virtual host, and a Context handles all requests for a specific web application.
- **Nested Components** Represent elements that can be nested inside the element for a Container. Some elements can be nested inside any Container, while others can only be nested inside a Context.

For each element, the corresponding documentation follows this general outline:

- **Introduction** Overall description of this particular component. There will be a corresponding Java *interface* (in the org.apache.catalina package) that is implemented by one or more standard implementations.
- **Attributes** The set of attributes that are legal for this element. Generally, this will be subdivided into *Common* attributes that are supported by all implementations of the corresponding Java interface, and *Standard Implementation*

• Filter

Other

• System properties

- attributes that are specific to a particular Java class that implements this interface. The names of required attributes are **bolded**.
- **Nested Components** Enumerates which of the *Nested Components* can be legally nested within this element.
- **Special Features** Describes the configuration of a large variety of special features (specific to each element type) that are supported by the standard implementation of this interface.

Comments

Notice: This comments section collects your suggestions on improving documentation for Apache Tomcat.

If you have trouble and need help, read <u>Find Help</u> page and ask your question on the tomcat-users <u>mailing list</u>. Do not ask such questions here. This is not a Q&A section.

The Apache Comments System is explained <u>here</u>. Comments may be removed by our moderators if they are either implemented or considered invalid/off-topic.

Comments are disabled for this page at the moment.