NAME

xcmsdb - Device Color Characterization utility for X Color Management System

SYNOPSIS

```
xcmsdb [ -query ] [ -remove ] [ -format 32|16|8 ] [ -help ] [ -version ] [ filename ]
```

DESCRIPTION

xcmsdb is used to load, query, or remove Device Color Characterization data stored in properties on the root window of the screen as specified in section 7, Device Color Characterization, of the ICCCM. Device Color Characterization data (also called the Device Profile) is an integral part of Xlib's X Color Management System (Xcms), necessary for proper conversion of color specification between device-independent and device-dependent forms. Xcms uses 3x3 matrices stored in the XDCCC_LINEAR_RGB_MATRICES property to convert color specifications between CIEXYZ and RGB Intensity (XcmsRGBi, also referred to as linear RGB). Xcms then uses display gamma information stored in the XDCCC_LINEAR_RGB_COR-RECTION property to convert color specifications between RGBi and RGB device (XcmsRGB, also referred to as device RGB).

Note that Xcms allows clients to register *function sets* in addition to its built-in function set for CRT color monitors. Additional function sets may store their device profile information in other properties in function set specific format. This utility is unaware of these non-standard properties.

The ASCII readable contents of *filename* (or the standard input if no input file is given) are appropriately transformed for storage in properties, provided the **–query** or **–remove** options are not specified.

OPTIONS

xcmsdb program accepts the following options:

-query This option attempts to read the XDCCC properties off the screen's root window. If successful, it transforms the data into a more readable format, then sends the data to standard out.

-remove

This option attempts to remove the XDCCC properties on the screen's root window.

-format 32|16|8

Specifies the property format (32, 16, or 8 bits per entry) for the XDCCC_LINEAR_RGB_COR-RECTION property. Precision of encoded floating point values increases with the increase in bits per entry. The default is 32 bits per entry.

-help This option prints a summary of the available options and exits.

-version

This option prints the program version and exits.

SEE ALSO

xprop(1), Xlib documentation

ENVIRONMENT

DISPLAY

to figure out which display and screen to use.

AUTHOR

Chuck Adams, Tektronix Inc. Al Tabayoyon, SynChromatics Inc. (added multi-visual support)