NAME

chcpu – configure CPUs

SYNOPSIS

chcpu −c|−d|−e|−g *cpu-list*
chcpu −p *mode*
chcpu −r|−h|−V

DESCRIPTION

chcpu can modify the state of CPUs. It can enable or disable CPUs, scan for new CPUs, change the CPU dispatching *mode* of the underlying hypervisor, and request CPUs from the hypervisor (configure) or return CPUs to the hypervisor (deconfigure).

Some options have a *cpu-list* argument. Use this argument to specify a comma-separated list of CPUs. The list can contain individual CPU addresses or ranges of addresses. For example, **0,5,7,9-11** makes the command applicable to the CPUs with the addresses 0, 5, 7, 9, 10, and 11.

OPTIONS

−c, **−−configure** *cpu-list*

Configure the specified CPUs. Configuring a CPU means that the hypervisor takes a CPU from the CPU pool and assigns it to the virtual hardware on which your kernel runs.

−d, **−−disable** *cpu-list*

Disable the specified CPUs. Disabling a CPU means that the kernel sets it offline.

−e, **−−enable** *cpu-list*

Enable the specified CPUs. Enabling a CPU means that the kernel sets it online. A CPU must be configured, see **−c**, before it can be enabled.

−g, **−−deconfigure** *cpu-list*

Deconfigure the specified CPUs. Deconfiguring a CPU means that the hypervisor removes the CPU from the virtual hardware on which the Linux instance runs and returns it to the CPU pool. A CPU must be offline, see **−d**, before it can be deconfigured.

−p, **−−dispatch** *mode*

Set the CPU dispatching *mode* (polarization). This option has an effect only if your hardware architecture and hypervisor support CPU polarization. Available *modes* are:

horizontal	The workload is spread across all available CPUs.
vertical	The workload is concentrated on few CPUs.

−r, **−−rescan**

Trigger a rescan of CPUs. After a rescan, the Linux kernel recognizes the new CPUs. Use this option on systems that do not automatically detect newly attached CPUs.

−V, **−−version**

Display version information and exit.

−h, **−−help**

Display help text and exit.

RETURN CODES

chcpu has the following return codes:

0   success

1   failure

64   partial success

AUTHOR
Heiko Carstens ⟨heiko.carstens@de.ibm.com⟩

COPYRIGHT
Copyright IBM Corp. 2011

SEE ALSO
lscpu(1)

AVAILABILITY
The chcpu command is part of the util-linux package and is available from Linux Kernel Archive ⟨https:// www.kernel.org/pub/linux/utils/util-linux/⟩.