NAME
>   mousetweaks − Accessibility enhancements for pointing devices

SYNOPSIS
>   **mousetweaks**   [−−dwell]   [−−ssc]   [−−dwell−time=FLOAT]   [−−ssc−time=FLOAT]
>   [−m|−−dwell−mode=STRING] [−c|−−show−ctw] [−t|−−threshold=INT] [−g|−−geometry] [−s|−−shutdown]
>   [−−daemonize] [−?|−−help]

DESCRIPTION
>   **mousetweaks** is a collection of accessibility enhancements for pointing devices. This manual page de-
>   scribes the mousetweaks daemon.

OPTIONS
>   **−−dwell**
>   >   Automatically perform mouse clicks without using a physical button.
>
>   **−−ssc**   Trigger the secondary mouse button when the primary mouse button is held down for a specified
>   amount of time.
>
>   **−−dwell−time=FLOAT**
>   >   Time to keep the pointer motionless before a dwell click is performed. Range: 0.2 − 3.0 seconds.
>
>   **−−ssc−time=FLOAT**
>   >   Time to hold the primary mouse button before a simulated secondary click is performed. Range:
>   >   0.5 − 3.0 seconds.
>
>   **−m, −−dwell−mode=STRING**
>   >   Select a dwell mode. Available options: **window** − Select the click type from a window or a panel
>   >   applet. **gesture** − Perform different clicks by moving in different directions.
>
>   **−c, −−show−ctw**
>   >   Show the click−type window. Only useful in combination with −−dwell−mode=window.
>
>   **−t, −−threshold=INT**
>   >   Ignore small pointer movements. Range: 0 − 30 pixels.
>
>   **−g, −−geometry**
>   >   Size and position of the click-type window. Expects a standard X Window System geometry
>   >   string. ie. WIDTHxHEIGHT+X+Y
>
>   **−s, −−shutdown**
>   >   Stop the mousetweaks daemon.
>
>   **−−daemonize**
>   >   Start mousetweaks in the background, ie. spawn a child process.
>
>   **−−login**
>   >   Start mousetweaks in login mode. Login mode enables workarounds specific to GDM. Currently
>   >   unused.

FILES
>   *mousetweaks.pid*
>   >   The daemon creates a lock file in the $XDG_RUNTIME_DIR directory to keep track of its state.
>   >   On systems with no user runtime directory, the $XDG_CACHE_HOME directory is used.

BUGS
>   Report bugs to <http://bugzilla.gnome.org/> ⟨http://bugzilla.gnome.org/⟩

AUTHORS
>   This manual page was written by Francesco Fumanti.

LICENSE
>   Licenced under the GNU General Public License v3 or later.