### **NAME**

pull-lp-source - download a source package from Launchpad

#### **SYNOPSIS**

pull-lp-source [options] source package [release|version]

### DESCRIPTION

**pull-lp-source** downloads and extracts the specified *version* of **source package** from Launchpad, or the latest version of the specified *release*. To request a version from a particular pocket say *release-pocket* (with a magic **-release** for only the release pocket). If no *version* or *release* is specified, the latest version in the development release will be downloaded.

### **OPTIONS**

Listed below are the command line options for pull-lp-source:

### source package

This is the source package that you would like to be downloaded from Launchpad.

#### version

This is the version of the source package to be downloaded.

**release** This is the release that you would like the source package to be downloaded from. This value defaults to the current development release.

### -h, --help

Display a help message and exit.

### -d, --download-only

Do not extract the source package.

### -m UBUNTU MIRROR, --mirror=UBUNTU MIRROR

Use the specified Ubuntu mirror. Should be in the form **http://archive.ubuntu.com/ubuntu**. If the package isn't found on this mirror, **pull-lp-source** will fall back to Launchpad, as its name implies.

## --no-conf

Do not read any configuration files, or configuration from environment variables.

## **ENVIRONMENT**

All of the **CONFIGURATION VARIABLES** below are also supported as environment variables. Variables in the environment take precedence to those in configuration files.

**DIST** Specifies the default target.

# **CONFIGURATION VARIABLES**

The following variables can be set in the environment or in **ubuntu-dev-tools**(5) configuration files. In each case, the script-specific variable takes precedence over the package-wide variable.

## $PULL\_LP\_SOURCE\_UBUNTU\_MIRROR, UBUNTUTOOLS\_UBUNTU\_MIRROR$

The default value for **--mirror**.

## **SEE ALSO**

dget(1), pull-debian-source(1), pull-debian-debdiff(1), ubuntu-dev-tools(5)

## **AUTHOR**

**pull-lp-source** and this manual page were written by Iain Lane <iain@orangesquash.org.uk>. Both are released under the GNU General Public License, version 3 or later.