NAME
ptx − produce a permuted index of file contents

SYNOPSIS
ptx [*OPTION*]... [*INPUT*]...   *(without -G)*
ptx *-G* [*OPTION*]... [*INPUT* [*OUTPUT*]]

DESCRIPTION
Output a permuted index, including context, of the words in the input files.

With no FILE, or when FILE is −, read standard input.

Mandatory arguments to long options are mandatory for short options too.

−A, **−−auto−reference**
> output automatically generated references

−G, **−−traditional**
> behave more like System V 'ptx'

−F, **−−flag−truncation**=*STRING*
> use STRING for flagging line truncations. The default is '/'

−M, **−−macro−name**=*STRING*
> macro name to use instead of 'xx'

−O, **−−format**=*roff*
> generate output as roff directives

−R, **−−right−side−refs**
> put references at right, not counted in **−w**

−S, **−−sentence−regexp**=*REGEXP*
> for end of lines or end of sentences

−T, **−−format**=*tex*
> generate output as TeX directives

−W, **−−word−regexp**=*REGEXP*
> use REGEXP to match each keyword

−b, **−−break−file**=*FILE*
> word break characters in this FILE

−f, **−−ignore−case**
> fold lower case to upper case for sorting

−g, **−−gap−size**=*NUMBER*
> gap size in columns between output fields

−i, **−−ignore−file**=*FILE*
> read ignore word list from FILE

−o, **−−only−file**=*FILE*
> read only word list from this FILE

−r, **−−references**
> first field of each line is a reference

−t, **−−typeset−mode**   − not implemented −

−w, **−−width**=*NUMBER*
> output width in columns, reference excluded

−−help display this help and exit

−−version
>   output version information and exit

AUTHOR
>   Written by F. Pinard.

REPORTING BUGS
>   GNU coreutils online help: <https://www.gnu.org/software/coreutils/>
>   Report ptx translation bugs to <https://translationproject.org/team/>

COPYRIGHT
>   Copyright © 2018 Free Software Foundation, Inc. License GPLv3+: GNU GPL version 3 or later <https://gnu.org/licenses/gpl.html>.
>   This is free software: you are free to change and redistribute it. There is NO WARRANTY, to the extent permitted by law.

SEE ALSO
>   Full documentation at: <https://www.gnu.org/software/coreutils/ptx>
>   or available locally via: info '(coreutils) ptx invocation'