NAME

gvfs - GIO virtual file system

DESCRIPTION

GIO provides a VFS API to GLib applications. It includes a 'local' implementation using POSIX. gvfs provides implementations that go beyond that and allow to access files and storage using many protocols, such as ftp, http, sftp, dav, nfs, etc. It also provides support for trash folders, for cd burning and for monitoring interesting devices and volumes on the computer.

Applications use gvfs indirectly, by means of GIO loading the gvfs module that implements the GIO extension points. The gvfs support for volume monitoring is included in a separate loadable module.

The actual gvfs implementation is distributed over a number of processes. None of these are expected to be started from the commandline, except for debugging purposes.

Main processes:

- gvfsd the main gvfs daemon
- gvfsd-fuse mounts gvfs as a fuse filesystem
- gvfsd-metadata writes gvfs metadata

Volume monitors:

- gvfs-afc-volume-monitor a volume monitor for Apple iPhone/iPod Touch devices
- gvfs-goa-volume-monitor a volume monitor for GNOME Online Accounts
- gvfs-gphoto2-volume-monitor a volume monitor for PTP devices
- gvfs-mtp-volume-monitor a volume monitor for MTP devices
- gvfs-udisks2-volume-monitor a udisks2-based volume monitor

Mount backends:

- gvfsd-admin mounts local filesystem with admin privileges
- gvfsd-afc mounts iPhone/iPod touch volumes
- gvfsd-afp mounts Apple Filing Protocol volumes
- gvfsd-afp-browse browses Apple Filing Protocol volumes
- gvfsd-archive mounts archive files in various formats
- gvfsd-burn provides a location for burning CDs
- gvfsd-cdda mounts audio CDs
- gvfsd-computer provides computer://
- gvfsd-dav mounts DAV filesystems
- gvfsd–dnssd browses dnssd
- gvfsd-ftp mounts over FTP
- gvfsd-google mounts Google Drive shares
- gvfsd-gphoto2 mounts over PTP
- gvfsd-http mounts over HTTP
- gvfsd-localtest a test backend
- gvfsd-mtp mounts over MTP
- gvfsd-network provides network://

gvfs 1

- gvfsd-nfs mounts over NFS
- gvfsd-recent provides recent://
- gvfsd-sftp mounts over sftp
- gvfsd-smb mounts Windows Shares Filesystem volumes
- gvfsd-smb-browse browses Windows Shares Filesystem volumes
- gvfsd-trash provides trash://

ENVIRONMENT

GIO_USE_VFS

If set, specifies the GIO vfs implementation to use. Possible values include 'local' and 'gvfs'.

GIO_USE_VOLUME_MONITOR

If set, specifies the GIO volume monitor implementation to use. Possible values include 'unix', 'GProxyVolumeMonitorUDisks2', as well as other native volume monitors that are described in the key files in **\$XDG_DATA_DIRS**/gvfs/remote-volume-monitors.

FILES

\$XDG_DATA_DIRS/gvfs/mounts

This directory contains key files describing mount daemons.

\$XDG_DATA_DIRS/gvfs/remote-volume-monitors

This directory contains key files describing remote volume monitors.

SEE ALSO

GIO documentation^[1], gvfsd(1), gvfsd-fuse(1), gvfsd-metadata(1)

NOTES

1. GIO documentation http://developer.gnome.org/gio

gvfs 2