TMUX

TMUX

Part 1: Getting started with tmux

1) Install TMUX $ sudo apt install tmux

Part2

Part 2: Horizontall and vertical Panes

1. To default tmux prefix : CTRL + B
   1) split the window horigontall prefix, then (")
   2) split the window vertically : prefix, then (%)

2. To switch betweeen : CTRL + B (←↕→)
   1) switch between panes: prefix , then (←↕→)

3. if connection get lost with tmux:-
   > tmux attach
   > tmux a

4. to zoom to the pane(window)
   1) zoom into a pane :- prefix, then z (ctrl b, z)
   2) to unzoom : parefi, then z to unzoom

5. to kill the pane
   1) to kill the window : Prefix, x

Part3

Part3: Creating and managing windows

1. To create a new window
   1) Create a new window :- Prefix, c
   2) move to previous window : prefix, p {P for previous}
   3) move to next window : prefix, n {n for next}

Note:- To see which window you are it will show (*) on the window

   4) to kill a window :- &
       prefix, &
   5) to Rename a window : prefix,(,)

Part4

Part4 : Creating and switching Between sessios

1. To Disconnect your session
   1) Disconnect your session :- Prefix,d [d for disconnect]
   2) To go back the session :- > Tmux attach
   3) To see the lest of Tmux session :- > tmux list-sessions or tmux ls

2. To go to other session
   1) To see the lest of Tmux session :- > Tmux lest-sessions or (Tmux ls)
   2) To go to the other session :- > Tmux attach{a} -t {target} [number]

3. To Rename the session
   1) To rename the session :- prefix, $ ($)

4. To creae new Tmux session
   > Tmux new -s "[name]"

5. Show session list : prefix,s
   1) to show session list: prefix, S

Tweaks

Customization and tweaks

Go:- Tmux Cheat Sheet.com

1. Crete a file .tmux.conf in ~ (home)
   1) Edit :- # use Alt-arrow keys to switch panes
         bind -n M-Left Select-pane -L
         "   " " -Right "   " -R
         "   " " -Up "   " -U
         "   " " -Down "   " -D

             # Move Mode
               setw -g mouse on

           # Sheft arrow to switch window
             bind -n S-Left prefious-window
             bind -n S-Right next-window

           # set easier window split keys
             bind -key v split-window -h
             "   " h "   " -v

Note: Ctrl + B (?) :- help!