



Creating and managing Virtual Machine in Azure-50

Create a Microsoft azure account its free to use we need to pay extra to use more

Open you azure click on virtual machine



Create a new VM



Give VM a name and resource group leave everything default if you want

Microsoft Azure portal (PWA) - Create a virtual machine - Microsoft Azure

Microsoft Azure
Search resources, services, and docs (G+/I)

Home > Compute infrastructure | Virtual machines >

Create a virtual machine
Help me create a VM optimized for high availability
Help me choose the right VM size for my workload
Help me create a low cost VM

Project details

Select the subscription to manage deployed resources and costs. Use resource groups like folders to organize and manage all your resources.

Subscription * ⓘ
Azure for Students

Resource group * ⓘ
(New) Learn
Create new

Instance details

Virtual machine name * ⓘ
Batch8VM

Region * ⓘ
(US) West US 3
Deploy to an Azure Extended Zone

Availability options ⓘ
Availability zone

Zone options ⓘ

☒ Self-selected zone
Choose up to 3 availability zones, one VM per zone

☐ Azure-selected zone (Preview)
Let Azure assign the best zone for your needs

Availability zone * ⓘ
Zone 1
You can now select multiple zones. Selecting multiple zones will create one VM per zone. Learn more ⓘ

Security type ⓘ
Trusted launch virtual machines
Configure security features

Image * ⓘ
Windows 11 Pro, version 24H2 - x64 Gen2
See all images | Configure VM generation

VM architecture ⓘ

☐ Arm64
☒ x64

Arm64 is not supported with the selected image.

Give username and password

Run with Azure Spot discount ⓘ
☐

Size * ⓘ
Standard_B2ats_v2 - 2 vcpus, 1 GiB memory (₹570.88/month) (free services ...
See all sizes

Enable Hibernation ⓘ
☐
Hibernate is not supported by the size that you have selected. Choose a size that is compatible with Hibernation to enable this feature. Learn more ⓘ

Administrator account

Username * ⓘ
Bharath

Password *

Confirm password *

Inbound port rules

Select which virtual machine network ports are accessible from the public internet. You can specify more limited or granular network access on the Networking tab.

Public inbound ports * ⓘ

☐ None
☒ Allow selected ports

Select inbound ports *
RDP (3389)

This will allow all IP addresses to access your virtual machine. This is only recommended for testing. Use the Advanced controls in the Networking tab to create rules to limit inbound traffic to known IP addresses.

Licensing

☒ I confirm I have an eligible Windows 10/11 license with multi-tenant hosting rights.

Review multi-tenant hosting rights for Windows 10/11 compliance ⓘ

< Previous
Next : Disks >
Review + create

After this you can leave everything at default

Create a virtual machine



Help me create a VM optimized for high availability

Help me choose the right VM size for my workload

He

Basics Disks Networking Management Monitoring Advanced Tags Review + create

Azure VMs have one operating system disk and a temporary disk for short-term storage. You can attach additional data disks. The size of the VM determines the type of storage you can use and the number of data disks allowed. [Learn more](#)

VM disk encryption

Azure disk storage encryption automatically encrypts your data stored on Azure managed disks (OS and data disks) at rest by default when persisting it to the cloud.

Encryption at host

☐

Encryption at host is not registered for the selected subscription. [Learn more](#)

OS disk

OS disk size

Image default (127 GiB)

OS disk type *

Premium SSD (locally-redundant storage)

Delete with VM

☒

Key management

Platform-managed key

Enable Ultra Disk compatibility

☐

Data disks for Batch8VM

You can add and configure additional data disks for your virtual machine or attach existing disks. This VM also comes with a temporary disk.

LUN	Name	Size (GiB)	Disk type	Host caching	Delete with VM
Create and attach a new disk Attach an existing disk					

Advanced

< Previous

Next : Networking >

Review + create

Give Virtual network and subnet if you want

Create a virtual machine



Help me create a VM optimized for high availability

Help me choose the right VM size for my w

Define network connectivity for your virtual machine by configuring network interface card (NIC) settings. You can control ports, inbound and outbound connectivity with security group rules, or place behind an existing load balancing solution. [Learn more](#)

Network interface

When creating a virtual machine, a network interface will be created for you.

Virtual network *

(new) Batch8VM-vnet

Create new

Subnet *

(new) default (10.0.0.0/24)

Public IP

Create new

NIC network security group

☐ None

☐ Basic

☒ Advanced

Configure network security group *

(new) Batch8VM-nsg

Create new

Delete public IP and NIC when VM is deleted

☐

Enable accelerated networking

☒

Load balancing

You can place this virtual machine in the backend pool of an existing Azure load balancing solution. [Learn more](#)

Load balancing options

☒ None

☐ Azure load balancer
Supports all TCP/UDP network traffic, port-forwarding, and outbound flows.

☐ Application gateway
Web traffic load balancer for HTTP/HTTPS with URL-based routing, SSL termination, session persistence, and web application firewall.

Create a virtual machine



Help me create a VM optimized for high availability

Help me choose the right VM size for my work

Microsoft Defender for Cloud

Microsoft Defender for Cloud provides unified security management and advanced threat protection across hybrid cloud workloads. [Learn more](#)

Your subscription is protected by Foundational Cloud Security Posture Management Free Plan.

Identity

Enable system assigned managed identity ☒

Microsoft Entra ID

Login with Microsoft Entra ID ☐
 RBAC role assignment of Virtual Machine Administrator Login or Virtual Machine User Login is required when using Microsoft Entra ID login. [Learn more](#)

Auto-shutdown

Enable auto-shutdown ☐

Backup

Enable backup ☐

Site Recovery

Enable Disaster Recovery ☐

Guest OS updates

Enable periodic assessment ☐

Enable hotpatch ☐

Hotpatch is not available for this image. [Learn more](#)

Patch orchestration options

Some patch orchestration options are not available for this image. [Learn more](#)

[< Previous](#)

[Next : Monitoring >](#)

[Review + create](#)

Create a virtual machine

[Help me create a VM optimized for high availability](#)[Help me choose the right VM size for my work](#)

✓ Validation passed

Basics Disks Networking Management Monitoring Advanced Tags **Review + create**

Price

1 X Standard B2ats v2
by Microsoft
[Terms of use](#) | [Privacy policy](#)

Subscription credits apply ⓘ

0.7820 INR/hr
[Pricing for other VM sizes](#)

TERMS

By clicking "Create", I (a) agree to the legal terms and privacy statement(s) associated with the Marketplace offering(s) listed above; (b) authorize Microsoft to bill my current payment method for the fees associated with the offering(s), with the same billing frequency as my Azure subscription; and (c) agree that Microsoft may share my contact, usage and transactional information with the provider(s) of the offering(s) for support, billing and other transactional activities. Microsoft does not provide rights for third-party offerings. See the [Azure Marketplace Terms](#) for additional details.

Basics

Subscription	Azure for Students
Resource group	(new) Learn
Virtual machine name	Batch8VM
Region	West US 3
Availability options	Availability zone
Zone options	Self-selected zone
Availability zone	1
Security type	Trusted launch virtual machines
Enable secure boot	Yes
Enable vTPM	Yes
Integrity monitoring	No
Image	Windows 11 Pro, version 24H2 - Gen2
VM architecture	x64

[< Previous](#)[Next >](#)[Create](#)

It will show price but don't worry they don't charge for it and now create it

Here you can start and stop the VM

Microsoft Azure portal (PWA) - Batch8VM - Microsoft Azure

Home > CreateVm-microsoftwindowsdesktop.windows-11-win11-20250823151207 | Overview >

Batch8VM
Virtual machine

Help me copy this VM in any region | Manage this VM with Azure CLI

Search

Connect > Start > Restart > Stop > Hibernate > Capture > Delete > Refresh > Open in mobile > Feedback > CU / PS

Overview

- Activity log
- Access control (IAM)
- Tags
- Diagnose and solve problems
- Resource visualizer
- Connect
- Networking
- Settings
- Availability + scale
- Security
- Backup + disaster recovery
- Operations
- Monitoring
- Automation
- Help

Essentials

Resource group (move) : [Learn](#)

Status : Running

Location : West US 3 (Zone 1)

Subscription (move) : [Azure for Students](#)

Subscription ID : 5af96dc8-24a9-4598-9c53-92bdd6e9e889

Availability zone : 1

Tags (edit) : [Add tags](#)

Operating system : Windows (Windows 11 Pro)

Size : Standard B2ats v2 (2 vcpus, 1 GiB memory)

Public IP address : [20.14.73.45](#)

Virtual network/subnet : [Batch8VM-vnet/default](#)

DNS name : [Not configured](#)

Health state : +

Time created : 8/23/2025, 9:49 AM UTC

Properties | Monitoring | Capabilities (8) | Recommendations | Tutorials

Virtual machine

Computer name	Batch8VM
Operating system	Windows (Windows 11 Pro)
VM generation	V2
VM architecture	x64
Agent status	Ready
Agent version	2.7.41491.1172
Hibernation	Disabled
Host group	-
Host	-
Proximity placement group	-
Colocation status	N/A

Networking

Public IP address	20.14.73.45 (Network interface batch8vm416_z1)
Public IP address (IPv6)	-
Private IP address	10.0.0.4
Private IP address (IPv6)	-
Virtual network/subnet	Batch8VM-vnet/default
DNS name	Configure

Size


Size	Standard B2ats v2
vCPUs	2
RAM	1 GiB

Add or remove favorites by pressing Ctrl+Shift+F


Click on connect and download your RSP file

The screenshot shows the Microsoft Azure portal interface. The top navigation bar includes the Microsoft Azure logo and a search bar. The breadcrumb trail indicates the path: Home > CreateVm-microsoftwindowsdesktop.windows-11-win11-20250823151207 | Overview > Batch8VM. The main heading is 'Batch8VM | Connect', with 'Virtual machine' as a subtitle. A search bar is located below the heading. The left sidebar contains a list of navigation options: Overview, Activity log, Access control (IAM), Tags, Diagnose and solve problems, Resource visualizer, Connect (highlighted with a red arrow), Bastion, Windows Admin Center, Networking, Settings, Availability + scale, Security, Backup + disaster recovery, Operations, Monitoring, Automation, and Help. The main content area displays the 'Native RDP' connection settings. It includes tabs for 'MOST POPULAR' and 'LOCAL MACHINE'. The 'Source machine' section shows 'Source machine OS' as Windows and 'Source IP address' as Local IP range | 152.59.0.0/16. The 'Destination VM' section shows 'VM IP address' as Public IP | 20.14.73.45 and 'VM port' as 3389. The 'Connection prerequisites' section has a 'Check access' button. The 'Connect using RDP file' section has a 'Download RDP file' button (highlighted with a red arrow) and a 'Download and open file to connect' option. The 'Username' field is set to 'Bharath', and there is a 'Forgot password? Reset password' link. An 'Edit settings' button is at the bottom left of the settings panel. Below the settings panel, there is a link for 'More ways to connect (4)'.


Open it proceed with connect



Give the password from earlier you have given



Click on yes and you will see your VM getting loaded and ready to use



Azure Batch8VM - 20.14.73.45:3389 - Remote Desktop Connection

