



Table of Contents

- Welcome
- Getting Started
- SOLIDWORKS API Help
- SOLIDWORKS Electrical API Help
- SOLIDWORKS PDM Professional API Help
- PDM Pro API Web Service
- FeatureWorks API Help
- SOLIDWORKS Costing API Help
- SOLIDWORKS Document Manager API Help
- SOLIDWORKS Inspection API Help
- SOLIDWORKS Routing API Help
- SOLIDWORKS Simulation API Help
- SOLIDWORKS Sustainability API Help
- SOLIDWORKS Toolbox API Help
- SOLIDWORKS Utilities API Help
- SOLIDWORKS Visualize API Help
- eDrawings API Help
- DraftSight API Help
 - Welcome
 - Getting Started
 - Release Notes
 - Access Diagram
 - Interop.dsAutomation Namespace
 - Overview
 - Interfaces
 - AlignedDimension
 - AngularDimension
 - Application
 - ApplicationOptions
 - ArcAlignedText
 - ArcLengthDimension
 - AttributeDefinition
 - IAtributeInstance**
 - Members
 - IBlockDefinition
 - IBlockInstance
 - ICircle
 - ICircleArc
 - IColor
 - IColorPicker
 - ICommand
 - ICommandMessage
 - IContextMenuItem
 - ICurvedSettings
 - ICustomCoordinateSystem
 - ICustomCoordinateSystemManager
 - ICustomData
 - ICustomPropertyControl
 - IDgnDefinition
 - IDgnReference
 - IDiameterDimension
 - IDictionary
 - DimensionStyle
 - IDimensionStyleAngularDimension
 - IDimensionStyleArrowsOptions
 - IDimensionStyleDualDimensionControl
 - IDimensionStyleFitOptions
 - IDimensionStyleLinearDimension
 - IDimensionStyleLineOptions
 - IDimensionStyleManager
 - IDimensionStyleRadialDiameterControl
 - IDimensionStyleTextOptions
 - IDimensionStyleToleranceOptions
 - IDimensionStyleUserData
 - IDocument
 - IDocumentExporter
 - IDrawingProperties
 - IDrawingSupportFiles
 - IDropData
 - IDSWindow
 - IDynamicBlockInstanceProperty
 - IEllipseArc
 - IEmbeddedObject

Interfaces \ IAtributeInstance

IAtribute Instance Interface

Allows access to a BlockAttribute instance.

.NET Syntax

Visual Basic (Declaration)

Public Interface IAtribute Instance

C#

public interface IAtribute Instance

JavaScript

Object dsAttributeInstance

COM native C++

interface IAtribute Instance

C++

class dsAttributeInstance_c

Example

This code snippet shows how to write the names and values of the BlockAttribute instances to a file.

COM native C++

```
void CAddinDumpManager::DumpAttributeInstances( CStdioFile& fileOutput, LPCWSTR tabStr, IBlockInstancePtr blkIns )
{
    CString strPrint;

    _variant_t pVariantArrayAI = blkIns->GetAttributeInstances();
    if( V_VT( &pVariantArrayAI ) != VT_EMPTY )
    {
        IAtribute InstancePtr *AttrIns = NULL;
        int countOfAI = 0;
        TypeConverter::convertVariantArrayToPtrArray< IAtribute InstancePtr, IAtribute Instance>( pVariantArrayAI, AttrIns, countOfAI );

        strPrint.Format( L"%sAttribute instances (%d):\r\n", tabStr, countOfAI );
        fileOutput.WriteString( strPrint );

        if( AttrIns && countOfAI > 0 )
        {
            for( int i = 0; i < countOfAI; ++i )
            {
                bstr_t AttInstName = AttrIns[i]->GetName();
                strPrint.Format( L"%s\tName: %s\r\n", tabStr, AttInstName.operator const wchar_t*() );
                fileOutput.WriteString( strPrint );

                bstr_t AttInstValue = AttrIns[i]->GetValue();
                strPrint.Format( L"%s\tValue: %s\r\n", tabStr, AttInstValue.operator const wchar_t*() );
                fileOutput.WriteString( strPrint );
            }
            delete[] AttrIns;
        }
        else
        {
            strPrint.Format( L"%s\tERROR GetAttributeInstances\r\n", tabStr );
            fileOutput.WriteString( strPrint );
        }
    }
    else
    {
        strPrint.Format( L"%s\tERROR GetAttributeInstances\r\n", tabStr );
        fileOutput.WriteString( strPrint );
    }
}
```

Example

Get and Set Block Definitions, Block Instances, and Block Attribute Instances (C#)
Get and Set Block Definitions, Block Instances, and BlockAttribute Instances (VB.NET)
Get and Set Block Definitions, Block Instances, and BlockAttribute Instances (VBA)

Accessors

IBlockInstance::GetAttributeIntances

IDocument::GetObjectByHandle

Access Diagram

AttributeInstance

See Also

IAtribute Instance Members
Interop.dsAutomation Namespace
IBlockInstance Interface
IAttribute Definition Interface
IBlockDefinition Interface

< Members

Members >