

SOLIDWORKS API (.NET VBA C#) — Reference (167/337): IModelDoc (part 3 of 13)

SOLIDWORKS API Documentation (converted from CHM)

IModelDoc (part 3 of 13) (Type)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreateCircleByRadius Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateCircleByRadius Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateCircleByRadius](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateCircleByRadius( _  
    ByVal P1 As System.Object, _  
    ByVal Radius As System.Double _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim P1 As System.Object  
Dim Radius As System.Double  
Dim value As System.Boolean  
  
value = instance.CreateCircleByRadius(P1, Radius)
```

C#

```
System.bool CreateCircleByRadius(  
    System.object P1,  
    System.double Radius  
)
```

C++/CLI

```
System.bool CreateCircleByRadius(  
& System.Object^ P1,  
& System.double Radius  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

P1

Radius

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreateCircleByRadius](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreateCircleByRadius2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateCircleByRadius2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateCircleByRadius2](#).

.NET Syntax

```
Function CreateCircleByRadius2( _
    ByVal XC As System.Double, _
    ByVal YC As System.Double, _
    ByVal Zc As System.Double, _
    ByVal Radius As System.Double _
) As System.Object
```



```
Dim instance As IModelDoc
Dim XC As System.Double
Dim YC As System.Double
Dim Zc As System.Double
Dim Radius As System.Double
Dim value As System.Object

value = instance.CreateCircleByRadius2(XC, YC, Zc, Radius)
```

```
System.object CreateCircleByRadius2(
    System.double XC,
    System.double YC,
    System.double Zc,
    System.double Radius
)
```

```
System.Object^ CreateCircleByRadius2(
    & System.double XC,
    & System.double YC,
    & System.double Zc,
    & System.double Radius
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

XC

YC

Zc

Radius

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreateCircleByRadius2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

CreateCircleDB Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateCircleDB Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateCircleDB](#).

.NET Syntax

```
Function CreateCircleDB( _  
    ByVal Cx As System.Double, _  
    ByVal Cy As System.Double, _  
    ByVal Cz As System.Double, _  
    ByVal Radius As System.Double _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Cx As System.Double  
Dim Cy As System.Double  
Dim Cz As System.Double  
Dim Radius As System.Double  
Dim value As System.Boolean  
  
value = instance.CreateCircleDB(Cx, Cy, Cz, Radius)
```

C#

```
System.bool CreateCircleDB(  
    System.double Cx,  
    System.double Cy,  
    System.double Cz,  
    System.double Radius  
)
```

C++/CLI

```
System.bool CreateCircleDB(  
& System.double Cx,  
& System.double Cy,  
& System.double Cz,  
& System.double Radius  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Cx

Cy

Cz

Radius

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreateCircleDB](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

CreateCircleVB Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateCircleVB Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateCircleVB](#).

.NET Syntax

Visual Basic (Declaration)

```

Sub CreateCircleVB( _
    ByVal Plx As System.Double, _
    ByVal Ply As System.Double, _
    ByVal Plz As System.Double, _
    ByVal Radius As System.Double _
)

```

Visual Basic (Usage)



```

Dim instance As IModelDoc
Dim Plx As System.Double
Dim Ply As System.Double
Dim Plz As System.Double
Dim Radius As System.Double

instance.CreateCircleVB(Plx, Ply, Plz, Radius)

```

C#

```

void CreateCircleVB(
    System.double Plx,
    System.double Ply,
    System.double Plz,
    System.double Radius
)

```

C++/CLI

```

void CreateCircleVB(
    & System.double Plx,
    & System.double Ply,
    & System.double Plz,
    & System.double Radius
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Plx

Ply

Plz

Radius

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::CreateCircleVB](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

CreateCircularSketchStepAndRepeat Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateCircularSketchStepAndRepeat Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateCircularSketchStepAndRepeat](#).

.NET Syntax

Visual Basic (Declaration)

```

Function CreateCircularSketchStepAndRepeat( _
    ByVal ArcRadius As System.Double, _

```

```

    ByVal ArcAngle As System.Double, _
    ByVal PatternNum As System.Integer, _
    ByVal PatternSpacing As System.Double, _
    ByVal PatternRotate As System.Boolean, _
    ByVal DeleteInstances As System.String _
) As System.Boolean

```

Visual Basic (Usage)



```

Dim instance As IModelDoc
Dim ArcRadius As System.Double
Dim ArcAngle As System.Double
Dim PatternNum As System.Integer
Dim PatternSpacing As System.Double
Dim PatternRotate As System.Boolean
Dim DeleteInstances As System.String
Dim value As System.Boolean

value = instance.CreateCircularSketchStepAndRepeat(ArcRadius, ArcAngle, PatternNum,
PatternSpacing, PatternRotate, DeleteInstances)

```

C#

```

System.bool CreateCircularSketchStepAndRepeat(
    System.double ArcRadius,
    System.double ArcAngle,
    System.int PatternNum,
    System.double PatternSpacing,
    System.bool PatternRotate,
    System.string DeleteInstances
)

```

C++/CLI

```

System.bool CreateCircularSketchStepAndRepeat(
    & System.double ArcRadius,
    & System.double ArcAngle,
    & System.int PatternNum,
    & System.double PatternSpacing,
    & System.bool PatternRotate,
    & System.String^ DeleteInstances
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ArcRadius

ArcAngle

PatternNum

PatternSpacing

PatternRotate

DeleteInstances

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreateCircularSketchStepAndRepeat](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

Obsolete. Superseded by [IModelDoc2::CreateClippedSplines](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateClippedSplines( _
    ByVal ParamsIn As System.Object, _
    ByVal X1 As System.Double, _
    ByVal Y1 As System.Double, _
    ByVal X2 As System.Double, _
    ByVal Y2 As System.Double _
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc
Dim ParamsIn As System.Object
Dim X1 As System.Double
Dim Y1 As System.Double
Dim X2 As System.Double
Dim Y2 As System.Double
Dim value As System.Object

value = instance.CreateClippedSplines(ParamsIn, X1, Y1, X2, Y2)
```

C#

```
System.object CreateClippedSplines(
    System.object ParamsIn,
    System.double X1,
    System.double Y1,
    System.double X2,
    System.double Y2
)
```

C++/CLI

```
System.Object^ CreateClippedSplines(
    & System.Object^ ParamsIn,
    & System.double X1,
    & System.double Y1,
    & System.double X2,
    & System.double Y2
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ParamsIn

X1

Y1

X2

Y2

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreateClippedSplines](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

CreateEllipse Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateEllipse Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateEllipse](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateEllipse( _  
    ByVal Center As System.Object, _  
    ByVal Major As System.Object, _  
    ByVal Minor As System.Object _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Center As System.Object  
Dim Major As System.Object  
Dim Minor As System.Object  
Dim value As System.Boolean  
  
value = instance.CreateEllipse(Center, Major, Minor)
```

C#

```
System.bool CreateEllipse(  
    System.object Center,  
    System.object Major,  
    System.object Minor  
)
```

C++/CLI

```
System.bool CreateEllipse(  
& System.Object^ Center,  
& System.Object^ Major,  
& System.Object^ Minor  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Center

Major

Minor

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreateEllipse](#).

See Also

[IModelDoc Interface](#)

[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreateEllipse2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateEllipse2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateEllipse2](#).

Visual Basic (Declaration)

```
Function CreateEllipse2( _
    ByVal CenterX As System.Double, _
    ByVal CenterY As System.Double, _
    ByVal CenterZ As System.Double, _
    ByVal MajorX As System.Double, _
    ByVal MajorY As System.Double, _
    ByVal MajorZ As System.Double, _
    ByVal MinorX As System.Double, _
    ByVal MinorY As System.Double, _
    ByVal MinorZ As System.Double _
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc
Dim CenterX As System.Double
Dim CenterY As System.Double
Dim CenterZ As System.Double
Dim MajorX As System.Double
Dim MajorY As System.Double
Dim MajorZ As System.Double
Dim MinorX As System.Double
Dim MinorY As System.Double
Dim MinorZ As System.Double
Dim value As System.Object

value = instance.CreateEllipse2(CenterX, CenterY, CenterZ, MajorX, MajorY, MajorZ, MinorX, MinorY, MinorZ)
```

C#

```
System.object CreateEllipse2(
    System.double CenterX,
    System.double CenterY,
    System.double CenterZ,
    System.double MajorX,
    System.double MajorY,
    System.double MajorZ,
    System.double MinorX,
    System.double MinorY,
    System.double MinorZ
)
```

C++/CLI

```
System.Object^ CreateEllipse2(
    & System.double CenterX,
    & System.double CenterY,
    & System.double CenterZ,
    & System.double MajorX,
    & System.double MajorY,
    & System.double MajorZ,
    & System.double MinorX,
    & System.double MinorY,
    & System.double MinorZ
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

CenterX

CenterY

CenterZ

MajorX

MajorY
MajorZ
MinorX
MinorY
MinorZ

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::CreateEllipse2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreateEllipseVB Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateEllipseVB Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateEllipseVB](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateEllipseVB( _  
    ByVal CenterX As System.Double, _  
    ByVal CenterY As System.Double, _  
    ByVal CenterZ As System.Double, _  
    ByVal MajorX As System.Double, _  
    ByVal MajorY As System.Double, _  
    ByVal MajorZ As System.Double, _  
    ByVal MinorX As System.Double, _  
    ByVal MinorY As System.Double, _  
    ByVal MinorZ As System.Double _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim CenterX As System.Double  
Dim CenterY As System.Double  
Dim CenterZ As System.Double  
Dim MajorX As System.Double  
Dim MajorY As System.Double  
Dim MajorZ As System.Double  
Dim MinorX As System.Double  
Dim MinorY As System.Double  
Dim MinorZ As System.Double  
Dim value As System.Boolean
```

```
value = instance.CreateEllipseVB(CenterX, CenterY, CenterZ, MajorX, MajorY, MajorZ, MinorX,  
MinorY, MinorZ)
```

C#

```
System.bool CreateEllipseVB(  
    System.double CenterX,  
    System.double CenterY,  
    System.double CenterZ,  
    System.double MajorX,  
    System.double MajorY,  
    System.double MajorZ,  
    System.double MinorX,  
    System.double MinorY,
```

```
        System.double MinorZ  
    )
```

C++/CLI

```
System.bool CreateEllipseVB(  
    & System.double CenterX,  
    & System.double CenterY,  
    & System.double CenterZ,  
    & System.double MajorX,  
    & System.double MajorY,  
    & System.double MajorZ,  
    & System.double MinorX,  
    & System.double MinorY,  
    & System.double MinorZ  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

CenterX

CenterY

CenterZ

MajorX

MajorY

MajorZ

MinorX

MinorY

MinorZ

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreateEllipseVB](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

CreateEllipticalArc2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateEllipticalArc2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateEllipticalAr2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateEllipticalArc2(  
    ByVal CenterX As System.Double, _  
    ByVal CenterY As System.Double, _  
    ByVal CenterZ As System.Double, _  
    ByVal MajorX As System.Double, _  
    ByVal MajorY As System.Double, _  
    ByVal MajorZ As System.Double, _  
    ByVal MinorX As System.Double, _  
    ByVal MinorY As System.Double, _  
    ByVal MinorZ As System.Double, _  
    ByVal StartX As System.Double, _  
    ByVal StartY As System.Double, _  
    ByVal StartZ As System.Double, _  
    ByVal EndX As System.Double, _  
    ByVal EndY As System.Double, _
```

```
ByVal EndZ As System.Double _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim CenterX As System.Double  
Dim CenterY As System.Double  
Dim CenterZ As System.Double  
Dim MajorX As System.Double  
Dim MajorY As System.Double  
Dim MajorZ As System.Double  
Dim MinorX As System.Double  
Dim MinorY As System.Double  
Dim MinorZ As System.Double  
Dim StartX As System.Double  
Dim StartY As System.Double  
Dim StartZ As System.Double  
Dim EndX As System.Double  
Dim EndY As System.Double  
Dim EndZ As System.Double  
Dim value As System.Object  
  
value = instance.CreateEllipticalArc2(CenterX, CenterY, CenterZ, MajorX, MajorY, MajorZ, MinorX,  
MinorY, MinorZ, StartX, StartY, StartZ, EndX, EndY, EndZ)
```

C#

```
System.object CreateEllipticalArc2(  
    System.double CenterX,  
    System.double CenterY,  
    System.double CenterZ,  
    System.double MajorX,  
    System.double MajorY,  
    System.double MajorZ,  
    System.double MinorX,  
    System.double MinorY,  
    System.double MinorZ,  
    System.double StartX,  
    System.double StartY,  
    System.double StartZ,  
    System.double EndX,  
    System.double EndY,  
    System.double EndZ  
)
```

C++/CLI

```
System.Object^ CreateEllipticalArc2(  
& System.double CenterX,  
& System.double CenterY,  
& System.double CenterZ,  
& System.double MajorX,  
& System.double MajorY,  
& System.double MajorZ,  
& System.double MinorX,  
& System.double MinorY,  
& System.double MinorZ,  
& System.double StartX,  
& System.double StartY,  
& System.double StartZ,  
& System.double EndX,  
& System.double EndY,  
& System.double EndZ  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

CenterX

CenterY
CenterZ
MajorX
MajorY
MajorZ
MinorX
MinorY
MinorZ
StartX
StartY
StartZ
EndX
EndY
EndZ

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::CreateEllipticalArc2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreateEllipticalArcByCenter Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateEllipticalArcByCenter Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateEllipticalArcByCenter](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateEllipticalArcByCenter( _  
    ByVal Center As System.Object, _  
    ByVal Major As System.Object, _  
    ByVal Minor As System.Object, _  
    ByVal Start As System.Object, _  
    ByVal End As System.Object _  
    ) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Center As System.Object  
Dim Major As System.Object  
Dim Minor As System.Object  
Dim Start As System.Object  
Dim End As System.Object  
Dim value As System.Boolean
```

```
value = instance.CreateEllipticalArcByCenter(Center, Major, Minor, Start, End)
```

C#

```
System.bool CreateEllipticalArcByCenter(  
    System.object Center,  
    System.object Major,  
    System.object Minor,  
    System.object Start,
```

```
System.Object End  
)
```

C++/CLI

```
System.bool CreateEllipticalArcByCenter(  
& System.Object^ Center,  
& System.Object^ Major,  
& System.Object^ Minor,  
& System.Object^ Start,  
& System.Object^ End  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Center

Major

Minor

Start

End

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::CreateEllipticalArcByCenter](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreateEllipticalArcByCenterVB Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateEllipticalArcByCenterVB Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateEllipticalArcByCenterVB](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateEllipticalArcByCenterVB( _  
    ByVal CenterX As System.Double, _  
    ByVal CenterY As System.Double, _  
    ByVal CenterZ As System.Double, _  
    ByVal MajorX As System.Double, _  
    ByVal MajorY As System.Double, _  
    ByVal MajorZ As System.Double, _  
    ByVal MinorX As System.Double, _  
    ByVal MinorY As System.Double, _  
    ByVal MinorZ As System.Double, _  
    ByVal StartX As System.Double, _  
    ByVal StartY As System.Double, _  
    ByVal StartZ As System.Double, _  
    ByVal EndX As System.Double, _  
    ByVal EndY As System.Double, _  
    ByVal EndZ As System.Double _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim CenterX As System.Double  
Dim CenterY As System.Double  
Dim CenterZ As System.Double
```

```

Dim MajorX As System.Double
Dim MajorY As System.Double
Dim MajorZ As System.Double
Dim MinorX As System.Double
Dim MinorY As System.Double
Dim MinorZ As System.Double
Dim StartX As System.Double
Dim StartY As System.Double
Dim StartZ As System.Double
Dim EndX As System.Double
Dim EndY As System.Double
Dim EndZ As System.Double
Dim value As System.Boolean

```

```

value = instance.CreateEllipticalArcByCenterVB(CenterX, CenterY, CenterZ, MajorX, MajorY, MajorZ,
MinorX, MinorY, MinorZ, StartX, StartY, StartZ, EndX, EndY, EndZ)

```

C#

```

System.bool CreateEllipticalArcByCenterVB(
    System.double CenterX,
    System.double CenterY,
    System.double CenterZ,
    System.double MajorX,
    System.double MajorY,
    System.double MajorZ,
    System.double MinorX,
    System.double MinorY,
    System.double MinorZ,
    System.double StartX,
    System.double StartY,
    System.double StartZ,
    System.double EndX,
    System.double EndY,
    System.double EndZ
)

```

C++/CLI

```

System.bool CreateEllipticalArcByCenterVB(
& System.double CenterX,
& System.double CenterY,
& System.double CenterZ,
& System.double MajorX,
& System.double MajorY,
& System.double MajorZ,
& System.double MinorX,
& System.double MinorY,
& System.double MinorZ,
& System.double StartX,
& System.double StartY,
& System.double StartZ,
& System.double EndX,
& System.double EndY,
& System.double EndZ
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

CenterX

CenterY

CenterZ

MajorX

MajorY

MajorZ

MinorX

MinorY

MinorZ
StartX
StartY
StartZ
EndX
EndY
EndZ

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreateEllipticalArcByCenterVB](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreateFeatureMgrView Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateFeatureMgrView Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateFeatureManager](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateFeatureMgrView( _  
    ByRef Bitmap As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Bitmap As System.Integer  
Dim value As System.Object  
  
value = instance.CreateFeatureMgrView(Bitmap)
```

C#

```
System.Object CreateFeatureMgrView(  
    ref System.int Bitmap  
)
```

C++/CLI

```
System.Object^ CreateFeatureMgrView(  
    & System.int% Bitmap  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Bitmap

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreateFeatureMgrView](#).

See Also

CreateFeatureMgrView2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateFeatureMgrView2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateFeatureMgrView2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateFeatureMgrView2( _  
    ByRef Bitmap As System.Integer, _  
    ByVal ToolTip As System.String _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Bitmap As System.Integer  
Dim ToolTip As System.String  
Dim value As System.Object  
  
value = instance.CreateFeatureMgrView2(Bitmap, ToolTip)
```

C#

```
System.Object CreateFeatureMgrView2(  
    ref System.int Bitmap,  
    System.string ToolTip  
)
```

C++/CLI

```
System.Object^ CreateFeatureMgrView2(  
& System.int% Bitmap,  
& System.String^ ToolTip  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Bitmap

ToolTip

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreateFeatureMgrView2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

CreateFeatureMgrView3 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateFeatureMgrView3 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateFeatureMgrView3](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateFeatureMgrView3( _
    ByRef Bitmap As System.Integer, _
    ByVal ToolTip As System.String, _
    ByVal WhichPane As System.Integer _
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc
Dim Bitmap As System.Integer
Dim ToolTip As System.String
Dim WhichPane As System.Integer
Dim value As System.Object

value = instance.CreateFeatureMgrView3(Bitmap, ToolTip, WhichPane)
```

C#

```
System.Object CreateFeatureMgrView3(
    ref System.int Bitmap,
    System.string ToolTip,
    System.int WhichPane
)
```

C++/CLI

```
System.Object^ CreateFeatureMgrView3(
    & System.int% Bitmap,
    & System.String^ ToolTip,
    & System.int WhichPane
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Bitmap

ToolTip

WhichPane

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreateFeatureMgrView3](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreateGroup Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateGroup Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateGroup](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub CreateGroup()
```

Visual Basic (Usage)



```
Dim instance As IModelDoc
```

```
instance.CreateGroup()
```

C#

```
void CreateGroup()
```

C++/CLI

```
void CreateGroup();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreateGroup](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreateLine Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateLine Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateLine](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateLine( _  
    ByVal P1 As System.Object, _  
    ByVal P2 As System.Object _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim P1 As System.Object  
Dim P2 As System.Object  
Dim value As System.Boolean
```

```
value = instance.CreateLine(P1, P2)
```

C#

```
System.bool CreateLine(  
    System.object P1,  
    System.object P2  
)
```

C++/CLI

```
System.bool CreateLine(  
& System.Object^ P1,  
& System.Object^ P2  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

P1

P2

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::CreateLine](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreateLine2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateLine2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateLine2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateLine2( _  
    ByVal P1x As System.Double, _  
    ByVal P1y As System.Double, _  
    ByVal P1z As System.Double, _  
    ByVal P2x As System.Double, _  
    ByVal P2y As System.Double, _  
    ByVal P2z As System.Double _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim P1x As System.Double  
Dim P1y As System.Double  
Dim P1z As System.Double  
Dim P2x As System.Double  
Dim P2y As System.Double  
Dim P2z As System.Double  
Dim value As System.Object
```

```
value = instance.CreateLine2(P1x, P1y, P1z, P2x, P2y, P2z)
```

C#

```
System.object CreateLine2(  
    System.double P1x,  
    System.double P1y,  
    System.double P1z,  
    System.double P2x,  
    System.double P2y,  
    System.double P2z  
)
```

C++/CLI

```
System.Object^ CreateLine2(  
& System.double P1x,  
& System.double P1y,  
& System.double P1z,  
& System.double P2x,  
& System.double P2y,  
& System.double P2z  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

P1x

P1y

P1z

P2x

P2y

P2z

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreateLine2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

CreateLinearSketchStepAndRepeat Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateLinearSketchStepAndRepeat Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateLinearSketchStepAndRepeat](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateLinearSketchStepAndRepeat( _  
    ByVal NumX As System.Integer, _  
    ByVal NumY As System.Integer, _  
    ByVal SpacingX As System.Double, _  
    ByVal SpacingY As System.Double, _  
    ByVal AngleX As System.Double, _  
    ByVal AngleY As System.Double, _  
    ByVal DeleteInstances As System.String _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim NumX As System.Integer  
Dim NumY As System.Integer  
Dim SpacingX As System.Double  
Dim SpacingY As System.Double  
Dim AngleX As System.Double  
Dim AngleY As System.Double  
Dim DeleteInstances As System.String  
Dim value As System.Boolean
```

```
value = instance.CreateLinearSketchStepAndRepeat(NumX, NumY, SpacingX, SpacingY, AngleX, AngleY, DeleteInstances)
```

C#

```
System.bool CreateLinearSketchStepAndRepeat(  
    System.int NumX,  
    System.int NumY,  
    System.double SpacingX,  
    System.double SpacingY,  
    System.double AngleX,  
    System.double AngleY,  
    System.string DeleteInstances  
)
```

C++/CLI

```
System.bool CreateLinearSketchStepAndRepeat(  
& System.int NumX,  
& System.int NumY,  
& System.double SpacingX,
```

```

& System.double SpacingY,
& System.double AngleX,
& System.double AngleY,
& System.String^ DeleteInstances
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

NumX

NumY

SpacingX

SpacingY

AngleX

AngleY

DeleteInstances

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreateLinearSketchStepAndRepeat](#).

See Also

[IModelDoc Interface](#)

[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreateLineDB Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateLineDB Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateLineDB](#).

.NET Syntax

Visual Basic (Declaration)

```

Function CreateLineDB( _
    ByVal Sx As System.Double, _
    ByVal Sy As System.Double, _
    ByVal Sz As System.Double, _
    ByVal Ex As System.Double, _
    ByVal Ey As System.Double, _
    ByVal Ez As System.Double _
) As System.Boolean

```

Visual Basic (Usage)



```

Dim instance As IModelDoc
Dim Sx As System.Double
Dim Sy As System.Double
Dim Sz As System.Double
Dim Ex As System.Double
Dim Ey As System.Double
Dim Ez As System.Double
Dim value As System.Boolean

```

```
value = instance.CreateLineDB(Sx, Sy, Sz, Ex, Ey, Ez)
```

C#

```

System.bool CreatelineDB(
    System.double Sx,
    System.double Sy,
    System.double Sz,
    System.double Ex,

```

```
System.double Ey,  
System.double Ez  
)
```

C++/CLI

```
System.bool CreateLineDB(  
& System.double Sx,  
& System.double Sy,  
& System.double Sz,  
& System.double Ex,  
& System.double Ey,  
& System.double Ez  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Sx

Sy

Sz

Ex

Ey

Ez

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreateLineDB](#).

See Also

[IModelDoc Interface](#)

[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

CreateLineVB Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateLineVB Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateLineVB](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub CreateLineVB( _  
    ByVal X1 As System.Double, _  
    ByVal Y1 As System.Double, _  
    ByVal Z1 As System.Double, _  
    ByVal X2 As System.Double, _  
    ByVal Y2 As System.Double, _  
    ByVal Z2 As System.Double _  
)
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim X1 As System.Double  
Dim Y1 As System.Double  
Dim Z1 As System.Double  
Dim X2 As System.Double  
Dim Y2 As System.Double  
Dim Z2 As System.Double
```

```
instance.CreateLineVB(X1, Y1, Z1, X2, Y2, Z2)
```

C#

```
void CreateLineVB(  
    System.double X1,  
    System.double Y1,  
    System.double Z1,  
    System.double X2,  
    System.double Y2,  
    System.double Z2  
)
```

C++/CLI

```
void CreateLineVB(  
& System.double X1,  
& System.double Y1,  
& System.double Z1,  
& System.double X2,  
& System.double Y2,  
& System.double Z2  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

[X1](#)

[Y1](#)

[Z1](#)

[X2](#)

[Y2](#)

[Z2](#)

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreateLineVB](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreatePlaneAtAngle Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreatePlaneAtAngle Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreatePlaneAtAngle](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub CreatePlaneAtAngle( _  
    ByVal Val As System.Double, _  
    ByVal FlipDir As System.Boolean _  
)
```

Visual Basic (Usage)

```
Dim instance As IModelDoc  
Dim Val As System.Double  
Dim FlipDir As System.Boolean  
  
instance.CreatePlaneAtAngle(Val, FlipDir)
```

C#



```
void CreatePlaneAtAngle(  
    System.double Val,  
    System.bool FlipDir  
)
```

C++/CLI

```
void CreatePlaneAtAngle(  
& System.double Val,  
& System.bool FlipDir  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Val

FlipDir

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreatePlaneAtAngle](#).

See Also

[IModelDoc Interface](#)

[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreatePlaneAtAngle2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreatePlaneAtAngle2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreatePlaneAtAngle2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreatePlaneAtAngle2( _  
    ByVal Val As System.Double, _  
    ByVal FlipDir As System.Boolean _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Val As System.Double  
Dim FlipDir As System.Boolean  
Dim value As System.Object
```

```
value = instance.CreatePlaneAtAngle2(Val, FlipDir)
```

C#

```
System.object CreatePlaneAtAngle2(  
    System.double Val,  
    System.bool FlipDir  
)
```

C++/CLI

```
System.Object^ CreatePlaneAtAngle2(  
& System.double Val,  
& System.bool FlipDir  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Val

FlipDir

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreatePlaneAtAngle2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

CreatePlaneAtOffset Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreatePlaneAtOffset Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreatePlaneAtOffset](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub CreatePlaneAtOffset( _  
    ByVal Val As System.Double, _  
    ByVal FlipDir As System.Boolean _  
)
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Val As System.Double  
Dim FlipDir As System.Boolean  
  
instance.CreatePlaneAtOffset(Val, FlipDir)
```

C#

```
void CreatePlaneAtOffset(  
    System.double Val,  
    System.bool FlipDir  
)
```

C++/CLI

```
void CreatePlaneAtOffset(  
&    System.double Val,  
&    System.bool FlipDir  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Val

FlipDir

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreatePlaneAtOffset](#).

See Also

CreatePlaneAtOffset2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreatePlaneAtOffset2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreatePlaneAtOffset2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreatePlaneAtOffset2( _  
    ByVal Val As System.Double, _  
    ByVal FlipDir As System.Boolean _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Val As System.Double  
Dim FlipDir As System.Boolean  
Dim value As System.Object  
  
value = instance.CreatePlaneAtOffset2(Val, FlipDir)
```

C#

```
System.object CreatePlaneAtOffset2(  
    System.double Val,  
    System.bool FlipDir  
)
```

C++/CLI

```
System.Object^ CreatePlaneAtOffset2(  
& System.double Val,  
& System.bool FlipDir  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Val

FlipDir

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreatePlaneAtOffset2](#).

See Also

CreatePlaneAtSurface Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreatePlaneAtSurface Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreatePlaneAtSurface](#).

.NET Syntax

Visual Basic (Declaration)

```

Sub CreatePlaneAtSurface( _
    ByVal InterIndex As System.Integer, _
    ByVal ProjOpt As System.Boolean, _
    ByVal ReverseDir As System.Boolean, _
    ByVal NormalPlane As System.Boolean, _
    ByVal Angle As System.Double _
)

```

Visual Basic (Usage)



```

Dim instance As IModelDoc
Dim InterIndex As System.Integer
Dim ProjOpt As System.Boolean
Dim ReverseDir As System.Boolean
Dim NormalPlane As System.Boolean
Dim Angle As System.Double

instance.CreatePlaneAtSurface(InterIndex, ProjOpt, ReverseDir, NormalPlane, Angle)

```

C#

```

void CreatePlaneAtSurface(
    System.int InterIndex,
    System.bool ProjOpt,
    System.bool ReverseDir,
    System.bool NormalPlane,
    System.double Angle
)

```

C++/CLI

```

void CreatePlaneAtSurface(
    & System.int InterIndex,
    & System.bool ProjOpt,
    & System.bool ReverseDir,
    & System.bool NormalPlane,
    & System.double Angle
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

InterIndex

ProjOpt

ReverseDir

NormalPlane

Angle

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreatePlaneAtSurface](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

CreatePlaneAtSurface2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreatePlaneAtSurface2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreatePlaneAtSurface2](#).

.NET Syntax

```
Function CreatePlaneAtSurface2( _
    ByVal InterIndex As System.Integer, _
    ByVal ProjOpt As System.Boolean, _
    ByVal ReverseDir As System.Boolean, _
    ByVal NormalPlane As System.Boolean, _
    ByVal Angle As System.Double _
) As System.Object
```



```
Dim instance As IModelDoc
Dim InterIndex As System.Integer
Dim ProjOpt As System.Boolean
Dim ReverseDir As System.Boolean
Dim NormalPlane As System.Boolean
Dim Angle As System.Double
Dim value As System.Object

value = instance.CreatePlaneAtSurface2(InterIndex, ProjOpt, ReverseDir, NormalPlane, Angle)
```

```
System.object CreatePlaneAtSurface2(
    System.int InterIndex,
    System.bool ProjOpt,
    System.bool ReverseDir,
    System.bool NormalPlane,
    System.double Angle
)
```

```
System.Object^ CreatePlaneAtSurface2(
    & System.int InterIndex,
    & System.bool ProjOpt,
    & System.bool ReverseDir,
    & System.bool NormalPlane,
    & System.double Angle
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

InterIndex

ProjOpt

ReverseDir

NormalPlane

Angle

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreatePlaneAtSurface2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

CreatePlaneFixed Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreatePlaneFixed Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreatePlaneFixed](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreatePlaneFixed( _  
    ByVal P1 As System.Object, _  
    ByVal P2 As System.Object, _  
    ByVal P3 As System.Object, _  
    ByVal UseGlobal As System.Boolean _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim P1 As System.Object  
Dim P2 As System.Object  
Dim P3 As System.Object  
Dim UseGlobal As System.Boolean  
Dim value As System.Boolean  
  
value = instance.CreatePlaneFixed(P1, P2, P3, UseGlobal)
```

C#

```
System.bool CreatePlaneFixed(  
    System.object P1,  
    System.object P2,  
    System.object P3,  
    System.bool UseGlobal  
)
```

C++/CLI

```
System.bool CreatePlaneFixed(  
& System.Object^ P1,  
& System.Object^ P2,  
& System.Object^ P3,  
& System.bool UseGlobal  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

P1

P2

P3

UseGlobal

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreatePlaneFixed](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreatePlanePerCurveAndPassPoint Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreatePlanePerCurveAndPassPoint Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreatePlanePerCurveAndPassPoint](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub CreatePlanePerCurveAndPassPoint( _  
    ByVal OrigAtCurve As System.Boolean _  
)
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim OrigAtCurve As System.Boolean  
  
instance.CreatePlanePerCurveAndPassPoint(OrigAtCurve)
```

C#

```
void CreatePlanePerCurveAndPassPoint(  
    System.bool OrigAtCurve  
)
```

C++/CLI

```
void CreatePlanePerCurveAndPassPoint(  
& System.bool OrigAtCurve  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

OrigAtCurve

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreatePlanePerCurveAndPassPoint](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreatePlanePerCurveAndPassPoint2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreatePlanePerCurveAndPassPoint2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreatePlanePerCurveAndPassPoint2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreatePlanePerCurveAndPassPoint2( _  
    ByVal OrigAtCurve As System.Boolean _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim OrigAtCurve As System.Boolean  
Dim value As System.Object  
  
value = instance.CreatePlanePerCurveAndPassPoint2(OrigAtCurve)
```

C#

```
System.object CreatePlanePerCurveAndPassPoint2(  
    System.bool OrigAtCurve  
)
```

C++/CLI

```
System.Object^ CreatePlanePerCurveAndPassPoint2(  
& System.bool OrigAtCurve  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

OrigAtCurve

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreatePlanePerCurveAndPassPoint2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreatePlaneThru3Points Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreatePlaneThru3Points Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreatePlaneThru3Points](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub CreatePlaneThru3Points()
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
  
instance.CreatePlaneThru3Points()
```

C#

```
void CreatePlaneThru3Points()
```

C++/CLI

```
void CreatePlaneThru3Points();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreatePlaneThru3Points](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreatePlaneThru3Points2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreatePlaneThru3Points2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreatePlaneThru3Points2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreatePlaneThru3Points2() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim value As System.Object  
  
value = instance.CreatePlaneThru3Points2()
```

C#

```
System.object CreatePlaneThru3Points2()
```

C++/CLI

```
System.Object^ CreatePlaneThru3Points2();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::CreatePlaneThru3Points2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreatePoint Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreatePoint Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreatePoint](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreatePoint( _  
    ByVal PointX As System.Double, _  
    ByVal PointY As System.Double, _  
    ByVal PointZ As System.Double _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim PointX As System.Double  
Dim PointY As System.Double  
Dim PointZ As System.Double  
Dim value As System.Boolean  
  
value = instance.CreatePoint(PointX, PointY, PointZ)
```

C#

```
System.bool CreatePoint(  
    System.double PointX,  
    System.double PointY,  
    System.double PointZ  
)
```

C++/CLI

```
System.bool CreatePoint(  
    & System.double PointX,  
    & System.double PointY,  
    & System.double PointZ  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

PointX

PointY

PointZ

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::CreatePoint](#).

See Also

[IModelDoc Interface](#)

[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreatePoint2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreatePoint2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreatePoint2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreatePoint2( _  
    ByVal PointX As System.Double, _  
    ByVal PointY As System.Double, _  
    ByVal PointZ As System.Double _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim PointX As System.Double  
Dim PointY As System.Double  
Dim PointZ As System.Double  
Dim value As System.Object
```

```
value = instance.CreatePoint2(PointX, PointY, PointZ)
```

C#

```
System.object CreatePoint2(  
    System.double PointX,  
    System.double PointY,  
    System.double PointZ  
)
```

C++/CLI

```
System.Object^ CreatePoint2(  
    & System.double PointX,  
    & System.double PointY,  
    & System.double PointZ  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

PointX

PointY

PointZ

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreatePoint2](#).

See Also

[IModelDoc Interface](#)

[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreatePointDB Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreatePointDB Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreatePointDB](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreatePointDB(  
    ByVal X As System.Double, _  
    ByVal Y As System.Double, _  
    ByVal Z As System.Double _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim X As System.Double  
Dim Y As System.Double  
Dim Z As System.Double  
Dim value As System.Boolean  
  
value = instance.CreatePointDB(X, Y, Z)
```

C#

```
System.bool CreatePointDB(  
    System.double X,  
    System.double Y,  
    System.double Z  
)
```

C++/CLI

```
System.bool CreatePointDB(  
& System.double X,  
& System.double Y,  
& System.double Z  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

X

Y

Z

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreatePointDB](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreateSpline Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateSpline Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateSpline](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateSpline( _  
    ByVal PointData As System.Object _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim PointData As System.Object  
Dim value As System.Object  
  
value = instance.CreateSpline(PointData)
```

C#

```
System.object CreateSpline(  
    System.object PointData  
)
```

C++/CLI

```
System.Object^ CreateSpline(  
& System.Object^ PointData  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

PointData

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreateSpline](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreateSplineByEqnParams Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateSplineByEqnParams Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateSplineByEqnParams](#).

Visual Basic Syntax

Visual Basic (Declaration)

```
Function CreateSplineByEqnParams( _  
    ByVal ParamsIn As System.Object _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim ParamsIn As System.Object  
Dim value As System.Object  
  
value = instance.CreateSplineByEqnParams(ParamsIn)
```

C#

```
System.object CreateSplineByEqnParams(  
    System.object ParamsIn  
)
```

C++/CLI

```
System.Object^ CreateSplineByEqnParams(  
& System.Object^ ParamsIn  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ParamsIn

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::CreateSplineByEqnParams](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreateSplinesByEqnParams Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateSplinesByEqnParams Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateSplinesByEqnParams](#).

Visual Basic Syntax

Visual Basic (Declaration)

```
Function CreateSplinesByEqnParams( _  
    ByVal ParamsIn As System.Object _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim ParamsIn As System.Object  
Dim value As System.Object  
  
value = instance.CreateSplinesByEqnParams(ParamsIn)
```

C#

```
System.object CreateSplinesByEqnParams(  
    System.object ParamsIn  
)
```

C++/CLI

```
System.Object^ CreateSplinesByEqnParams(  
& System.Object^ ParamsIn  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ParamsIn

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreateSplinesByEqnParams](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreateTangentArc Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateTangentArc Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateTangentArc](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateTangentArc( _  
    ByVal P1x As System.Double, _  
    ByVal P1y As System.Double, _  
    ByVal P1z As System.Double, _  
    ByVal P2x As System.Double, _  
    ByVal P2y As System.Double, _  
    ByVal P2z As System.Double _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim P1x As System.Double  
Dim P1y As System.Double  
Dim P1z As System.Double  
Dim P2x As System.Double  
Dim P2y As System.Double  
Dim P2z As System.Double  
Dim value As System.Boolean
```

```
value = instance.CreateTangentArc(P1x, P1y, P1z, P2x, P2y, P2z)
```

C#

```
System.bool CreateTangentArc(  
    System.double P1x,  
    System.double P1y,  
    System.double P1z,  
    System.double P2x,  
    System.double P2y,
```

```
        System.double P2z  
    )
```

C++/CLI

```
System.bool CreateTangentArc(  
    & System.double P1x,  
    & System.double P1y,  
    & System.double P1z,  
    & System.double P2x,  
    & System.double P2y,  
    & System.double P2z  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

P1x

P1y

P1z

P2x

P2y

P2z

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreateTangentArc](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreateTangentArc2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CreateTangentArc2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CreateTangentArc2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateTangentArc2( _  
    ByVal P1x As System.Double, _  
    ByVal P1y As System.Double, _  
    ByVal P1z As System.Double, _  
    ByVal P2x As System.Double, _  
    ByVal P2y As System.Double, _  
    ByVal P2z As System.Double, _  
    ByVal ArcTypeIn As System.Integer _  
    ) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim P1x As System.Double  
Dim P1y As System.Double  
Dim P1z As System.Double  
Dim P2x As System.Double  
Dim P2y As System.Double  
Dim P2z As System.Double  
Dim ArcTypeIn As System.Integer  
Dim value As System.Boolean
```

```
value = instance.CreateTangentArc2(P1x, P1y, P1z, P2x, P2y, P2z, ArcTypeIn)
```

C#

```
System.bool CreateTangentArc2(  
    System.double P1x,  
    System.double P1y,  
    System.double P1z,  
    System.double P2x,  
    System.double P2y,  
    System.double P2z,  
    System.int ArcTypeIn  
)
```

C++/CLI

```
System.bool CreateTangentArc2(  
& System.double P1x,  
& System.double P1y,  
& System.double P1z,  
& System.double P2x,  
& System.double P2y,  
& System.double P2z,  
& System.int ArcTypeIn  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

P1x

P1y

P1z

P2x

P2y

P2z

ArcTypeIn

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CreateTangentArc2](#).

See Also

[IModelDoc Interface](#)

[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CustomInfo Property (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CustomInfo Property (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CustomInfo](#).

.NET Syntax

Visual Basic (Declaration)

```
Property CustomInfo( _  
    ByVal FieldName As System.String _  
) As System.String
```

Visual Basic (Usage)



```

Dim instance As IModelDoc
Dim FieldName As System.String
Dim value As System.String

instance.CustomInfo(FieldName) = value

value = instance.CustomInfo(FieldName)

```

C#

```

System.string CustomInfo(
    System.string FieldName
) {get; set;}

```

C++/CLI

```

property System.String^ CustomInfo {
    System.String^ get(System.String^ FieldName);
    void set (System.String^ FieldName, System.String^ value);
}

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

FieldName

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CustomInfo](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

CustomInfo2 Property (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : CustomInfo2 Property (IModelDoc)

Obsolete. Superseded by [IModelDoc2::CustomInfo2](#).

.NET Syntax

Visual Basic (Declaration)

```

Property CustomInfo2( _
    ByVal Configuration As System.String, _
    ByVal FieldName As System.String _
) As System.String

```

Visual Basic (Usage)



```

Dim instance As IModelDoc
Dim Configuration As System.String
Dim FieldName As System.String
Dim value As System.String

instance.CustomInfo2(Configuration, FieldName) = value

value = instance.CustomInfo2(Configuration, FieldName)

```

C#

```

System.string CustomInfo2(
    System.string Configuration,

```

```
System.string FieldName
) {get; set;}
```

C++/CLI

```
property System.String^ CustomInfo2 {
    System.String^ get(System.String^ Configuration, System.String^ FieldName);
    void set (System.String^ Configuration, System.String^ FieldName, System.String^ value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Configuration

FieldName

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::CustomInfo2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

DeActivateFeatureMgrView Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : DeActivateFeatureMgrView Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::DeActivateFeatureMgrView](#).

.NET Syntax

Visual Basic (Declaration)

```
Function DeActivateFeatureMgrView( _
    ByRef AppView As System.Integer _
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc
Dim AppView As System.Integer
Dim value As System.Boolean
```

```
value = instance.DeActivateFeatureMgrView(AppView)
```

C#

```
System.bool DeActivateFeatureMgrView(
    ref System.int AppView
)
```

C++/CLI

```
System.bool DeActivateFeatureMgrView(
    & System.int% AppView
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AppView

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::DeActivateFeatureMgrView](#).

 See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

DebugCheckIgesGeom Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : DebugCheckIgesGeom Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::DebugCheckIgesGeom](#).

 .NET Syntax

Visual Basic (Declaration)

Sub DebugCheckIgesGeom()

Visual Basic (Usage)



```
Dim instance As IModelDoc  
instance.DebugCheckIgesGeom()
```

C#

```
void DebugCheckIgesGeom()
```

C++/CLI

```
void DebugCheckIgesGeom();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

 Visual Basic for Applications (VBA) Syntax

See [ModelDoc::DebugCheckIgesGeom](#).

 See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

DeleteAllRelations Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : DeleteAllRelations Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::DeleteAllRelations](#).

 .NET Syntax

Visual Basic (Declaration)

Sub DeleteAllRelations()

Visual Basic (Usage)



```
Dim instance As IModelDoc  
instance.DeleteAllRelations()
```

C#

```
void DeleteAllRelations()
```

C++/CLI

```
void DeleteAllRelations();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::DeleteAllRelations](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

DeleteBendTable Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : DeleteBendTable Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::DeleteBendTable](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub DeleteBendTable()
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
instance.DeleteBendTable()
```

C#

```
void DeleteBendTable()
```

C++/CLI

```
void DeleteBendTable();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::DeleteBendTable](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

DeleteBkgImage Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : DeleteBkgImage Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::DeleteBkgImage](#).

.NET Syntax

Visual Basic (Declaration)

Sub DeleteBkgImage()

Visual Basic (Usage)



```
Dim instance As IModelDoc  
instance.DeleteBkgImage()
```

C#

```
void DeleteBkgImage()
```

C++/CLI

```
void DeleteBkgImage();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::DeleteBkgImage](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

DeleteConfiguration Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : DeleteConfiguration Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::DeleteConfiguration](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub DeleteConfiguration( _  
    ByVal ConfigurationName As System.String _  
)
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim ConfigurationName As System.String  
instance.DeleteConfiguration(ConfigurationName)
```

C#

```
void DeleteConfiguration(  
    System.string ConfigurationName  
)
```

C++/CLI

```
void DeleteConfiguration(  
& System.String^ ConfigurationName  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ConfigurationName

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::DeleteConfiguration](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

DeleteConfiguration2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : DeleteConfiguration2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::DeleteConfiguration2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function DeleteConfiguration2( _  
    ByVal ConfigurationName As System.String _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim ConfigurationName As System.String  
Dim value As System.Boolean  
  
value = instance.DeleteConfiguration2(ConfigurationName)
```

C#

```
System.bool DeleteConfiguration2(  
    System.string ConfigurationName  
)
```

C++/CLI

```
System.bool DeleteConfiguration2(  
& System.String^ ConfigurationName  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ConfigurationName

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::DeleteConfiguration2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

DeleteCustomInfo Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : DeleteCustomInfo Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::DeleteCustomInfo](#).

.NET Syntax

Visual Basic (Declaration)

```
Function DeleteCustomInfo( _  
    ByVal FieldName As System.String _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim FieldName As System.String  
Dim value As System.Boolean  
  
value = instance.DeleteCustomInfo(FieldName)
```

C#

```
System.bool DeleteCustomInfo(  
    System.string FieldName  
)
```

C++/CLI

```
System.bool DeleteCustomInfo(  
& System.String^ FieldName  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

FieldName

Visual Basic for Applications (VBA) Syntax

See [ModelDoc2::DeleteCustomInfo](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

DeleteCustomInfo2 Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : DeleteCustomInfo2 Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::DeleteCustomInfo2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function DeleteCustomInfo2( _  
    ByVal Configuration As System.String, _  
    ByVal FieldName As System.String _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim Configuration As System.String  
Dim FieldName As System.String  
Dim value As System.Boolean  
  
value = instance.DeleteCustomInfo2(Configuration, FieldName)
```

C#

```
System.bool DeleteCustomInfo2(  
    System.string Configuration,  
    System.string FieldName  
)
```

C++/CLI

```
System.bool DeleteCustomInfo2(  
& System.String^ Configuration,  
& System.String^ FieldName  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Configuration

FieldName

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::DeleteCustomInfo2](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

DeleteDesignTable Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : DeleteDesignTable Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::DeleteDesignTable](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub DeleteDesignTable()
```

Visual Basic (Usage)

```
Dim instance As IModelDoc  
instance.DeleteDesignTable()
```

C#

```
void DeleteDesignTable()
```

C++/CLI

```
void DeleteDesignTable();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::DeleteDesignTable](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

 Copy Code

DeleteFeatureMgrView Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : DeleteFeatureMgrView Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::DeleteFeatureMgrView](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub DeleteFeatureMgrView( _  
    ByRef AppView As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim AppView As System.Integer  
  
instance.DeleteFeatureMgrView(AppView)
```

C#

```
void DeleteFeatureMgrView(  
    ref System.int AppView  
)
```

C++/CLI

```
void DeleteFeatureMgrView(  
& System.int% AppView  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

AppView

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::DeleteFeatureMgrView](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

DeleteLightSource Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : DeleteLightSource Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::DeleteLightSource](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub DeleteLightSource( _  
    ByVal ID As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim ID As System.Integer  
  
instance.DeleteLightSource(ID)
```

C#

```
void DeleteLightSource(  
    System.int ID  
)
```

C++/CLI

```
void DeleteLightSource(  
    & System.int ID  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ID

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::DeleteLightSource](#).

See Also

[IModelDoc Interface](#)
[IModelDoc Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

DeleteNamedView Method (IModelDoc)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelDoc Interface](#) : DeleteNamedView Method (IModelDoc)

Obsolete. Superseded by [IModelDoc2::DeleteNamedView](#).

.NET Syntax

Visual Basic (Declaration)

```
Function DeleteNamedView( _  
    ByVal ViewName As System.String _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelDoc  
Dim ViewName As System.String  
Dim value As System.Boolean  
  
value = instance.DeleteNamedView(ViewName)
```

C#

```
System.bool DeleteNamedView(  
    System.string ViewName  
)
```

C++/CLI

```
System.bool DeleteNamedView(  
    & System.String^ ViewName  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ViewName

Visual Basic for Applications (VBA) Syntax

See [ModelDoc::DeleteNamedView](#).

See Also

[IModelDoc Interface](#)

[IModelDoc Members](#)