

SOLIDWORKS API (VB6 COM) — Reference (12/102): Component2-ConcentricMateFeatureData

SOLIDWORKS API Documentation (converted from CHM)

Component2 (Type)

SOLIDWORKS Type Library
Component2 Object

Object Model

Component2

- EnumBodies (EnumBodies2)
- EnumBodies2
- EnumBodies3 (EnumBodies2)
- EnumRelatedBodies (EnumBodies2)
- EnumSectionedBodies (EnumBodies2)
- FeatureByName (Feature)
- FirstFeature (Feature)
- GetDrawingComponent (DrawingComponent)
- GetModelTexture (Texture)
- GetParent (Component2)
- GetTexture (Texture)
- GetTotalTransform (MathTransform)
- IFindAttribute (Attribute)
- IGetBody (Body2)
- IGetChildren (Component2)
- IGetCorrespondingEntity (Entity)
- IGetDecals (Decal)
- IGetModelDoc (ModelDoc2)
- IGetRenderMaterials (RenderMaterial)
- PresentationTransform (MathTransform)
- Transform (MathTransform)
- Transform2 (MathTransform)

SOLIDWORKS Type Library
Component2 Object Members

Public Methods

- [AddPropertyExtension](#)
- [DeSelect](#)

	
	EnumBodies
	EnumBodies2
	EnumBodies3
	EnumRelatedBodies
	EnumSectionedBodies
	FeatureByName
	FindAttribute
	FirstFeature
	GetBodies
	GetBodies2
	GetBodies3
	GetBody
	GetBox
	GetChildren
	GetConfigurationCount
	GetConfigurationNames
	GetConstrainedStatus
	GetCorresponding
	GetCorrespondingEntity
	GetDecals
	GetDecalsCount
	GetDrawingComponent
	GetExcludeFromBOM2
	GetHiddenUnloadedChildrenCount
	GetID
	GetImportedPath
	GetMaterialIdName
	GetMaterialPropertyValues2
	GetMaterialUserName
	GetMates
	GetModelDoc
	GetModelDoc2
	GetModelMaterialPropertyValues
	GetModelTexture
	GetParent
	GetPathName
	GetPLMID
	GetPropertyExtension
	GetReferencedDisplayStates
	GetRemainingDOFs
	GetRenderMaterials
	GetRenderMaterials2
	GetRenderMaterialsCount

	
	<u>GetRenderMaterialsCount2</u>
	<u>GetRepresentationParent</u>
	<u>GetSectionedBodies</u>
	<u>GetSelectByIDString</u>
	<u>GetSmartComponentData</u>
	<u>GetSpecificTransform</u>
	<u>GetSuppression</u>
	<u>GetSuppression2</u>
	<u>GetTessNorms</u>
	<u>GetTessTriangles</u>
	<u>GetTessTriStripEdges</u>
	<u>GetTessTriStripNorms</u>
	<u>GetTessTriStrips</u>
	<u>GetTexture</u>
	<u>GetTotalTransform</u>
	<u>GetType</u>
	<u>GetUnloadedComponentNames</u>
	<u>GetVisibility</u>
	<u>GetVisibilityInAsmDisplayStates</u>
	<u>GetXform</u>
	<u>HasAssemblyFeatures</u>
	<u>HasMaterialPropertyValues</u>
	<u>HasUnloadedComponents</u>
	<u>IFindAttribute</u>
	<u>IGetBody</u>
	<u>IGetBox</u>
	<u>IGetChildren</u>
	<u>IGetChildrenCount</u>
	<u>IGetCorrespondingEntity</u>
	<u>IGetDecals</u>
	<u>IGetMaterialPropertyValues2</u>
	<u>IGetMaterialPropertyValuesForFace</u>
	<u>IGetModelDoc</u>
	<u>IGetModelMaterialPropertyValues</u>
	<u>IGetRenderMaterials</u>
	<u>IGetTemporaryBodyID</u>
	<u>IGetTessNorms</u>
	<u>IGetTessTriangleCount</u>
	<u>IGetTessTriangles</u>
	<u>IGetTessTriStripEdges</u>
	<u>IGetTessTriStripEdgeSize</u>
	<u>IGetTessTriStripNorms</u>
	<u>IGetTessTriStrips</u>

	
	IGetTessTriStripSize
	IGetVisibility
	IGetXform
	IListExternalFileReferences
	IListExternalFileReferences2
	IRemoveMaterialProperty2
	IsDisplayDataOutOfDate
	IsEnvelope
	ISetMaterialPropertyValues2
	ISetVisibility
	ISetXform
	ISetXformAndSolve
	IsFixed
	IsHidden
	IsLoaded
	IsMirrored
	IsNameOveridden
	IsPatternInstance
	IsRoot
	IsSmartComponent
	IsSuppressed
	ListExternalFileReferences
	ListExternalFileReferences2
	ListExternalFileReferencesCount
	MakeVirtual
	MakeVirtual2
	RemoveMaterialProperty
	RemoveMaterialProperty2
	RemovePresentationTransform
	RemoveTexture
	RemoveTextureByDisplayState
	ReplaceReference
	ResetPropertyExtension
	SaveVirtualComponent
	Select
	Select2
	Select3
	Select4
	SelectByMark
	SetCosmosWorksMaterial
	SetExcludeFromBOM2
	SetMaterialIdName
	SetMaterialPropertyValues2

SetMaterialUserName
SetReferencedDisplayStates
SetSmartComponentData
SetSuppression
SetSuppression2
SetTexture
SetTextureByDisplayState
SetTransformAndSolve
SetTransformAndSolve2
SetTransformAndSolve3
SetVisibility
SetVisibilityInAsmDisplayStates
SetXform
SetXformAndSolve
UpdateExternalFileReferences

Public Properties

ComponentReference
CustomPropertyManager
DisplayTitle
ExcludeFromBOM
IMaterialPropertyValues
IsGraphicsOnly
IsSpeedPak
IsVirtual
MaterialPropertyValues
Name
Name2
PresentationTransform
ReferencedConfiguration
ReferencedDisplayState
ReferencedDisplayState2
Solving
Transform
Transform2
UseNamedConfiguration
Visible

SOLIDWORKS Type Library

AddPropertyExtension Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddPropertyExtension( _
    ByVal PropertyExtension As Variant _
```

) As Long

SOLIDWORKS Type Library

ComponentReference Property (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property ComponentReference As String
```

SOLIDWORKS Type Library

CustomPropertyManager Property (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property CustomPropertyManager( _  
    ByVal ConfigurationName As String _  
) As Object
```

SOLIDWORKS Type Library

DeSelect Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function DeSelect() As Boolean
```

SOLIDWORKS Type Library

DisplayTitle Property (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property DisplayTitle As String
```

SOLIDWORKS Type Library

EnumBodies Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function EnumBodies( _  
    ByVal BodyType As Long _  
) As EnumBodies2
```

SOLIDWORKS Type Library

EnumBodies2 Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function EnumBodies2( _  
    ByVal BodyType As Long _  
) As EnumBodies2
```

SOLIDWORKS Type Library

EnumBodies3 Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function EnumBodies3( _  
    ByVal BodyType As Long, _
```

```
ByVal VisibleOnly As Boolean _  
) As EnumBodies2
```

SOLIDWORKS Type Library

EnumRelatedBodies Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function EnumRelatedBodies() As EnumBodies2
```

SOLIDWORKS Type Library

EnumSectionedBodies Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function EnumSectionedBodies( _  
    ByVal ViewIn As ModelView _  
) As EnumBodies2
```

SOLIDWORKS Type Library

ExcludeFromBOM Property (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property ExcludeFromBOM As Boolean
```

SOLIDWORKS Type Library

FeatureByName Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function FeatureByName( _  
    ByVal Name As String _  
) As Feature
```

SOLIDWORKS Type Library

FindAttribute Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function FindAttribute( _  
    ByVal AttributeDef As Object, _  
    ByVal WhichOne As Long _  
) As Object
```

SOLIDWORKS Type Library

FirstFeature Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function FirstFeature() As Feature
```

SOLIDWORKS Type Library

GetBodies Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetBodies( _  
    ByVal BodyType As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetBodies2 Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetBodies2( _  
    ByVal BodyType As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetBodies3 Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetBodies3( _  
    ByVal BodyType As Long, _  
    ByRef BodiesInfo As Variant _  
) As Variant
```

SOLIDWORKS Type Library

GetBody Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetBody() As Object
```

SOLIDWORKS Type Library

GetBox Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetBox( _  
    ByVal IncludeRefPlanes As Boolean, _  
    ByVal IncludeSketches As Boolean _  
) As Variant
```

SOLIDWORKS Type Library

GetChildren Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetChildren() As Variant
```

SOLIDWORKS Type Library

GetConfigurationCount Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetConfigurationCount() As Long
```

SOLIDWORKS Type Library

GetConfigurationNames Method (Component2)

Syntax

```
Public Function GetConfigurationNames() As Variant
```

SOLIDWORKS Type Library

GetConstrainedStatus Method (Component2)

Visual Basic for Applications (VBA)

```
Public Function GetConstrainedStatus() As Long
```

SOLIDWORKS Type Library

GetCorresponding Method (Component2)

Visual Basic for Applications (VBA)

```
Public Function GetCorresponding( _  
    ByVal InputObject As Object _  
) As Object
```

SOLIDWORKS Type Library

GetCorrespondingEntity Method (Component2)

Visual Basic for Applications (VBA)

```
Public Function GetCorrespondingEntity( _  
    ByVal Entity As Object _  
) As Object
```

SOLIDWORKS Type Library

GetDecals Method (Component2)

Visual Basic for Applications (VBA)

```
Public Function GetDecals() As Variant
```

SOLIDWORKS Type Library

GetDecalsCount Method (Component2)

Visual Basic for Applications (VBA)

```
Public Function GetDecalsCount() As Long
```

SOLIDWORKS Type Library

GetDrawingComponent Method (Component2)

Visual Basic for Applications (VBA)

```
Public Function GetDrawingComponent( _  
    ByVal ViewIn As View _  
) As DrawingComponent
```

SOLIDWORKS Type Library

GetExcludeFromBOM2 Method (Component2)

Visual Basic for Applications (VBA)

```
Public Function GetExcludeFromBOM2( _  
    ByVal Config_opt As Long, _  
    ByVal Config_names As Variant _  
    ) As Variant
```

SOLIDWORKS Type Library

GetHiddenUnloadedChildrenCount Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetHiddenUnloadedChildrenCount() As Long
```

SOLIDWORKS Type Library

GetID Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetID() As Long
```

SOLIDWORKS Type Library

GetImportedPath Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetImportedPath() As String
```

SOLIDWORKS Type Library

GetMaterialIdName Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetMaterialIdName() As String
```

SOLIDWORKS Type Library

GetMaterialPropertyValues2 Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetMaterialPropertyValues2( _  
    ByVal Config_opt As Long, _  
    ByVal Config_names As Variant _  
    ) As Variant
```

SOLIDWORKS Type Library

GetMaterialUserName Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetMaterialUserName() As String
```

SOLIDWORKS Type Library

GetMates Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetMates() As Variant
```

SOLIDWORKS Type Library

GetModelDoc Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function GetModelDoc() As Object
```

SOLIDWORKS Type Library

GetModelDoc2 Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function GetModelDoc2() As Object
```

SOLIDWORKS Type Library

GetModelMaterialPropertyValues Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function GetModelMaterialPropertyValues( _  
    ByVal ConfigName As String _  
) As Variant
```

SOLIDWORKS Type Library

GetModelTexture Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function GetModelTexture( _  
    ByVal ConfigName As String _  
) As Texture
```

SOLIDWORKS Type Library

GetParent Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function GetParent() As Component2
```

SOLIDWORKS Type Library

GetPathName Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function GetPathName() As String
```

SOLIDWORKS Type Library

GetPLMID Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function GetPLMID() As String
```

SOLIDWORKS Type Library

GetPropertyExtension Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function GetPropertyExtension( _  
    ByVal ID As Long _  
    ) As Variant
```

SOLIDWORKS Type Library

GetReferencedDisplayStates Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetReferencedDisplayStates( _  
    ByVal AssemblyDisplayStateOption As Long, _  
    ByVal AssemblyDisplayStateNames As Variant _  
    ) As Variant
```

SOLIDWORKS Type Library

GetRemainingDOFs Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetRemainingDOFs( _  
    ByRef Rpoint1_status As Long, _  
    ByRef Rpoint1 As MathPoint, _  
    ByRef Rdirection1_status As Long, _  
    ByRef Rdirection1 As MathVector, _  
    ByRef Rpoint2_status As Long, _  
    ByRef Rpoint2 As MathPoint, _  
    ByRef Rdirection2_status As Long, _  
    ByRef Rdirection2 As MathVector, _  
    ByRef Tdirection1_status As Long, _  
    ByRef Tdirection1 As MathVector, _  
    ByRef Tdirection2_status As Long, _  
    ByRef Tdirection2 As MathVector _  
    ) As Long
```

SOLIDWORKS Type Library

GetRenderMaterials Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetRenderMaterials() As Variant
```

SOLIDWORKS Type Library

GetRenderMaterials2 Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetRenderMaterials2( _  
    ByVal DisplayStateOption As Long, _  
    ByVal DisplayStateNames As Variant _  
    ) As Variant
```

SOLIDWORKS Type Library

GetRenderMaterialsCount Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetRenderMaterialsCount() As Long
```

SOLIDWORKS Type Library

GetRenderMaterialsCount2 Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetRenderMaterialsCount2( _  
    ByVal DisplayStateOption As Long, _  
    ByVal DisplayStateNames As Variant _  
    ) As Long
```

SOLIDWORKS Type Library

GetRepresentationParent Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetRepresentationParent() As String
```

SOLIDWORKS Type Library

GetSectionedBodies Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSectionedBodies( _  
    ByVal ViewIn As Object _  
    ) As Variant
```

SOLIDWORKS Type Library

GetSelectByIDString Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSelectByIDString() As String
```

SOLIDWORKS Type Library

GetSmartComponentData Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSmartComponentData( _  
    ByRef Features As Variant, _  
    ByRef FeaturesSelected As Variant, _  
    ByRef Components As Variant, _  
    ByRef ComponentsSelected As Variant, _  
    ByRef References As Variant _  
    ) As Boolean
```

SOLIDWORKS Type Library

GetSpecificTransform Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSpecificTransform( _  
    ByVal IgnoreExplode As Boolean _  
    ) As Object
```

SOLIDWORKS Type Library

GetSuppression Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSuppression() As Long
```

SOLIDWORKS Type Library

GetSuppression2 Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function GetSuppression2() As Long
```

SOLIDWORKS Type Library

GetTessNorms Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function GetTessNorms() As Variant
```

SOLIDWORKS Type Library

GetTessTriangles Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function GetTessTriangles( _  
    ByVal NoConversion As Boolean _  
    ) As Variant
```

SOLIDWORKS Type Library

GetTessTriStripEdges Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function GetTessTriStripEdges() As Variant
```

SOLIDWORKS Type Library

GetTessTriStripNorms Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function GetTessTriStripNorms() As Variant
```

SOLIDWORKS Type Library

GetTessTriStrips Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function GetTessTriStrips( _  
    ByVal NoConversion As Boolean _  
    ) As Variant
```

SOLIDWORKS Type Library

GetTexture Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function GetTexture( _  
    ByVal Config_name As String _  
    ) As Texture
```

SOLIDWORKS Type Library

GetTotalTransform Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTotalTransform( _  
    ByVal IncludePresentationXform As Boolean _  
    ) As MathTransform
```

SOLIDWORKS Type Library

GetType Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetType() As Long
```

SOLIDWORKS Type Library

GetUnloadedComponentNames Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetUnloadedComponentNames( _  
    ByRef UnloadedComponentPathNames As Variant, _  
    ByRef UnloadedComponentReferencedConfigurationNames As Variant, _  
    ByRef ReasonForUnloadingComponents As Variant, _  
    ByRef DocTypes As Variant _  
    ) As Variant
```

SOLIDWORKS Type Library

GetVisibility Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetVisibility( _  
    ByVal Config_opt As Long, _  
    ByVal Config_names As Variant _  
    ) As Variant
```

SOLIDWORKS Type Library

GetVisibilityInAsmDisplayStates Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetVisibilityInAsmDisplayStates( _  
    ByVal AssemblyDisplayStateOption As Long, _  
    ByVal AssemblyDisplayStateNames As Variant _  
    ) As Variant
```

SOLIDWORKS Type Library

GetXform Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetXform() As Variant
```

SOLIDWORKS Type Library

HasAssemblyFeatures Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function HasAssemblyFeatures( _  
    ByRef ConfigurationName As String _
```

) As Boolean

SOLIDWORKS Type Library

HasMaterialPropertyValues Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function HasMaterialPropertyValues() As Boolean
```

SOLIDWORKS Type Library

HasUnloadedComponents Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function HasUnloadedComponents() As Boolean
```

SOLIDWORKS Type Library

IFindAttribute Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function IFindAttribute( _  
    ByVal AttributeDef As AttributeDef, _  
    ByVal WhichOne As Long _  
    ) As Attribute
```

SOLIDWORKS Type Library

IGetBody Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function IGetBody() As Body2
```

SOLIDWORKS Type Library

IGetBox Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function IGetBox( _  
    ByVal IncludeRefPlanes As Boolean, _  
    ByVal IncludeSketches As Boolean _  
    ) As Double
```

SOLIDWORKS Type Library

IGetChildren Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function IGetChildren() As Component2
```

SOLIDWORKS Type Library

IGetChildrenCount Method (Component2)



Visual Basic for Applications (VBA)

```
Public Function IGetChildrenCount() As Integer
```

SOLIDWORKS Type Library

IGetCorrespondingEntity Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetCorrespondingEntity( _  
    ByVal PEntity As Entity _  
    ) As Entity
```

SOLIDWORKS Type Library

IGetDecals Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetDecals( _  
    ByVal Count As Long _  
    ) As Decal
```

SOLIDWORKS Type Library

IGetMaterialPropertyValues2 Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetMaterialPropertyValues2( _  
    ByVal Config_opt As Long, _  
    ByVal Config_count As Long, _  
    ByRef Config_names As String _  
    ) As Double
```

SOLIDWORKS Type Library

IGetMaterialPropertyValuesForFace Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetMaterialPropertyValuesForFace( _  
    ByVal FaceIn As Object _  
    ) As Double
```

SOLIDWORKS Type Library

IGetModelDoc Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetModelDoc() As ModelDoc2
```

SOLIDWORKS Type Library

IGetModelMaterialPropertyValues Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetModelMaterialPropertyValues( _  
    ByVal ConfigName As String _  
    ) As Double
```

SOLIDWORKS Type Library

IGetRenderMaterials Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetRenderMaterials( _  
    ByVal Count As Long _  
    ) As RenderMaterial
```

SOLIDWORKS Type Library

IGetTemporaryBodyID Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetTemporaryBodyID() As Long
```

SOLIDWORKS Type Library

IGetTessNorms Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetTessNorms() As Single
```

SOLIDWORKS Type Library

IGetTessTriangleCount Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetTessTriangleCount() As Long
```

SOLIDWORKS Type Library

IGetTessTriangles Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetTessTriangles( _  
    ByVal NoConversion As Boolean _  
    ) As Single
```

SOLIDWORKS Type Library

IGetTessTriStripEdges Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetTessTriStripEdges() As Long
```

SOLIDWORKS Type Library

IGetTessTriStripEdgeSize Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetTessTriStripEdgeSize() As Long
```

SOLIDWORKS Type Library

IGetTessTriStripNorms Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetTessTriStripNorms() As Single
```

SOLIDWORKS Type Library

IGetTessTriStrips Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetTessTriStrips( _  
    ByVal NoConversion As Boolean _  
) As Single
```

SOLIDWORKS Type Library

IGetTessTriStripSize Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetTessTriStripSize() As Long
```

SOLIDWORKS Type Library

IGetVisibility Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetVisibility( _  
    ByVal Config_opt As Long, _  
    ByVal Config_count As Long, _  
    ByRef Config_names As String _  
) As Long
```

SOLIDWORKS Type Library

IGetXform Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetXform() As Double
```

SOLIDWORKS Type Library

IListExternalFileReferences Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub IListExternalFileReferences( _  
    ByVal NumRefs As Long, _  
    ByRef ModelPathName As String, _  
    ByRef CompPathName As String, _  
    ByRef Feature As String, _  
    ByRef DataType As String, _  
    ByRef Status As Long, _  
    ByRef RefEntity As String, _  
    ByRef FeatComp As String _  
)
```

SOLIDWORKS Type Library

IListExternalFileReferences2 Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub IListExternalFileReferences2( _  
    ByVal NumRefs As Long, _  
    ByRef ModelPathName As String, _  
    ByRef CompPathName As String, _  
    ByRef Feature As String, _  
    ByRef DataType As String, _
```

```
ByRef Status As Long, _  
ByRef RefEntity As String, _  
ByRef FeatComp As String, _  
ByRef ConfigOption As Long, _  
ByRef ConfigName As String _  
)
```

SOLIDWORKS Type Library

IMaterialPropertyValues Property (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property IMaterialPropertyValues As Double
```

SOLIDWORKS Type Library

IRemoveMaterialProperty2 Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IRemoveMaterialProperty2( _  
    ByVal Config_opt As Long, _  
    ByVal Config_count As Long, _  
    ByRef Config_names As String _  
) As Boolean
```

SOLIDWORKS Type Library

IsDisplayDataOutOfDate Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsDisplayDataOutOfDate() As Long
```

SOLIDWORKS Type Library

IsEnvelope Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsEnvelope() As Boolean
```

SOLIDWORKS Type Library

ISetMaterialPropertyValues2 Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ISetMaterialPropertyValues2( _  
    ByRef Material_values As Double, _  
    ByVal Config_opt As Long, _  
    ByVal Config_count As Long, _  
    ByRef Config_names As String _  
)
```

SOLIDWORKS Type Library

ISetVisibility Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ISetVisibility( _  
    ByVal State As Long, _  
    ByVal Config_opt As Long, _  
    ByVal Config_count As Long, _
```

```
ByRef Config_names As String _  
)
```

SOLIDWORKS Type Library

ISetXform Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ISetXform( _  
    ByRef XformIn As Double _  
) As Boolean
```

SOLIDWORKS Type Library

ISetXformAndSolve Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ISetXformAndSolve( _  
    ByRef XformIn As Double _  
) As Boolean
```

SOLIDWORKS Type Library

IsFixed Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsFixed() As Boolean
```

SOLIDWORKS Type Library

IsGraphicsOnly Property (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property IsGraphicsOnly As Boolean
```

SOLIDWORKS Type Library

IsHidden Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsHidden( _  
    ByVal ConsiderSuppressed As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

IsLoaded Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsLoaded() As Boolean
```

SOLIDWORKS Type Library

IsMirrored Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsMirrored() As Boolean
```

SOLIDWORKS Type Library

IsNameOverridden Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsNameOverridden() As Boolean
```

SOLIDWORKS Type Library

IsPatternInstance Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsPatternInstance() As Boolean
```

SOLIDWORKS Type Library

IsRoot Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsRoot() As Boolean
```

SOLIDWORKS Type Library

IsSmartComponent Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsSmartComponent() As Boolean
```

SOLIDWORKS Type Library

IsSpeedPak Property (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property IsSpeedPak As Boolean
```

SOLIDWORKS Type Library

IsSuppressed Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsSuppressed() As Boolean
```

SOLIDWORKS Type Library

IsVirtual Property (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property IsVirtual As Boolean
```

SOLIDWORKS Type Library

ListExternalFileReferences Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ListExternalFileReferences( _  
    ByRef ModelPathName As Variant, _  
    ByRef ComponentPathName As Variant, _
```

```
ByRef Feature As Variant, _  
ByRef DataType As Variant, _  
ByRef Status As Variant, _  
ByRef RefEntity As Variant, _  
ByRef FeatCom As Variant _  
)
```

SOLIDWORKS Type Library

ListExternalFileReferences2 Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ListExternalFileReferences2( _  
    ByRef ModelPathName As Variant, _  
    ByRef ComponentPathName As Variant, _  
    ByRef Feature As Variant, _  
    ByRef DataType As Variant, _  
    ByRef Status As Variant, _  
    ByRef RefEntity As Variant, _  
    ByRef FeatCom As Variant, _  
    ByRef ConfigOption As Long, _  
    ByRef ConfigName As String _  
)
```

SOLIDWORKS Type Library

ListExternalFileReferencesCount Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ListExternalFileReferencesCount() As Long
```

SOLIDWORKS Type Library

MakeVirtual Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function MakeVirtual() As Boolean
```

SOLIDWORKS Type Library

MakeVirtual2 Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function MakeVirtual2( _  
    ByVal AlsoChildVirtual As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

MaterialPropertyValues Property (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property MaterialPropertyValues As Variant
```

SOLIDWORKS Type Library

Name Property (Component2)

Syntax

Visual Basic for Applications (VBA)

Public Property Name As String

SOLIDWORKS Type Library

Name2 Property (Component2)

 Syntax

Visual Basic for Applications (VBA)

Public Property Name2 As String

SOLIDWORKS Type Library

PresentationTransform Property (Component2)

 Syntax

Visual Basic for Applications (VBA)

Public Property PresentationTransform As [MathTransform](#)

SOLIDWORKS Type Library

ReferencedConfiguration Property (Component2)

 Syntax

Visual Basic for Applications (VBA)

Public Property ReferencedConfiguration As String

SOLIDWORKS Type Library

ReferencedDisplayState Property (Component2)

 Syntax

Visual Basic for Applications (VBA)

Public Property ReferencedDisplayState As String

SOLIDWORKS Type Library

ReferencedDisplayState2 Property (Component2)

 Syntax

Visual Basic for Applications (VBA)

Public Property ReferencedDisplayState2 As String

SOLIDWORKS Type Library

RemoveMaterialProperty Method (Component2)

 Syntax

Visual Basic for Applications (VBA)

Public Function RemoveMaterialProperty() As Boolean

SOLIDWORKS Type Library

RemoveMaterialProperty2 Method (Component2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function RemoveMaterialProperty2( _  
    ByVal Config_opt As Long, _  
    ByVal Config_names As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

RemovePresentationTransform Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub RemovePresentationTransform()
```

SOLIDWORKS Type Library

RemoveTexture Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function RemoveTexture( _  
    ByVal Config_name As String _  
) As Boolean
```

SOLIDWORKS Type Library

RemoveTextureByDisplayState Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function RemoveTextureByDisplayState( _  
    ByVal DisplayStateName As String _  
) As Boolean
```

SOLIDWORKS Type Library

ReplaceReference Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function ReplaceReference( _  
    ByVal FileName As String _  
) As Long
```

SOLIDWORKS Type Library

ResetPropertyExtension Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ResetPropertyExtension()
```

SOLIDWORKS Type Library

SaveVirtualComponent Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function SaveVirtualComponent( _  
    ByVal CompPathName As String _  
) As Boolean
```

SOLIDWORKS Type Library

Select Method (Component2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function Select( _  
    ByVal AppendFlag As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

Select2 Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function Select2( _  
    ByVal Append As Boolean, _  
    ByVal Mark As Long _  
) As Boolean
```

SOLIDWORKS Type Library

Select3 Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function Select3( _  
    ByVal Append As Boolean, _  
    ByVal Data As SelectData, _  
) As Boolean
```

SOLIDWORKS Type Library

Select4 Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function Select4( _  
    ByVal Append As Boolean, _  
    ByVal Data As SelectData, _  
    ByVal ShowPopup As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

SelectByMark Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SelectByMark( _  
    ByVal AppendFlag As Boolean, _  
    ByVal Mark As Long _  
) As Boolean
```

SOLIDWORKS Type Library

SetCosmosWorksMaterial Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetCosmosWorksMaterial( _  
    ByVal ConfigName As String, _  
    ByVal Type As Long _  
) As Boolean
```

SOLIDWORKS Type Library

SetExcludeFromBOM2 Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetExcludeFromBOM2( _  
    ByVal Exclude As Boolean, _  
    ByVal Config_opt As Long, _  
    ByVal Config_names As Variant _  
) As Long
```

SOLIDWORKS Type Library

SetMaterialIdName Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetMaterialIdName( _  
    ByVal Name As String _  
) As Boolean
```

SOLIDWORKS Type Library

SetMaterialPropertyValues2 Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetMaterialPropertyValues2( _  
    ByVal Material_values As Variant, _  
    ByVal Config_opt As Long, _  
    ByVal Config_names As Variant _  
)
```

SOLIDWORKS Type Library

SetMaterialUserName Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetMaterialUserName( _  
    ByVal Name As String _  
) As Boolean
```

SOLIDWORKS Type Library

SetReferencedDisplayStates Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetReferencedDisplayStates( _  
    ByVal ComponentDisplayStateName As String, _  
    ByVal Option As Long, _  
    ByVal AssemblyDisplayStateNames As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

SetSmartComponentData Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetSmartComponentData( _  
    ByVal FeaturesSelected As Variant, _  
    ByVal ComponentsSelected As Variant, _  
    ByVal References As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

SetSuppression Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetSuppression( _  
    ByVal State As Long _  
) As Long
```

SOLIDWORKS Type Library

SetSuppression2 Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetSuppression2( _  
    ByVal State As Long _  
) As Long
```

SOLIDWORKS Type Library

SetTexture Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetTexture( _  
    ByVal Config_name As String, _  
    ByVal TextureIn As Texture _  
) As Boolean
```

SOLIDWORKS Type Library

SetTextureByDisplayState Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetTextureByDisplayState( _  
    ByVal DisplayStateName As String, _  
    ByVal TextureIn As Texture _  
) As Boolean
```

SOLIDWORKS Type Library

SetTransformAndSolve Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetTransformAndSolve( _  
    ByVal XformIn As MathTransform _  
) As Boolean
```

SOLIDWORKS Type Library

SetTransformAndSolve2 Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetTransformAndSolve2( _  
    ByVal XformIn As MathTransform _  
) As Boolean
```

SOLIDWORKS Type Library

SetTransformAndSolve3 Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetTransformAndSolve3( _  
    ByVal XformIn As MathTransform, _  
    ByVal ThisConfiguration As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

SetVisibility Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetVisibility( _  
    ByVal State As Long, _  
    ByVal Config_opt As Long, _  
    ByVal Config_names As Variant _  
)
```

SOLIDWORKS Type Library

SetVisibilityInAsmDisplayStates Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetVisibilityInAsmDisplayStates( _  
    ByVal HideComponent As Long, _  
    ByVal Option As Long, _  
    ByVal AssemblyDisplayStateNames As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

SetXform Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetXform( _  
    ByVal XformIn As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

SetXformAndSolve Method (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetXformAndSolve( _  
    ByVal XformIn As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

Solving Property (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Solving As Long
```

SOLIDWORKS Type Library

Transform Property (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Transform As MathTransform
```

SOLIDWORKS Type Library

Transform2 Property (Component2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Transform2 As MathTransform
```

SOLIDWORKS Type Library

UpdateExternalFileReferences Method (Component2)



Visual Basic for Applications (VBA)

```
Public Sub UpdateExternalFileReferences( _  
    ByVal ConfigOption As Long, _  
    ByVal ConfigName As String, _  
    ByVal UpdateStatus As Long _  
)
```

SOLIDWORKS Type Library

UseNamedConfiguration Property (Component2)



Visual Basic for Applications (VBA)

```
Public Property UseNamedConfiguration As Boolean
```

SOLIDWORKS Type Library

Visible Property (Component2)



Visual Basic for Applications (VBA)

```
Public Property Visible As Long
```

CompositeCurveFeatureData (Type)

SOLIDWORKS Type Library
CompositeCurveFeatureData Object

Object Model

CompositeCurveFeatureData

SOLIDWORKS Type Library
CompositeCurveFeatureData Object Members

Public Methods

 AccessSelections
 GetEntitiesToJoin
 GetEntitiesToJoinCount
 IGetEntitiesToJoin
 ISetEntitiesToJoin
 ReleaseSelectionAccess
 SetEntitiesToJoin

SOLIDWORKS Type Library
AccessSelections Method (CompositeCurveFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AccessSelections( _  
    ByVal TopDoc As ModelDoc2, _  
    ByVal Component As Component2 _  
    ) As Boolean
```

SOLIDWORKS Type Library
GetEntitiesToJoin Method (CompositeCurveFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetEntitiesToJoin( _  
    ByRef Type As Variant _  
    ) As Variant
```

SOLIDWORKS Type Library
GetEntitiesToJoinCount Method (CompositeCurveFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetEntitiesToJoinCount() As Long
```

SOLIDWORKS Type Library
IGetEntitiesToJoin Method (CompositeCurveFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetEntitiesToJoin( _  
    ByVal Count As Long, _
```

```
ByRef Type As Long _  
) As Object
```

SOLIDWORKS Type Library

ISetEntitiesToJoin Method (CompositeCurveFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ISetEntitiesToJoin( _  
    ByVal Count As Long, _  
    ByRef Ents As Object _  
)
```

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (CompositeCurveFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ReleaseSelectionAccess()
```

SOLIDWORKS Type Library

SetEntitiesToJoin Method (CompositeCurveFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetEntitiesToJoin( _  
    ByVal EntVar As Variant _  
)
```

ConcentricMateFeatureData (Type)

SOLIDWORKS Type Library

ConcentricMateFeatureData Object

Object Model

ConcentricMateFeatureData

SOLIDWORKS Type Library

ConcentricMateFeatureData Object Members

Public Properties

- EntitiesToMate
- LockRotation
- MateAlignment
- PickPoints

SOLIDWORKS Type Library

EntitiesToMate Property (ConcentricMateFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property EntitiesToMate As Variant
```

SOLIDWORKS Type Library

LockRotation Property (ConcentricMateFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property LockRotation As Boolean
```

SOLIDWORKS Type Library

MateAlignment Property (ConcentricMateFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property MateAlignment As Long
```

SOLIDWORKS Type Library

PickPoints Property (ConcentricMateFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property PickPoints As Variant
```