

SOLIDWORKS API (VB6 COM) — Reference (18/102): DimensionTolerance-DisplayData

SOLIDWORKS API Documentation (converted from CHM)

DimensionTolerance (Type)

SOLIDWORKS Type Library
DimensionTolerance Object

 Object Model

DimensionTolerance

SOLIDWORKS Type Library
DimensionTolerance Object Members

 Public Methods

	GetFitFontHeight
	GetFitFontScale
	GetFitFontUseDimension
	GetFitFontUseScale
	GetFontHeight
	GetFontScale
	GetFontUseDimension
	GetFontUseScale
	GetHoleFitValue
	GetMaxValue
	GetMaxValue2
	GetMinValue
	GetMinValue2
	GetShaftFitValue
	SetFitFont
	SetFitValues
	SetFont
	SetValues
	SetValues2

 Public Properties

	FitDisplayStyle
	FitType
	ShowParenthesis
	Type

SOLIDWORKS Type Library
FitDisplayStyle Property (DimensionTolerance)

 Syntax

Visual Basic for Applications (VBA)

Public Property FitDisplayStyle As Long

SOLIDWORKS Type Library
FitType Property (DimensionTolerance)



Visual Basic for Applications (VBA)

Public Property FitType As Long

SOLIDWORKS Type Library

GetFitFontHeight Method (DimensionTolerance)



Visual Basic for Applications (VBA)

Public Function GetFitFontHeight() As Double

SOLIDWORKS Type Library

GetFitFontScale Method (DimensionTolerance)



Visual Basic for Applications (VBA)

Public Function GetFitFontScale() As Double

SOLIDWORKS Type Library

GetFitFontUseDimension Method (DimensionTolerance)



Visual Basic for Applications (VBA)

Public Function GetFitFontUseDimension() As Boolean

SOLIDWORKS Type Library

GetFitFontUseScale Method (DimensionTolerance)



Visual Basic for Applications (VBA)

Public Function GetFitFontUseScale() As Boolean

SOLIDWORKS Type Library

GetFontHeight Method (DimensionTolerance)



Visual Basic for Applications (VBA)

Public Function GetFontHeight() As Double

SOLIDWORKS Type Library

GetFontScale Method (DimensionTolerance)



Visual Basic for Applications (VBA)

Public Function GetFontScale() As Double

SOLIDWORKS Type Library

GetFontUseDimension Method (DimensionTolerance)



Visual Basic for Applications (VBA)

Public Function GetFontUseDimension() As Boolean

SOLIDWORKS Type Library

GetFontUseScale Method (DimensionTolerance)



Visual Basic for Applications (VBA)

```
Public Function GetFontUseScale() As Boolean
```

SOLIDWORKS Type Library

GetHoleFitValue Method (DimensionTolerance)



Visual Basic for Applications (VBA)

```
Public Function GetHoleFitValue() As String
```

SOLIDWORKS Type Library

GetMaxValue Method (DimensionTolerance)



Visual Basic for Applications (VBA)

```
Public Function GetMaxValue() As Double
```

SOLIDWORKS Type Library

GetMaxValue2 Method (DimensionTolerance)



Visual Basic for Applications (VBA)

```
Public Function GetMaxValue2( _  
    ByRef ToleranceValue As Double _  
    ) As Long
```

SOLIDWORKS Type Library

GetMinValue Method (DimensionTolerance)



Visual Basic for Applications (VBA)

```
Public Function GetMinValue() As Double
```

SOLIDWORKS Type Library

GetMinValue2 Method (DimensionTolerance)



Visual Basic for Applications (VBA)

```
Public Function GetMinValue2( _  
    ByRef ToleranceValue As Double _  
    ) As Long
```

SOLIDWORKS Type Library

GetShaftFitValue Method (DimensionTolerance)



Visual Basic for Applications (VBA)

```
Public Function GetShaftFitValue() As String
```

SOLIDWORKS Type Library

SetFitFont Method (DimensionTolerance)



Visual Basic for Applications (VBA)

```
Public Function SetFitFont( _  
    ByVal UseDimension As Boolean, _
```

```
    ByVal UseScale As Boolean, _  
    ByVal Value As Double _  
) As Boolean
```

SOLIDWORKS Type Library

SetFitValues Method (DimensionTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetFitValues( _  
    ByVal HoleFit As String, _  
    ByVal ShaftFit As String _  
) As Boolean
```

SOLIDWORKS Type Library

SetFont Method (DimensionTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetFont( _  
    ByVal UseDimension As Boolean, _  
    ByVal UseScale As Boolean, _  
    ByVal Value As Double _  
) As Boolean
```

SOLIDWORKS Type Library

SetValues Method (DimensionTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetValues( _  
    ByVal MinValue As Double, _  
    ByVal MaxValue As Double _  
) As Boolean
```

SOLIDWORKS Type Library

SetValues2 Method (DimensionTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetValues2( _  
    ByVal MinValue As Double, _  
    ByVal MaxValue As Double, _  
    ByVal WhichConfigurations As Long, _  
    ByVal Config_names As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

ShowParenthesis Property (DimensionTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Property ShowParenthesis As Boolean
```

SOLIDWORKS Type Library

Type Property (DimensionTolerance)

Syntax

Visual Basic for Applications (VBA)

DimPatternFeatureData (Type)

SOLIDWORKS Type Library
DimPatternFeatureData Object

 Object Model

DimPatternFeatureData

SOLIDWORKS Type Library
DimPatternFeatureData Object Members

 Public Methods

 AccessSelections
 AddDimension
 AddInstanceAt
 DeleteDimension
 DeleteInstanceAt
 ExportToExcel
 GetControllingDimensionCount
 GetControllingDimensionName
 GetInstanceCount
 GetInstanceDimensionName
 GetInstanceIndex
 GetInstanceNameByIndex
 GetInstanceSuppressStateByIndex
 GetInstanceSuppressStateByName
 GetTableRowIndex
 ImportFromExcel
 ReleaseSelectionAccess
 SetInstanceDimensionValue
 SetInstanceSuppressStateByIndex
 SetInstanceSuppressStateByName

 Public Properties

 PropagateVisualProperties

SOLIDWORKS Type Library
AccessSelections Method (DimPatternFeatureData)

 Syntax

```
Visual Basic for Applications (VBA)

Public Function AccessSelections( _
    ByVal TopDoc As ModelDoc2, _
    ByVal Component As Component2 _
) As Boolean
```

SOLIDWORKS Type Library
AddDimension Method (DimPatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function AddDimension() As Boolean
```

SOLIDWORKS Type Library

AddInstanceAt Method (DimPatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function AddInstanceAt( _  
    ByVal IsSuppressed As Boolean, _  
    ByVal Index As Long _  
) As Boolean
```

SOLIDWORKS Type Library

DeleteDimension Method (DimPatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function DeleteDimension( _  
    ByVal DimensionColumnName As String _  
) As Boolean
```

SOLIDWORKS Type Library

DeleteInstanceAt Method (DimPatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function DeleteInstanceAt( _  
    ByVal Index As Long _  
) As Boolean
```

SOLIDWORKS Type Library

ExportToExcel Method (DimPatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function ExportToExcel( _  
    ByVal ExcelFile As String, _  
    ByVal Overwrite As Boolean _  
) As Long
```

SOLIDWORKS Type Library

GetControllingDimensionCount Method (DimPatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetControllingDimensionCount() As Long
```

SOLIDWORKS Type Library

GetControllingDimensionName Method (DimPatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetControllingDimensionName( _  
    ByVal Index As Long _  
) As String
```

SOLIDWORKS Type Library

GetInstanceCount Method (DimPatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetInstanceCount() As Long
```

SOLIDWORKS Type Library

GetInstanceDimensionName Method (DimPatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetInstanceDimensionName( _  
    ByVal InstanceName As String, _  
    ByVal ControllingDimName As String _  
    ) As String
```

SOLIDWORKS Type Library

GetInstanceIndex Method (DimPatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetInstanceIndex( _  
    ByVal InstanceName As String _  
    ) As Long
```

SOLIDWORKS Type Library

GetInstanceNameByIndex Method (DimPatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetInstanceNameByIndex( _  
    ByVal TableRowIndex As Long _  
    ) As String
```

SOLIDWORKS Type Library

GetInstanceSuppressStateByIndex Method (DimPatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetInstanceSuppressStateByIndex( _  
    ByVal TableRowIndex As Long _  
    ) As Boolean
```

SOLIDWORKS Type Library

GetInstanceSuppressStateByName Method (DimPatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetInstanceSuppressStateByName( _  
    ByVal InstanceName As String _  
    ) As Boolean
```

SOLIDWORKS Type Library

GetTableRowIndex Method (DimPatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTableRowIndex( _  
    ByVal InstanceName As String _  
    ) As Long
```

SOLIDWORKS Type Library

ImportFromExcel Method (DimPatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ImportFromExcel( _  
    ByVal ExcelFile As String _  
    ) As Long
```

SOLIDWORKS Type Library

PropagateVisualProperties Property (DimPatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property PropagateVisualProperties As Boolean
```

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (DimPatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ReleaseSelectionAccess()
```

SOLIDWORKS Type Library

SetInstanceDimensionValue Method (DimPatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetInstanceDimensionValue( _  
    ByVal TableRowIndex As Long, _  
    ByVal ControlDimName As String, _  
    ByVal NewValue As Double _  
    ) As String
```

SOLIDWORKS Type Library

SetInstanceSuppressStateByIndex Method (DimPatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetInstanceSuppressStateByIndex( _  
    ByVal TableRowIndex As Long, _  
    ByVal SuppressState As Boolean _  
    ) As String
```

SOLIDWORKS Type Library

SetInstanceSuppressStateByName Method (DimPatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetInstanceSuppressStateByName( _  
    ByVal InstanceName As String, _  
    ByVal SuppressState As Boolean _  
    ) As String
```

DimXpertManager (Type)

SOLIDWORKS Type Library
DimXpertManager Object

Object Model

DimXpertManager

SOLIDWORKS Type Library
DimXpertManager Object Members

Public Properties

- DimXpertPart
- SchemaComment
- SchemaDescription
- SchemaName
- TreeDisplay

SOLIDWORKS Type Library
DimXpertPart Property (DimXpertManager)

Syntax

Visual Basic for Applications (VBA)

Public Property DimXpertPart As Object

SOLIDWORKS Type Library
SchemaComment Property (DimXpertManager)

Syntax

Visual Basic for Applications (VBA)

Public Property SchemaComment As String

SOLIDWORKS Type Library
SchemaDescription Property (DimXpertManager)

Syntax

Visual Basic for Applications (VBA)

Public Property SchemaDescription As String

SOLIDWORKS Type Library
SchemaName Property (DimXpertManager)

Syntax

Visual Basic for Applications (VBA)

Public Property SchemaName As String

SOLIDWORKS Type Library
TreeDisplay Property (DimXpertManager)

Syntax

Visual Basic for Applications (VBA)

Public Property TreeDisplay As Long

DisplayData (Type)

SOLIDWORKS Type Library
DisplayData Object

Object Model

DisplayData

SOLIDWORKS Type Library
DisplayData Object Members

Public Methods

	GetArcAtIndex
	GetArcAtIndex2
	GetArcCount
	GetArrowHeadAtIndex
	GetArrowHeadAtIndex2
	GetArrowHeadCount
	GetEllipseAtIndex
	GetEllipseAtIndex2
	GetEllipseCount
	GetLineAtIndex
	GetLineAtIndex2
	GetLineAtIndex3
	GetLineCount
	GetParabolaAtIndex
	GetParabolaCount
	GetPointAtIndex
	GetPointCount
	GetPolygonAtIndex
	GetPolygonCount
	GetPolygonSizeAtIndex
	GetPolylineAtIndex
	GetPolylineAtIndex2
	GetPolyLineCount
	GetPolylineSizeAtIndex
	GetPolylineSizeAtIndex2
	GetTextAngleAtIndex
	GetTextAtIndex
	GetTextCount
	GetTextFontAtIndex
	GetTextHeightAtIndex
	GetTextInBoxHeightAtIndex
	GetTextInBoxStyleAtIndex

	GetTextBoxWidthAtIndex
	GetTextInvertAtIndex
	GetTextLineSpacingAtIndex
	GetTextPlaneAtIndex
	GetTextPositionAtIndex
	GetTextRefPositionAtIndex
	GetTriangleAtIndex
	GetTriangleCount
	IGetArcAtIndex
	IGetArcAtIndex2
	IGetArrowHeadAtIndex
	IGetEllipseAtIndex
	IGetEllipseAtIndex2
	IGetLineAtIndex
	IGetLineAtIndex2
	IGetLineAtIndex3
	IGetParabolaAtIndex
	IGetPointAtIndex
	IGetPolygonAtIndex
	IGetPolylineAtIndex
	IGetPolylineAtIndex2
	IGetTextPositionAtIndex
	IGetTriangleAtIndex

SOLIDWORKS Type Library

GetArcAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

Public Function GetArcAtIndex(_
 ByVal *Index* As Long _
) As Variant

SOLIDWORKS Type Library

GetArcAtIndex2 Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

Public Function GetArcAtIndex2(_
 ByVal *Index* As Long _
) As Variant

SOLIDWORKS Type Library

GetArcCount Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

Public Function GetArcCount() As Long

SOLIDWORKS Type Library

GetArrowHeadAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetArrowHeadAtIndex( _  
    ByVal Index As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetArrowHeadAtIndex2 Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetArrowHeadAtIndex2( _  
    ByVal Index As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetArrowHeadCount Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetArrowHeadCount() As Long
```

SOLIDWORKS Type Library

GetEllipseAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetEllipseAtIndex( _  
    ByVal Index As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetEllipseAtIndex2 Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetEllipseAtIndex2( _  
    ByVal Index As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetEllipseCount Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetEllipseCount() As Long
```

SOLIDWORKS Type Library

GetLineAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetLineAtIndex( _  
    ByVal Index As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetLineAtIndex2 Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetLineAtIndex2( _  
    ByVal Index As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetLineAtIndex3 Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetLineAtIndex3( _  
    ByVal Index As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetLineCount Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetLineCount() As Long
```

SOLIDWORKS Type Library

GetParabolaAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetParabolaAtIndex( _  
    ByVal Index As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetParabolaCount Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetParabolaCount() As Long
```

SOLIDWORKS Type Library

GetPointAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPointAtIndex( _  
    ByVal Index As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetPointCount Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPointCount() As Long
```

SOLIDWORKS Type Library

GetPolygonAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPolygonAtIndex( _  
    ByVal Index As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetPolygonCount Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPolygonCount() As Long
```

SOLIDWORKS Type Library

GetPolygonSizeAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPolygonSizeAtIndex( _  
    ByVal Index As Long _  
) As Long
```

SOLIDWORKS Type Library

GetPolylineAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPolylineAtIndex( _  
    ByVal Index As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetPolylineAtIndex2 Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPolylineAtIndex2( _  
    ByVal Index As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetPolyLineCount Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPolyLineCount() As Long
```

SOLIDWORKS Type Library

GetPolylineSizeAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPolylineSizeAtIndex( _  
    ByVal Index As Long _  
) As Long
```

SOLIDWORKS Type Library

GetPolylineSizeAtIndex2 Method (DisplayData)

Syntax

```
Public Function GetPolylineSizeAtIndex2( _  
    ByVal Index As Long _  
) As Long
```

GetTextAngleAtIndex Method (DisplayData) **Syntax**

```
Public Function GetTextAngleAtIndex( _  
    ByVal Index As Long _  
) As Double
```

GetTextAtIndex Method (DisplayData) **Syntax**

```
Public Function GetTextAtIndex( _  
    ByVal Index As Long _  
) As String
```

GetTextCount Method (DisplayData) **Syntax**

```
Public Function GetTextCount() As Long
```

GetTextFontAtIndex Method (DisplayData) **Syntax**

```
Public Function GetTextFontAtIndex( _  
    ByVal Index As Long _  
) As String
```

GetTextHeightAtIndex Method (DisplayData) **Syntax**

```
Public Function GetTextHeightAtIndex( _  
    ByVal Index As Long _  
) As Double
```

GetTextInBoxHeightAtIndex Method (DisplayData) **Syntax**

```
Public Function GetTextInBoxHeightAtIndex( _  
    ByVal Index As Long _  
) As Double
```

GetTextInBoxStyleAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTextInBoxStyleAtIndex( _  
    ByVal Index As Long _  
) As Long
```

SOLIDWORKS Type Library

GetTextInBoxWidthAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTextInBoxWidthAtIndex( _  
    ByVal Index As Long _  
) As Double
```

SOLIDWORKS Type Library

GetTextInvertAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTextInvertAtIndex( _  
    ByVal Index As Long _  
) As Long
```

SOLIDWORKS Type Library

GetTextLineSpacingAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTextLineSpacingAtIndex( _  
    ByVal Index As Long _  
) As Double
```

SOLIDWORKS Type Library

GetTextPlaneAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTextPlaneAtIndex( _  
    ByVal Index As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetTextPositionAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTextPositionAtIndex( _  
    ByVal Index As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetTextRefPositionAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTextRefPositionAtIndex( _  
    ByVal Index As Long _  
    ) As Long
```

SOLIDWORKS Type Library

GetTriangleAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTriangleAtIndex( _  
    ByVal Index As Long _  
    ) As Variant
```

SOLIDWORKS Type Library

GetTriangleCount Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTriangleCount() As Long
```

SOLIDWORKS Type Library

IGetArcAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetArcAtIndex( _  
    ByVal Index As Long _  
    ) As Double
```

SOLIDWORKS Type Library

IGetArcAtIndex2 Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetArcAtIndex2( _  
    ByVal Index As Long _  
    ) As Double
```

SOLIDWORKS Type Library

IGetArrowHeadAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetArrowHeadAtIndex( _  
    ByVal Index As Long _  
    ) As Double
```

SOLIDWORKS Type Library

IGetEllipseAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetEllipseAtIndex( _  
    ByVal Index As Long _  
    ) As Double
```

SOLIDWORKS Type Library

IGetEllipseAtIndex2 Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetEllipseAtIndex2( _  
    ByVal Index As Long _  
    ) As Double
```

SOLIDWORKS Type Library

IGetLineAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetLineAtIndex( _  
    ByVal Index As Long _  
    ) As Double
```

SOLIDWORKS Type Library

IGetLineAtIndex2 Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetLineAtIndex2( _  
    ByVal Index As Long _  
    ) As Double
```

SOLIDWORKS Type Library

IGetLineAtIndex3 Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetLineAtIndex3( _  
    ByVal Index As Long _  
    ) As Double
```

SOLIDWORKS Type Library

IGetParabolaAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetParabolaAtIndex( _  
    ByVal Index As Long _  
    ) As Double
```

SOLIDWORKS Type Library

IGetPointAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetPointAtIndex( _  
    ByVal Index As Long _  
    ) As Double
```

SOLIDWORKS Type Library

IGetPolygonAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetPolygonAtIndex( _  
    ByVal Index As Long _  
) As Double
```

SOLIDWORKS Type Library

IGetPolylineAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetPolylineAtIndex( _  
    ByVal Index As Long _  
) As Double
```

SOLIDWORKS Type Library

IGetPolylineAtIndex2 Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetPolylineAtIndex2( _  
    ByVal Index As Long _  
) As Double
```

SOLIDWORKS Type Library

IGetTextPositionAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetTextPositionAtIndex( _  
    ByVal Index As Long _  
) As Double
```

SOLIDWORKS Type Library

IGetTriangleAtIndex Method (DisplayData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetTriangleAtIndex( _  
    ByVal Index As Long _  
) As Double
```