

SOLIDWORKS API (VB6 COM) — Reference (43/102): InstanceToVaryOptions- IPMIDimensionData

SOLIDWORKS API Documentation (converted from CHM)

InstanceToVaryOptions (Type)

SOLIDWORKS Type Library
InstanceToVaryOptions Object

Object Model

InstanceToVaryOptions

SOLIDWORKS Type Library
InstanceToVaryOptions Object Members

Public Methods

	GetD1IncrementDimensions
	GetD1ModifiedSpacingValue
	GetD2IncrementDimensions
	GetD2ModifiedSpacingValue
	GetModifiedDimensions
	GetModifiedInstances
	ModifyD1SpacingValue
	ModifyD2SpacingValue
	ModifyDimensions
	SetD1IncrementDimensions
	SetD2IncrementDimensions

Public Properties

	D1SpacingIncrement
	D2SpacingIncrement

SOLIDWORKS Type Library
D1SpacingIncrement Property (InstanceToVaryOptions)

Syntax

Visual Basic for Applications (VBA)
Public Property D1SpacingIncrement As Double

SOLIDWORKS Type Library
D2SpacingIncrement Property (InstanceToVaryOptions)

Syntax

Visual Basic for Applications (VBA)
Public Property D2SpacingIncrement As Double

SOLIDWORKS Type Library
GetD1IncrementDimensions Method (InstanceToVaryOptions)

Syntax

Visual Basic for Applications (VBA)
Public Sub GetD1IncrementDimensions(_ ByRef IncrementDimensions As Variant, _ ByRef IncrementDimValues As Variant _)

GetD1ModifiedSpacingValue Method (InstanceToVaryOptions) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetD1ModifiedSpacingValue( _  
    ByVal Instance As Long _  
) As Double
```

GetD2IncrementDimensions Method (InstanceToVaryOptions) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub GetD2IncrementDimensions( _  
    ByRef IncrementDimensions As Variant, _  
    ByRef IncrementDimValues As Variant _  
)
```

GetD2ModifiedSpacingValue Method (InstanceToVaryOptions) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetD2ModifiedSpacingValue( _  
    ByVal Instance As Long _  
) As Double
```

GetModifiedDimensions Method (InstanceToVaryOptions) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub GetModifiedDimensions( _  
    ByVal Instance As Long, _  
    ByRef Dimensions As Variant, _  
    ByRef Values As Variant _  
)
```

GetModifiedInstances Method (InstanceToVaryOptions) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetModifiedInstances( _  
    ByVal ModificationType As Long _  
) As Variant
```

ModifyD1SpacingValue Method (InstanceToVaryOptions) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function ModifyD1SpacingValue( _  
    ByVal Instance As Long, _  
    ByVal Value As Double _  
) As Boolean
```

ModifyD2SpacingValue Method (InstanceToVaryOptions)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ModifyD2SpacingValue( _  
    ByVal Instance As Long, _  
    ByVal Value As Double _  
) As Boolean
```

SOLIDWORKS Type Library

ModifyDimensions Method (InstanceToVaryOptions)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ModifyDimensions( _  
    ByVal Instance As Long, _  
    ByVal Dimensions As Variant, _  
    ByVal Values As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

SetD1IncrementDimensions Method (InstanceToVaryOptions)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetD1IncrementDimensions( _  
    ByVal IncrementDimensions As Variant, _  
    ByVal IncrementDimValues As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

SetD2IncrementDimensions Method (InstanceToVaryOptions)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetD2IncrementDimensions( _  
    ByVal IncrementDimensions As Variant, _  
    ByVal IncrementDimValues As Variant _  
) As Boolean
```

Interference (Type)

SOLIDWORKS Type Library

Interference Object

Object Model

Interference

IGetComponents (Component2)

SOLIDWORKS Type Library

Interference Object Members

Public Methods

GetComponentCount

GetInterferenceBody

IGetComponents

Public Properties

Components

Ignore

IsFastener

IsPossibleInterference

Volume

SOLIDWORKS Type Library

Components Property (Interference)

Syntax

Visual Basic for Applications (VBA)

Public Property Components As Variant

SOLIDWORKS Type Library

GetComponentCount Method (Interference)

Syntax

Visual Basic for Applications (VBA)

Public Function GetComponentCount() As Long

SOLIDWORKS Type Library

GetInterferenceBody Method (Interference)

Syntax

Visual Basic for Applications (VBA)

Public Function GetInterferenceBody() As Object

SOLIDWORKS Type Library

IGetComponents Method (Interference)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetComponents( _  
    ByVal ComponentCount As Long _  
) As Component2
```

SOLIDWORKS Type Library

Ignore Property (Interference)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Property Ignore As Boolean
```

SOLIDWORKS Type Library

IsFastener Property (Interference)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Property IsFastener As Boolean
```

SOLIDWORKS Type Library

IsPossibleInterference Property (Interference)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Property IsPossibleInterference As Boolean
```

SOLIDWORKS Type Library

Volume Property (Interference)

 **Syntax**


Visual Basic for Applications (VBA)

```
Public Property Volume As Double
```

InterferenceDetectionMgr (Type)

SOLIDWORKS Type Library
InterferenceDetectionMgr Object

 Object Model



SOLIDWORKS Type Library
InterferenceDetectionMgr Object Members

 Public Methods

	Done
	ExportResults
	GetComponentsAndTransforms
	GetComponentsTransformInterference
	GetComponentsTransformInterferenceCount
	GetInterferenceComponentCount
	GetInterferenceComponents
	GetInterferenceCount
	GetInterferences
	IGetComponentsTransformInterference
	IGetInterferenceComponents
	IGetInterferences
	SetComponentsAndTransforms

 Public Properties

	CreateFastenersFolder
	IgnoreHiddenBodies
	IncludeMultibodyPartInterferences
	MakeInterferingPartsTransparent
	NonInterferingComponentDisplay
	ShowIgnoredInterferences
	TreatCoincidenceAsInterference
	TreatSubAssembliesAsComponents
	UseTransform

SOLIDWORKS Type Library
CreateFastenersFolder Property (InterferenceDetectionMgr)

 Syntax

Visual Basic for Applications (VBA)

Public Property CreateFastenersFolder As Boolean

Done Method (InterferenceDetectionMgr) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub Done()
```

ExportResults Method (InterferenceDetectionMgr) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function ExportResults( _  
    ByVal FileName As String, _  
    ByVal IncludeThumbnail As Boolean _  
    ) As Boolean
```

GetComponentsAndTransforms Method (InterferenceDetectionMgr) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetComponentsAndTransforms( _  
    ByRef ComponentList As Variant, _  
    ByRef TransformList As Variant _  
    ) As Boolean
```

GetComponentsTransformInterference Method (InterferenceDetectionMgr) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetComponentsTransformInterference( _  
    ByVal Component As Variant, _  
    ByVal Transform As Variant, _  
    ByRef InterferingComponent As Variant _  
    ) As Boolean
```

GetComponentsTransformInterferenceCount Method (InterferenceDetectionMgr) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetComponentsTransformInterferenceCount( _  
    ByVal NumOfComponent As Long, _  
    ByVal Component As Component2, _  
    ByVal Transform As MathTransform _  
    ) As Long
```

GetInterferenceComponentCount Method (InterferenceDetectionMgr) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetInterferenceComponentCount() As Long
```

GetInterferenceComponents Method (InterferenceDetectionMgr) **Syntax**

```
Public Function GetInterferenceComponents() As Variant
```

SOLIDWORKS Type Library

GetInterferenceCount Method (InterferenceDetectionMgr)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetInterferenceCount() As Long
```

SOLIDWORKS Type Library

GetInterferences Method (InterferenceDetectionMgr)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetInterferences() As Variant
```

SOLIDWORKS Type Library

IGetComponentsTransformInterference Method (InterferenceDetectionMgr)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetComponentsTransformInterference( _  
    ByVal NumOfComponent As Long, _  
    ByVal Component As Component2, _  
    ByVal Transform As MathTransform, _  
    ByVal NumOfIntComponent As Long, _  
    ByRef InterferingComponent As Component2 _  
    ) As Boolean
```

SOLIDWORKS Type Library

IGetInterferenceComponents Method (InterferenceDetectionMgr)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetInterferenceComponents( _  
    ByVal InterferenceComponentCount As Long _  
    ) As Component2
```

SOLIDWORKS Type Library

IGetInterferences Method (InterferenceDetectionMgr)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetInterferences( _  
    ByVal InterferenceCount As Long _  
    ) As Interference
```

SOLIDWORKS Type Library

IgnoreHiddenBodies Property (InterferenceDetectionMgr)

Syntax

Visual Basic for Applications (VBA)

```
Public Property IgnoreHiddenBodies As Boolean
```

SOLIDWORKS Type Library

IncludeMultibodyPartInterferences Property (InterferenceDetectionMgr)

Syntax

Visual Basic for Applications (VBA)

Public Property IncludeMultibodyPartInterferences As Boolean

SOLIDWORKS Type Library

MakeInterferingPartsTransparent Property (InterferenceDetectionMgr)



Syntax

Visual Basic for Applications (VBA)

Public Property MakeInterferingPartsTransparent As Boolean

SOLIDWORKS Type Library

NonInterferingComponentDisplay Property (InterferenceDetectionMgr)



Syntax

Visual Basic for Applications (VBA)

Public Property NonInterferingComponentDisplay As Long

SOLIDWORKS Type Library

SetComponentsAndTransforms Method (InterferenceDetectionMgr)



Syntax

Visual Basic for Applications (VBA)

```
Public Function SetComponentsAndTransforms( _  
    ByVal ComponentList As Variant, _  
    ByVal TransformList As Variant _  
    ) As Long
```

SOLIDWORKS Type Library

ShowIgnoredInterferences Property (InterferenceDetectionMgr)



Syntax

Visual Basic for Applications (VBA)

Public Property ShowIgnoredInterferences As Boolean

SOLIDWORKS Type Library

TreatCoincidenceAsInterference Property (InterferenceDetectionMgr)



Syntax

Visual Basic for Applications (VBA)

Public Property TreatCoincidenceAsInterference As Boolean

SOLIDWORKS Type Library

TreatSubAssembliesAsComponents Property (InterferenceDetectionMgr)



Syntax

Visual Basic for Applications (VBA)

Public Property TreatSubAssembliesAsComponents As Boolean

SOLIDWORKS Type Library

UseTransform Property (InterferenceDetectionMgr)



Syntax

Visual Basic for Applications (VBA)

Public Property UseTransform As Boolean

IntersectFeatureData (Type)

SOLIDWORKS Type Library
IntersectFeatureData Object

Object Model

IntersectFeatureData

SOLIDWORKS Type Library
IntersectFeatureData Object Members

Public Methods

 AccessSelections
 GetIntersections
 GetIntersectionsCount
 GetIntersectionsTools
 GetIntersectionsToolsCount
 ReleaseSelectionAccess
 SetIntersections
 SetIntersectionsTools

Public Properties

 CapPlanar
 Consume
 Merge

SOLIDWORKS Type Library
AccessSelections Method (IntersectFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Function AccessSelections( _
    ByVal TopDoc As ModelDoc2, _
    ByVal Component As Component2 _
) As Boolean
```

SOLIDWORKS Type Library
CapPlanar Property (IntersectFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property CapPlanar As Boolean
```

SOLIDWORKS Type Library
Consume Property (IntersectFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property Consume As Boolean
```

SOLIDWORKS Type Library
GetIntersections Method (IntersectFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetIntersections( _  
    ByRef Excluded As Variant _  
) As Variant
```

SOLIDWORKS Type Library

GetIntersectionsCount Method (IntersectFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetIntersectionsCount() As Long
```

SOLIDWORKS Type Library

GetIntersectionsTools Method (IntersectFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetIntersectionsTools() As Variant
```

SOLIDWORKS Type Library

GetIntersectionsToolsCount Method (IntersectFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetIntersectionsToolsCount() As Long
```

SOLIDWORKS Type Library

Merge Property (IntersectFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Property Merge As Boolean
```

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (IntersectFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ReleaseSelectionAccess()
```

SOLIDWORKS Type Library

SetIntersections Method (IntersectFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetIntersections( _  
    ByVal Intersections As Variant _  
)
```

SOLIDWORKS Type Library

SetIntersectionsTools Method (IntersectFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetIntersectionsTools( _  
    ByVal Tools As Variant _
```


IPackAndGo (Type)

SOLIDWORKS Type Library

IPackAndGo Object

Object Model

IPackAndGo

SOLIDWORKS Type Library

IPackAndGo Object Members

Public Methods

 [AddExternalDocuments](#)

 [GetDocumentNames](#)

 [GetDocumentNamesCount](#)

 [GetDocumentSaveToNames](#)

 [GetExternalDocuments](#)

 [GetSaveToName](#)

 [IGetDocumentNames](#)

 [IGetDocumentSaveToNames](#)

 [ISetDocumentSaveToNames](#)

 [RemoveExternalDocuments](#)

 [SetDocumentSaveToNames](#)

 [SetSaveToName](#)

 [SetSaveToName2](#)

Public Properties

 [AddPrefix](#)

 [AddSuffix](#)

 [FlattenToSingleFolder](#)

 [FolderStructureOption](#)

 [IncludeDrawings](#)

 [IncludeSimulationResults](#)

 [IncludeSuppressed](#)

 [IncludeToolboxComponents](#)

SOLIDWORKS Type Library

AddExternalDocuments Method (IPackAndGo)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddExternalDocuments( _  
    ByVal DocumentNames As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

AddPrefix Property (IPackAndGo)

Syntax

Visual Basic for Applications (VBA)

Public Property AddPrefix As String

SOLIDWORKS Type Library

AddSuffix Property (IPackAndGo)



Visual Basic for Applications (VBA)

Public Property AddSuffix As String

SOLIDWORKS Type Library

FlattenToSingleFolder Property (IPackAndGo)



Visual Basic for Applications (VBA)

Public Property FlattenToSingleFolder As Boolean

SOLIDWORKS Type Library

FolderStructureOption Property (IPackAndGo)



Visual Basic for Applications (VBA)

Public Property FolderStructureOption As Long

SOLIDWORKS Type Library

GetDocumentNames Method (IPackAndGo)



Visual Basic for Applications (VBA)

```
Public Function GetDocumentNames( _  
    ByRef DocumentNames As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

GetDocumentNamesCount Method (IPackAndGo)



Visual Basic for Applications (VBA)

```
Public Function GetDocumentNamesCount() As Long
```

SOLIDWORKS Type Library

GetDocumentSaveToNames Method (IPackAndGo)



Visual Basic for Applications (VBA)

```
Public Function GetDocumentSaveToNames( _  
    ByRef PathNameList As Variant, _  
    ByRef DocumentStatusList As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

GetExternalDocuments Method (IPackAndGo)



Visual Basic for Applications (VBA)

```
Public Function GetExternalDocuments( _  
    ByRef DocumentNames As Variant _
```

```
) As Boolean
```

SOLIDWORKS Type Library

GetSaveToName Method (IPackAndGo)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSaveToName() As String
```

SOLIDWORKS Type Library

IGetDocumentNames Method (IPackAndGo)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetDocumentNames( _  
    ByVal Count As Long, _  
    ByRef DocumentNames As String _  
) As Boolean
```

SOLIDWORKS Type Library

IGetDocumentSaveToNames Method (IPackAndGo)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetDocumentSaveToNames( _  
    ByVal NameCount As Long, _  
    ByRef NameList As String, _  
    ByRef StatusList As Long _  
) As Boolean
```

SOLIDWORKS Type Library

IncludeDrawings Property (IPackAndGo)

Syntax

Visual Basic for Applications (VBA)

```
Public Property IncludeDrawings As Boolean
```

SOLIDWORKS Type Library

IncludeSimulationResults Property (IPackAndGo)

Syntax

Visual Basic for Applications (VBA)

```
Public Property IncludeSimulationResults As Boolean
```

SOLIDWORKS Type Library

IncludeSuppressed Property (IPackAndGo)

Syntax

Visual Basic for Applications (VBA)

```
Public Property IncludeSuppressed As Boolean
```

SOLIDWORKS Type Library

IncludeToolboxComponents Property (IPackAndGo)

Syntax

Visual Basic for Applications (VBA)

```
Public Property IncludeToolboxComponents As Boolean
```

ISetDocumentSaveToNames Method (IPackAndGo) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function ISetDocumentSaveToNames( _  
    ByVal NameCount As Long, _  
    ByRef NameList As String _  
) As Boolean
```

RemoveExternalDocuments Method (IPackAndGo) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function RemoveExternalDocuments( _  
    ByVal DocumentNames As Variant _  
) As Boolean
```

SetDocumentSaveToNames Method (IPackAndGo) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function SetDocumentSaveToNames( _  
    ByVal PathNameList As Variant _  
) As Boolean
```

SetSaveToName Method (IPackAndGo) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function SetSaveToName( _  
    ByVal Override As Boolean, _  
    ByVal SaveToName As String _  
) As Boolean
```

SetSaveToName2 Method (IPackAndGo) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function SetSaveToName2( _  
    ByVal Override As Boolean, _  
    ByVal SaveToName As String _  
) As Boolean
```

IParagraphs (Type)

SOLIDWORKS Type Library
IParagraphs Object

Object Model

IParagraphs

SOLIDWORKS Type Library
IParagraphs Object Members

Public Methods

-  [GetBulletsAndNumbering](#)
-  [GetFormatting](#)
-  [GetIndentation](#)
-  [GetText](#)
-  [GetTextSegmentCount](#)
-  [GetTextSegmentFormat](#)
-  [GetTextSegmentText](#)
-  [SetBulletsAndNumbering](#)
-  [SetFormatting](#)
-  [SetIndentation](#)
-  [SetTextSegmentFormat](#)
-  [UpdateParagraph](#)

Public Properties

-  [Count](#)
-  [CurrentParagraph](#)

SOLIDWORKS Type Library
Count Property (IParagraphs)

Syntax

Visual Basic for Applications (VBA)

Public Property Count As Long

SOLIDWORKS Type Library
CurrentParagraph Property (IParagraphs)

Syntax

Visual Basic for Applications (VBA)

Public Property CurrentParagraph As Long

SOLIDWORKS Type Library
GetBulletsAndNumbering Method (IParagraphs)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetBulletsAndNumbering( _  
    ByRef ParagraphType As Long, _  
    ByRef NumberingType As Long, _
```

```
ByRef StartAt As Long, _  
ByRef Type As Long, _  
ByRef Format As Long _  
) As Boolean
```

SOLIDWORKS Type Library

GetFormatting Method (IParagraphs)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFormatting( _  
ByRef Paragraphspacing As Double, _  
ByRef LineSpacing As Double _  
) As Boolean
```

SOLIDWORKS Type Library

GetIndentation Method (IParagraphs)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetIndentation( _  
ByRef FirstlineIndent As Double, _  
ByRef Indent As Double, _  
ByRef IndentIncrement As Double _  
) As Boolean
```

SOLIDWORKS Type Library

GetText Method (IParagraphs)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetText( _  
ByVal ShowWordWrap As Boolean _  
) As String
```

SOLIDWORKS Type Library

GetTextSegmentCount Method (IParagraphs)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTextSegmentCount() As Long
```

SOLIDWORKS Type Library

GetTextSegmentFormat Method (IParagraphs)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTextSegmentFormat( _  
ByVal Index As Long _  
) As Object
```

SOLIDWORKS Type Library

GetTextSegmentText Method (IParagraphs)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTextSegmentText( _  
ByVal Index As Long _  
) As String
```

SetBulletsAndNumbering Method (IParagraphs)**Syntax**

Visual Basic for Applications (VBA)

```
Public Function SetBulletsAndNumbering( _  
    ByVal ParagraphType As Long, _  
    ByVal NumberingType As Long, _  
    ByVal StartAt As Long, _  
    ByVal Type As Long, _  
    ByVal Format As Long _  
) As Boolean
```

SetFormatting Method (IParagraphs)**Syntax**

Visual Basic for Applications (VBA)

```
Public Function SetFormatting( _  
    ByVal Paragraphspacing As Double, _  
    ByVal LineSpacing As Double _  
) As Boolean
```

SetIndentation Method (IParagraphs)**Syntax**

Visual Basic for Applications (VBA)

```
Public Function SetIndentation( _  
    ByVal FirstlineIndent As Double, _  
    ByVal Indent As Double, _  
    ByVal IndentIncrement As Double _  
) As Boolean
```

SetTextSegmentFormat Method (IParagraphs)**Syntax**

Visual Basic for Applications (VBA)

```
Public Function SetTextSegmentFormat( _  
    ByVal Segment As Long, _  
    ByVal Format As Object _  
) As Boolean
```

UpdateParagraph Method (IParagraphs)**Syntax**

Visual Basic for Applications (VBA)

```
Public Function UpdateParagraph() As Boolean
```

IParallelMateFeatureData (Type)

SOLIDWORKS Type Library

IParallelMateFeatureData Object

Object Model

IParallelMateFeatureData

SOLIDWORKS Type Library

IParallelMateFeatureData Object Members

Public Properties

EntitiesToMate

MateAlignment

PickPoints

SOLIDWORKS Type Library

EntitiesToMate Property (IParallelMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property EntitiesToMate As Variant

SOLIDWORKS Type Library

MateAlignment Property (IParallelMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property MateAlignment As Long

SOLIDWORKS Type Library

PickPoints Property (IParallelMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property PickPoints As Variant

IPartExplodeStep (Type)

SOLIDWORKS Type Library

IPartExplodeStep Object

Object Model

IPartExplodeStep

SOLIDWORKS Type Library

IPartExplodeStep Object Members

Public Methods

-  [GetBodies](#)
-  [GetExplodeDirection](#)
-  [SetBodies](#)
-  [SetExplodeDirection](#)

Public Properties

-  [AutoSpaceBodiesOnDrag](#)
-  [ExplodeDistance](#)
-  [Name](#)
-  [ReverseTranslationDirection](#)

SOLIDWORKS Type Library

AutoSpaceBodiesOnDrag Property (IPartExplodeStep)

Syntax

Visual Basic for Applications (VBA)

Public Property AutoSpaceBodiesOnDrag As Boolean

SOLIDWORKS Type Library

ExplodeDistance Property (IPartExplodeStep)

Syntax

Visual Basic for Applications (VBA)

Public Property ExplodeDistance As Double

SOLIDWORKS Type Library

GetBodies Method (IPartExplodeStep)

Syntax

Visual Basic for Applications (VBA)

Public Function GetBodies() As Variant

SOLIDWORKS Type Library

GetExplodeDirection Method (IPartExplodeStep)

Syntax

Visual Basic for Applications (VBA)

Public Function GetExplodeDirection(_
 ByRef ExplDirIndex As Long _
) As Object

SOLIDWORKS Type Library

Name Property (IPartExplodeStep)



Visual Basic for Applications (VBA)

```
Public Property Name As String
```

SOLIDWORKS Type Library

ReverseTranslationDirection Property (IPartExplodeStep)



Visual Basic for Applications (VBA)

```
Public Property ReverseTranslationDirection As Boolean
```

SOLIDWORKS Type Library

SetBodies Method (IPartExplodeStep)



Visual Basic for Applications (VBA)

```
Public Sub SetBodies(  
    ByVal Bodies As Variant _  
)
```

SOLIDWORKS Type Library

SetExplodeDirection Method (IPartExplodeStep)



Visual Basic for Applications (VBA)

```
Public Sub SetExplodeDirection(  
    ByVal ExplodeDirection As Object, _  
    ByVal ExplDirIndex As Long _  
)
```

IPartialEdgeFilletData (Type)

SOLIDWORKS Type Library

IPartialEdgeFilletData Object

Object Model

IPartialEdgeFilletData

SOLIDWORKS Type Library

IPartialEdgeFilletData Object Members

Public Methods

SetPartialFilletParameters

Public Properties

AlongEdgeDirection

DistanceOffsetEnd

DistanceOffsetStart

EndCondition

PercentOffsetEnd

PercentOffsetStart

ReferenceOffsetEnd

ReferenceOffsetEndType

ReferenceOffsetStart

ReferenceOffsetStartType

StartCondition

SOLIDWORKS Type Library

AlongEdgeDirection Property (IPartialEdgeFilletData)

Syntax

Visual Basic for Applications (VBA)

Public Property AlongEdgeDirection As Boolean

SOLIDWORKS Type Library

DistanceOffsetEnd Property (IPartialEdgeFilletData)

Syntax

Visual Basic for Applications (VBA)

Public Property DistanceOffsetEnd As Double

SOLIDWORKS Type Library

DistanceOffsetStart Property (IPartialEdgeFilletData)

Syntax

Visual Basic for Applications (VBA)

Public Property DistanceOffsetStart As Double

SOLIDWORKS Type Library

EndCondition Property (IPartialEdgeFilletData)



Visual Basic for Applications (VBA)

```
Public Property EndCondition As Long
```

SOLIDWORKS Type Library

PercentOffsetEnd Property (IPartialEdgeFilletData)



Visual Basic for Applications (VBA)

```
Public Property PercentOffsetEnd As Double
```

SOLIDWORKS Type Library

PercentOffsetStart Property (IPartialEdgeFilletData)



Visual Basic for Applications (VBA)

```
Public Property PercentOffsetStart As Double
```

SOLIDWORKS Type Library

ReferenceOffsetEnd Property (IPartialEdgeFilletData)



Visual Basic for Applications (VBA)

```
Public Property ReferenceOffsetEnd As Object
```

SOLIDWORKS Type Library

ReferenceOffsetEndType Property (IPartialEdgeFilletData)



Visual Basic for Applications (VBA)

```
Public Property ReferenceOffsetEndType As Long
```

SOLIDWORKS Type Library

ReferenceOffsetStart Property (IPartialEdgeFilletData)



Visual Basic for Applications (VBA)

```
Public Property ReferenceOffsetStart As Object
```

SOLIDWORKS Type Library

ReferenceOffsetStartType Property (IPartialEdgeFilletData)



Visual Basic for Applications (VBA)

```
Public Property ReferenceOffsetStartType As Long
```

SOLIDWORKS Type Library

SetPartialFilletParameters Method (IPartialEdgeFilletData)



Visual Basic for Applications (VBA)

```
Public Function SetPartialFilletParameters( _  
    ByVal AlongEdgeDirection As Boolean, _  
    ByVal StartCondition As Long, _  
    ByVal StartValue As Double, _  
    ByVal StartReference As Object, _  
    ByVal EndCondition As Long, _
```

```
ByVal EndValue As Double, _  
    ByVal EndReference As Object _  
) As Long
```

SOLIDWORKS Type Library

StartCondition Property (IPartialEdgeFilletData)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Property StartCondition As Long
```

IPerpendicularMateFeatureData (Type)

SOLIDWORKS Type Library
IPerpendicularMateFeatureData Object

 Object Model

IPerpendicularMateFeatureData

SOLIDWORKS Type Library
IPerpendicularMateFeatureData Object Members



 Public Properties

 [EntitiesToMate](#)

 [PickPoints](#)

SOLIDWORKS Type Library
EntitiesToMate Property (IPerpendicularMateFeatureData)

 Syntax

Visual Basic for Applications (VBA)

Public Property EntitiesToMate As Variant

SOLIDWORKS Type Library
PickPoints Property (IPerpendicularMateFeatureData)

 Syntax

Visual Basic for Applications (VBA)


Public Property PickPoints As Variant

IPlaneManipulator (Type)

SOLIDWORKS Type Library

IPlaneManipulator Object

Object Model



SOLIDWORKS Type Library

IPlaneManipulator Object Members

Public Methods

[Update](#)

Public Properties

[Color](#)

[Distance](#)

[Height](#)

[Normal](#)

[Origin](#)

[Width](#)

[XAngle](#)

[YAngle](#)

SOLIDWORKS Type Library

Color Property (IPlaneManipulator)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Color As Long
```

SOLIDWORKS Type Library

Distance Property (IPlaneManipulator)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Distance As Double
```

SOLIDWORKS Type Library

Height Property (IPlaneManipulator)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Height As Double
```

SOLIDWORKS Type Library

Normal Property (IPlaneManipulator)

Syntax

Visual Basic for Applications (VBA)

Public Property Normal As [MathVector](#)

SOLIDWORKS Type Library

Origin Property (IPlaneManipulator)



Visual Basic for Applications (VBA)

Public Property Origin As [MathPoint](#)

SOLIDWORKS Type Library

Update Method (IPlaneManipulator)



Visual Basic for Applications (VBA)

Public Function Update() As Boolean

SOLIDWORKS Type Library

Width Property (IPlaneManipulator)



Visual Basic for Applications (VBA)

Public Property Width As Double

SOLIDWORKS Type Library

XAngle Property (IPlaneManipulator)



Visual Basic for Applications (VBA)

Public Property XAngle As Double

SOLIDWORKS Type Library

YAngle Property (IPlaneManipulator)



Visual Basic for Applications (VBA)

Public Property YAngle As Double

IPLMObjectSpecification (Type)

SOLIDWORKS Type Library

IPLMObjectSpecification Object

Object Model

IPLMObjectSpecification

SOLIDWORKS Type Library

IPLMObjectSpecification Object Members



Public Properties



PLMID

SOLIDWORKS Type Library

PLMID Property (IPLMObjectSpecification)

Syntax

Visual Basic for Applications (VBA)

Public Property PLMID As String

IPMIDatumData (Type)

SOLIDWORKS Type Library
IPMIDatumData Object

Object Model

IPMIDatumData

SOLIDWORKS Type Library
IPMIDatumData Object Members

Public Methods

- GetDatumFeature
- GetDatumTarget
- GetDatumType

SOLIDWORKS Type Library
GetDatumFeature Method (IPMIDatumData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDatumFeature() As Object
```

SOLIDWORKS Type Library
GetDatumTarget Method (IPMIDatumData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDatumTarget() As Object
```

SOLIDWORKS Type Library
GetDatumType Method (IPMIDatumData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDatumType() As Long
```

IPMIDatumFeature (Type)

SOLIDWORKS Type Library
IPMIDatumFeature Object

 Object Model

IPMIDatumFeature

SOLIDWORKS Type Library
IPMIDatumFeature Object Members



 Public Properties

 [Label](#)

 [LeaderAnchorStyle](#)

 [LeaderBendLength](#)

 [Shape](#)

 [Text](#)

SOLIDWORKS Type Library
Label Property (IPMIDatumFeature)

 Syntax

Visual Basic for Applications (VBA)

Public Property Label As String

SOLIDWORKS Type Library
LeaderAnchorStyle Property (IPMIDatumFeature)

 Syntax

Visual Basic for Applications (VBA)

Public Property LeaderAnchorStyle As Long

SOLIDWORKS Type Library
LeaderBendLength Property (IPMIDatumFeature)

 Syntax

Visual Basic for Applications (VBA)

Public Property LeaderBendLength As Double

SOLIDWORKS Type Library
Shape Property (IPMIDatumFeature)

 Syntax

Visual Basic for Applications (VBA)

Public Property Shape As Long

SOLIDWORKS Type Library
Text Property (IPMIDatumFeature)

 Syntax

Visual Basic for Applications (VBA)

Public Property Text As String

IPMIDatumTarget (Type)

SOLIDWORKS Type Library
IPMIDatumTarget Object

Object Model

IPMIDatumTarget

SOLIDWORKS Type Library
IPMIDatumTarget Object Members

Public Methods

 [GetDatumTargetReferences](#)

Public Properties

 [AreaStyle](#)

 [Diameter](#)

 [Height](#)

 [MovableStyle](#)

 [SymbolStyle](#)

 [Unit](#)

 [Width](#)

SOLIDWORKS Type Library
AreaStyle Property (IPMIDatumTarget)

Syntax

Visual Basic for Applications (VBA)

Public Property AreaStyle As Long

SOLIDWORKS Type Library
Diameter Property (IPMIDatumTarget)

Syntax

Visual Basic for Applications (VBA)

Public Property Diameter As Double

SOLIDWORKS Type Library
GetDatumTargetReferences Method (IPMIDatumTarget)

Syntax

Visual Basic for Applications (VBA)

Public Function GetDatumTargetReferences() As Variant

SOLIDWORKS Type Library
Height Property (IPMIDatumTarget)

Syntax

Visual Basic for Applications (VBA)

Public Property Height As Double

SOLIDWORKS Type Library

MovableStyle Property (IPMIDatumTarget)



Visual Basic for Applications (VBA)

Public Property MovableStyle As Long

SOLIDWORKS Type Library

SymbolStyle Property (IPMIDatumTarget)



Visual Basic for Applications (VBA)

Public Property SymbolStyle As Long

SOLIDWORKS Type Library

Unit Property (IPMIDatumTarget)



Visual Basic for Applications (VBA)

Public Property Unit As Long

SOLIDWORKS Type Library

Width Property (IPMIDatumTarget)



Visual Basic for Applications (VBA)

Public Property Width As Double

IPMIDimensionData (Type)

SOLIDWORKS Type Library

IPMIDimensionData Object

Object Model

IPMIDimensionData

SOLIDWORKS Type Library

IPMIDimensionData Object Members



Public Methods

 [GetDimensionItemAtIndex](#)

 [GetDimensionItemCount](#)

Public Properties

 [DimensionText](#)

SOLIDWORKS Type Library

DimensionText Property (IPMIDimensionData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property DimensionText As String
```

SOLIDWORKS Type Library

GetDimensionItemAtIndex Method (IPMIDimensionData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionItemAtIndex( _  
    ByVal Index As Long _  
) As Object
```

SOLIDWORKS Type Library

GetDimensionItemCount Method (IPMIDimensionData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDimensionItemCount() As Long
```