

SOLIDWORKS API (VB6 COM) — Reference (44/102): IPMIDimensionItem-IRayTraceRenderer

SOLIDWORKS API Documentation (converted from CHM)

IPMIDimensionItem (Type)

SOLIDWORKS Type Library
IPMIDimensionItem Object

Object Model

IPMIDimensionItem

SOLIDWORKS Type Library
IPMIDimensionItem Object Members

Public Methods

IsReferenceOnly

Public Properties

AdditionalSymbol

CalloutText

InstanceCount

MaxVariation

MinVariation

Prefix

Suffix

Symbol

TolerancePrecision

TolType

Unit

Value

ValuePrecision

SOLIDWORKS Type Library
AdditionalSymbol Property (IPMIDimensionItem)

Syntax

Visual Basic for Applications (VBA)

Public Property AdditionalSymbol As Long

SOLIDWORKS Type Library
CalloutText Property (IPMIDimensionItem)

Syntax

Visual Basic for Applications (VBA)

Public Property CalloutText As String

SOLIDWORKS Type Library
InstanceCount Property (IPMIDimensionItem)

Syntax

Visual Basic for Applications (VBA)

Public Property InstanceCount As Long

SOLIDWORKS Type Library

IsReferenceOnly Method (IPMIDimensionItem)



Visual Basic for Applications (VBA)

```
Public Function IsReferenceOnly() As Boolean
```

SOLIDWORKS Type Library

MaxVariation Property (IPMIDimensionItem)



Visual Basic for Applications (VBA)

```
Public Property MaxVariation As Double
```

SOLIDWORKS Type Library

MinVariation Property (IPMIDimensionItem)



Visual Basic for Applications (VBA)

```
Public Property MinVariation As Double
```

SOLIDWORKS Type Library

Prefix Property (IPMIDimensionItem)



Visual Basic for Applications (VBA)

```
Public Property Prefix As String
```

SOLIDWORKS Type Library

Suffix Property (IPMIDimensionItem)



Visual Basic for Applications (VBA)

```
Public Property Suffix As String
```

SOLIDWORKS Type Library

Symbol Property (IPMIDimensionItem)



Visual Basic for Applications (VBA)

```
Public Property Symbol As Long
```

SOLIDWORKS Type Library

TolerancePrecision Property (IPMIDimensionItem)



Visual Basic for Applications (VBA)

```
Public Property TolerancePrecision As Long
```

SOLIDWORKS Type Library

TolType Property (IPMIDimensionItem)



Visual Basic for Applications (VBA)

```
Public Property TolType As Long
```

Unit Property (IPMIDimensionItem)



Visual Basic for Applications (VBA)

Public Property Unit As Long

Value Property (IPMIDimensionItem)



Visual Basic for Applications (VBA)

Public Property Value As Double

ValuePrecision Property (IPMIDimensionItem)



Visual Basic for Applications (VBA)

Public Property ValuePrecision As Long

IPMIFrameData (Type)

SOLIDWORKS Type Library

IPMIFrameData Object

Object Model

IPMIFrameData

SOLIDWORKS Type Library

IPMIFrameData Object Members

Public Methods

-  [GetGtolBoxAtIndex](#)
-  [GetGtolBoxCount](#)
-  [GetGtolDatumAtIndex](#)
-  [GetGtolDatumCount](#)

Public Properties

-  [FrameNumber](#)
-  [GeometricCharacteristic](#)

SOLIDWORKS Type Library

FrameNumber Property (IPMIFrameData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property FrameNumber As Long
```

SOLIDWORKS Type Library

GeometricCharacteristic Property (IPMIFrameData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property GeometricCharacteristic As Long
```

SOLIDWORKS Type Library

GetGtolBoxAtIndex Method (IPMIFrameData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetGtolBoxAtIndex( _  
    ByVal Index As Long _  
) As Object
```

SOLIDWORKS Type Library

GetGtolBoxCount Method (IPMIFrameData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetGtolBoxCount() As Long
```

SOLIDWORKS Type Library

GetGtolDatumAtIndex Method (IPMIFrameData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetGtolDatumAtIndex( _  
    ByVal Index As Long _  
) As Object
```

SOLIDWORKS Type Library

GetGtolDatumCount Method (IPMIFrameData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetGtolDatumCount() As Long
```

IPMIGtolBoxData (Type)

SOLIDWORKS Type Library
IPMIGtolBoxData Object

 Object Model

IPMIGtolBoxData

SOLIDWORKS Type Library
IPMIGtolBoxData Object Members

 Public Methods

-  [GetAdditionalSymbols](#)
-  [GetTolTypes](#)
-  [GetTolTypeValues](#)

 Public Properties

-  [MaterialModifier](#)
-  [TolerancePerUnitType](#)
-  [TolerancePerUnitValue1](#)
-  [TolerancePerUnitValue2](#)
-  [ToleranceZoneModifier](#)
-  [TolValue](#)
-  [Unit](#)

SOLIDWORKS Type Library
GetAdditionalSymbols Method (IPMIGtolBoxData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function GetAdditionalSymbols() As Variant
```

SOLIDWORKS Type Library
GetTolTypes Method (IPMIGtolBoxData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTolTypes() As Variant
```

SOLIDWORKS Type Library
GetTolTypeValues Method (IPMIGtolBoxData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTolTypeValues() As Variant
```

SOLIDWORKS Type Library
MaterialModifier Property (IPMIGtolBoxData)

 Syntax

Visual Basic for Applications (VBA)

Public Property MaterialModifier As Long

SOLIDWORKS Type Library

TolerancePerUnitType Property (IPMIGtolBoxData)



Visual Basic for Applications (VBA)

Public Property TolerancePerUnitType As Long

SOLIDWORKS Type Library

TolerancePerUnitValue1 Property (IPMIGtolBoxData)



Visual Basic for Applications (VBA)

Public Property TolerancePerUnitValue1 As Double

SOLIDWORKS Type Library

TolerancePerUnitValue2 Property (IPMIGtolBoxData)



Visual Basic for Applications (VBA)

Public Property TolerancePerUnitValue2 As Double

SOLIDWORKS Type Library

ToleranceZoneModifier Property (IPMIGtolBoxData)



Visual Basic for Applications (VBA)

Public Property ToleranceZoneModifier As Long

SOLIDWORKS Type Library

TolValue Property (IPMIGtolBoxData)



Visual Basic for Applications (VBA)

Public Property TolValue As Double

SOLIDWORKS Type Library

Unit Property (IPMIGtolBoxData)



Visual Basic for Applications (VBA)

Public Property Unit As Long

IPMIGtoIData (Type)

SOLIDWORKS Type Library
IPMIGtoIData Object

Object Model

IPMIGtoIData

SOLIDWORKS Type Library
IPMIGtoIData Object Members

Public Methods

	GetFirstPoint
	GetFrameAtIndex
	GetFrameCount
	GetSecondPoint
	GetText
	GetTextBelowFrames
	IsComposite

Public Properties

	InstanceCount
	LeaderLocation
	LeaderModifier
	LeaderStyle
	LeaderType

SOLIDWORKS Type Library
GetFirstPoint Method (IPMIGtoIData)

Syntax

```
Visual Basic for Applications (VBA)

Public Function GetFirstPoint() As String
```

SOLIDWORKS Type Library
GetFrameAtIndex Method (IPMIGtoIData)

Syntax

```
Visual Basic for Applications (VBA)

Public Function GetFrameAtIndex( _
    ByVal Index As Long _
) As Object
```

SOLIDWORKS Type Library
GetFrameCount Method (IPMIGtoIData)

Syntax

```
Visual Basic for Applications (VBA)

Public Function GetFrameCount() As Long
```

SOLIDWORKS Type Library

GetSecondPoint Method (IPMIGtolData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSecondPoint() As String
```

SOLIDWORKS Type Library

GetText Method (IPMIGtolData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetText() As String
```

SOLIDWORKS Type Library

GetTextBelowFrames Method (IPMIGtolData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTextBelowFrames() As String
```

SOLIDWORKS Type Library

InstanceCount Property (IPMIGtolData)



Syntax

Visual Basic for Applications (VBA)

```
Public Property InstanceCount As Long
```

SOLIDWORKS Type Library

IsComposite Method (IPMIGtolData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IsComposite() As Boolean
```

SOLIDWORKS Type Library

LeaderLocation Property (IPMIGtolData)



Syntax

Visual Basic for Applications (VBA)

```
Public Property LeaderLocation As Long
```

SOLIDWORKS Type Library

LeaderModifier Property (IPMIGtolData)



Syntax

Visual Basic for Applications (VBA)

```
Public Property LeaderModifier As Long
```

SOLIDWORKS Type Library

LeaderStyle Property (IPMIGtolData)



Syntax

Visual Basic for Applications (VBA)

```
Public Property LeaderStyle As Long
```

SOLIDWORKS Type Library



Syntax

Visual Basic for Applications (VBA)

Public Property LeaderType As Long

IPMIGtoIFrameDatum (Type)

SOLIDWORKS Type Library
IPMIGtoIFrameDatum Object

Object Model

IPMIGtoIFrameDatum

SOLIDWORKS Type Library
IPMIGtoIFrameDatum Object Members

Public Properties

- Datum
- DatumLinked1
- DatumLinked2
- DatumLinkedModifier1
- DatumLinkedModifier2
- DatumLinkedModifierValue1
- DatumLinkedModifierValue2
- DatumModifier
- DatumModifierValue

SOLIDWORKS Type Library
Datum Property (IPMIGtoIFrameDatum)

Syntax

Visual Basic for Applications (VBA)

Public Property Datum As String

SOLIDWORKS Type Library
DatumLinked1 Property (IPMIGtoIFrameDatum)

Syntax

Visual Basic for Applications (VBA)

Public Property DatumLinked1 As String

SOLIDWORKS Type Library
DatumLinked2 Property (IPMIGtoIFrameDatum)

Syntax

Visual Basic for Applications (VBA)

Public Property DatumLinked2 As String

SOLIDWORKS Type Library
DatumLinkedModifier1 Property (IPMIGtoIFrameDatum)

Syntax

Visual Basic for Applications (VBA)

Public Property DatumLinkedModifier1 As Long

SOLIDWORKS Type Library
DatumLinkedModifier2 Property (IPMIGtoIFrameDatum)



Visual Basic for Applications (VBA)

```
Public Property DatumLinkedModifier2 As Long
```

SOLIDWORKS Type Library

DatumLinkedModifierValue1 Property (IPMIGtolFrameDatum)



Visual Basic for Applications (VBA)

```
Public Property DatumLinkedModifierValue1 As Double
```

SOLIDWORKS Type Library

DatumLinkedModifierValue2 Property (IPMIGtolFrameDatum)



Visual Basic for Applications (VBA)

```
Public Property DatumLinkedModifierValue2 As Double
```

SOLIDWORKS Type Library

DatumModifier Property (IPMIGtolFrameDatum)



Visual Basic for Applications (VBA)

```
Public Property DatumModifier As Long
```

SOLIDWORKS Type Library

DatumModifierValue Property (IPMIGtolFrameDatum)



Visual Basic for Applications (VBA)

```
Public Property DatumModifierValue As Double
```

IPrimaryMemberFacePlaneIntersectionFeatureData (Type)

SOLIDWORKS Type Library

IPrimaryMemberFacePlaneIntersectionFeatureData Object

Object Model

IPrimaryMemberFacePlaneIntersectionFeatureData

SOLIDWORKS Type Library

IPrimaryMemberFacePlaneIntersectionFeatureData Object Members

Public Methods

 [GetIntersectingObjectTypes](#)

 [GetIntersectingPlanesAndFaces](#)

 [GetParameterFaces](#)

 [SetIntersectingPlanesAndFaces](#)

 [SetParameterFaces](#)

Public Properties

 [MergeTangentMembers](#)

SOLIDWORKS Type Library

GetIntersectingObjectTypes Method (IPrimaryMemberFacePlaneIntersectionFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetIntersectingObjectTypes() As Variant
```

SOLIDWORKS Type Library

GetIntersectingPlanesAndFaces Method (IPrimaryMemberFacePlaneIntersectionFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetIntersectingPlanesAndFaces() As Variant
```

SOLIDWORKS Type Library

GetParameterFaces Method (IPrimaryMemberFacePlaneIntersectionFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetParameterFaces() As Variant
```

SOLIDWORKS Type Library

MergeTangentMembers Property (IPrimaryMemberFacePlaneIntersectionFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property MergeTangentMembers As Boolean
```

SOLIDWORKS Type Library

SetIntersectingPlanesAndFaces Method (IPrimaryMemberFacePlaneIntersectionFeatureData)

Syntax

```
Public Function SetIntersectingPlanesAndFaces( _  
    ByVal RefList As Variant _  
) As Boolean
```

 Syntax

```
Public Function SetParameterFaces( _  
    ByVal Faces As Variant _  
) As Boolean
```

IPrimaryMemberPathSegmentFeatureData (Type)

SOLIDWORKS Type Library

IPrimaryMemberPathSegmentFeatureData Object

 Object Model

IPrimaryMemberPathSegmentFeatureData

SOLIDWORKS Type Library

IPrimaryMemberPathSegmentFeatureData Object Members

 Public Methods

 [GetPathSegments](#)

 [GetPathSegmentsTypes](#)

 [SetPathSegments](#)

 Public Properties

 [MergeTangentMembers](#)

SOLIDWORKS Type Library

GetPathSegments Method (IPrimaryMemberPathSegmentFeatureData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPathSegments() As Variant
```

SOLIDWORKS Type Library

GetPathSegmentsTypes Method (IPrimaryMemberPathSegmentFeatureData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPathSegmentsTypes() As Variant
```

SOLIDWORKS Type Library

MergeTangentMembers Property (IPrimaryMemberPathSegmentFeatureData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Property MergeTangentMembers As Boolean
```

SOLIDWORKS Type Library

SetPathSegments Method (IPrimaryMemberPathSegmentFeatureData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function SetPathSegments( _  
    ByVal PathSegments As Variant _  
) As Boolean
```


IPrimaryMemberPointLengthFeatureData (Type)

SOLIDWORKS Type Library

IPrimaryMemberPointLengthFeatureData Object

Object Model

IPrimaryMemberPointLengthFeatureData

SOLIDWORKS Type Library

IPrimaryMemberPointLengthFeatureData Object Members

Public Methods

 [GetPoints](#)

 [GetPointsTypes](#)

 [SetPoints](#)

Public Properties

 [DirectionReference](#)

 [EndCondition](#)

 [EndPlane](#)

 [EndPoint](#)

 [Length](#)

 [ReverseDirection](#)

 [UnChainPointsAndLength](#)

SOLIDWORKS Type Library

DirectionReference Property (IPrimaryMemberPointLengthFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property DirectionReference As Object

SOLIDWORKS Type Library

EndCondition Property (IPrimaryMemberPointLengthFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property EndCondition As Long

SOLIDWORKS Type Library

EndPlane Property (IPrimaryMemberPointLengthFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property EndPlane As Object

SOLIDWORKS Type Library

EndPoint Property (IPrimaryMemberPointLengthFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property EndPoint As Object

SOLIDWORKS Type Library

GetPoints Method (IPrimaryMemberPointLengthFeatureData)



Visual Basic for Applications (VBA)

Public Function GetPoints() As Variant

SOLIDWORKS Type Library

GetPointsTypes Method (IPrimaryMemberPointLengthFeatureData)



Visual Basic for Applications (VBA)

Public Function GetPointsTypes() As Variant

SOLIDWORKS Type Library

Length Property (IPrimaryMemberPointLengthFeatureData)



Visual Basic for Applications (VBA)

Public Property Length As Double

SOLIDWORKS Type Library

ReverseDirection Property (IPrimaryMemberPointLengthFeatureData)



Visual Basic for Applications (VBA)

Public Property ReverseDirection As Boolean

SOLIDWORKS Type Library

SetPoints Method (IPrimaryMemberPointLengthFeatureData)



Visual Basic for Applications (VBA)

```
Public Function SetPoints( _  
    ByVal Points As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

UnChainPointsAndLength Property (IPrimaryMemberPointLengthFeatureData)



Visual Basic for Applications (VBA)

Public Property UnChainPointsAndLength As Boolean

IPrimaryMemberRefPlaneFeatureData (Type)

SOLIDWORKS Type Library

IPrimaryMemberRefPlaneFeatureData Object

Object Model

IPrimaryMemberRefPlaneFeatureData

SOLIDWORKS Type Library

IPrimaryMemberRefPlaneFeatureData Object Members

Public Methods

	GetReferenceAxes
	GetReferenceAxesTypes
	GetReferenceLocations
	GetReferenceLocationsTypes
	GetStartAndEndReferences
	GetStartAndEndReferencesTypes
	SetReferenceAxes
	SetReferenceLocations
	SetStartAndEndReferences

SOLIDWORKS Type Library

GetReferenceAxes Method (IPrimaryMemberRefPlaneFeatureData)

Syntax

Visual Basic for Applications (VBA)
Public Function GetReferenceAxes() As Variant

SOLIDWORKS Type Library

GetReferenceAxesTypes Method (IPrimaryMemberRefPlaneFeatureData)

Syntax

Visual Basic for Applications (VBA)
Public Function GetReferenceAxesTypes() As Variant

SOLIDWORKS Type Library

GetReferenceLocations Method (IPrimaryMemberRefPlaneFeatureData)

Syntax

Visual Basic for Applications (VBA)
Public Function GetReferenceLocations() As Variant

SOLIDWORKS Type Library

GetReferenceLocationsTypes Method (IPrimaryMemberRefPlaneFeatureData)

Syntax

Visual Basic for Applications (VBA)
Public Function GetReferenceLocationsTypes() As Variant

SOLIDWORKS Type Library

GetStartAndEndReferences Method (IPrimaryMemberRefPlaneFeatureData)



Visual Basic for Applications (VBA)

```
Public Function GetStartAndEndReferences() As Variant
```

SOLIDWORKS Type Library

GetStartAndEndReferencesTypes Method (IPrimaryMemberRefPlaneFeatureData)



Visual Basic for Applications (VBA)

```
Public Function GetStartAndEndReferencesTypes() As Variant
```

SOLIDWORKS Type Library

SetReferenceAxes Method (IPrimaryMemberRefPlaneFeatureData)



Visual Basic for Applications (VBA)

```
Public Function SetReferenceAxes( _  
    ByVal RetEntities As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

SetReferenceLocations Method (IPrimaryMemberRefPlaneFeatureData)



Visual Basic for Applications (VBA)

```
Public Function SetReferenceLocations( _  
    ByVal RetEntities As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

SetStartAndEndReferences Method (IPrimaryMemberRefPlaneFeatureData)



Visual Basic for Applications (VBA)

```
Public Function SetStartAndEndReferences( _  
    ByVal RetEntities As Variant _  
) As Boolean
```

IPrimaryStructuralMemberFeatureData (Type)

SOLIDWORKS Type Library

IPrimaryStructuralMemberFeatureData Object

Object Model

IPrimaryStructuralMemberFeatureData

SOLIDWORKS Type Library

IPrimaryStructuralMemberFeatureData Object Members

Public Properties

PrimaryMemberType

SOLIDWORKS Type Library

PrimaryMemberType Property (IPrimaryStructuralMemberFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property PrimaryMemberType As Long

IPrintSpecification (Type)

SOLIDWORKS Type Library
IPrintSpecification Object

 Object Model

IPrintSpecification

SOLIDWORKS Type Library
IPrintSpecification Object Members

 Public Methods

 AddPrintRange
 ResetPrintRange
 RestoreDefaults

 Public Properties

 Collate
 ConvertToHighQuality
 CurrentSheet
 FromScale
 NumberOfCopies
 PrintBackground
 PrintCrossHatchOnOutOfDateViews
 PrinterQueue
 PrintFile
 PrintRange
 PrintToFile
 PrintWhiteItemsBlack
 ScaleMethod
 SheetCount
 ToScale
 XOrigin
 YOrigin

SOLIDWORKS Type Library
AddPrintRange Method (IPrintSpecification)

 Syntax

```
Visual Basic for Applications (VBA)

Public Sub AddPrintRange( _
    ByVal FirstPage As Long, _
    ByVal LastPage As Long _
)
```

SOLIDWORKS Type Library
Collate Property (IPrintSpecification)

 Syntax

```
Visual Basic for Applications (VBA)
```

Public Property Collate As Boolean

SOLIDWORKS Type Library

ConvertToHighQuality Property (IPrintSpecification)



Visual Basic for Applications (VBA)

Public Property ConvertToHighQuality As Boolean

SOLIDWORKS Type Library

CurrentSheet Property (IPrintSpecification)



Visual Basic for Applications (VBA)

Public Property CurrentSheet As Long

SOLIDWORKS Type Library

FromScale Property (IPrintSpecification)



Visual Basic for Applications (VBA)

Public Property FromScale As Double

SOLIDWORKS Type Library

NumberOfCopies Property (IPrintSpecification)



Visual Basic for Applications (VBA)

Public Property NumberOfCopies As Long

SOLIDWORKS Type Library

PrintBackground Property (IPrintSpecification)



Visual Basic for Applications (VBA)

Public Property PrintBackground As Boolean

SOLIDWORKS Type Library

PrintCrossHatchOnOutOfDateViews Property (IPrintSpecification)



Visual Basic for Applications (VBA)

Public Property PrintCrossHatchOnOutOfDateViews As Boolean

SOLIDWORKS Type Library

PrinterQueue Property (IPrintSpecification)



Visual Basic for Applications (VBA)

Public Property PrinterQueue As String

SOLIDWORKS Type Library

PrintFile Property (IPrintSpecification)



Visual Basic for Applications (VBA)

Public Property PrintFile As String

SOLIDWORKS Type Library

PrintRange Property (IPrintSpecification)



Visual Basic for Applications (VBA)

Public Property PrintRange As Variant

SOLIDWORKS Type Library

PrintToFile Property (IPrintSpecification)



Visual Basic for Applications (VBA)

Public Property PrintToFile As Boolean

SOLIDWORKS Type Library

PrintWhiteItemsBlack Property (IPrintSpecification)



Visual Basic for Applications (VBA)

Public Property PrintWhiteItemsBlack As Boolean

SOLIDWORKS Type Library

ResetPrintRange Method (IPrintSpecification)



Visual Basic for Applications (VBA)

Public Sub ResetPrintRange()

SOLIDWORKS Type Library

RestoreDefaults Method (IPrintSpecification)



Visual Basic for Applications (VBA)

Public Sub RestoreDefaults()

SOLIDWORKS Type Library

ScaleMethod Property (IPrintSpecification)



Visual Basic for Applications (VBA)

Public Property ScaleMethod As Long

SOLIDWORKS Type Library

SheetCount Property (IPrintSpecification)



Visual Basic for Applications (VBA)

Public Property SheetCount As Long

SOLIDWORKS Type Library

ToScale Property (IPrintSpecification)



Visual Basic for Applications (VBA)

Public Property ToScale As Double

SOLIDWORKS Type Library

XOrigin Property (IPrintSpecification)

Syntax

Visual Basic for Applications (VBA)

Public Property X0origin As Double

SOLIDWORKS Type Library

YOrigin Property (IPrintSpecification)

Syntax

Visual Basic for Applications (VBA)

Public Property Y0origin As Double

IProfileCenterMateFeatureData (Type)

SOLIDWORKS Type Library
IProfileCenterMateFeatureData Object

Object Model

IProfileCenterMateFeatureData

SOLIDWORKS Type Library
IProfileCenterMateFeatureData Object Members

Public Properties

- EntitiesToMate
- FlipDimension
- LockRotation
- MateAlignment
- OffsetDistance

SOLIDWORKS Type Library
EntitiesToMate Property (IProfileCenterMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property EntitiesToMate As Variant

SOLIDWORKS Type Library
FlipDimension Property (IProfileCenterMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property FlipDimension As Boolean

SOLIDWORKS Type Library
LockRotation Property (IProfileCenterMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property LockRotation As Boolean

SOLIDWORKS Type Library
MateAlignment Property (IProfileCenterMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property MateAlignment As Long

SOLIDWORKS Type Library
OffsetDistance Property (IProfileCenterMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property OffsetDistance As Double

IProfileGroupFolder (Type)

SOLIDWORKS Type Library

IProfileGroupFolder Object

Object Model

IProfileGroupFolder

GetFeature (Feature)

SOLIDWORKS Type Library

IProfileGroupFolder Object Members

Public Methods

GetFeature

GetPlane

GetSketch

GetStructureSystemMemberCount

GetStructureSystemMembers

Public Properties

ProfileSize

ProfileStandard

ProfileType

SOLIDWORKS Type Library

GetFeature Method (IProfileGroupFolder)

Syntax

Visual Basic for Applications (VBA)

Public Function GetFeature() As [Feature](#)

SOLIDWORKS Type Library

GetPlane Method (IProfileGroupFolder)

Syntax

Visual Basic for Applications (VBA)

Public Function GetPlane() As Object

SOLIDWORKS Type Library

GetSketch Method (IProfileGroupFolder)

Syntax

Visual Basic for Applications (VBA)

Public Function GetSketch() As Object

SOLIDWORKS Type Library

GetStructureSystemMemberCount Method (IProfileGroupFolder)

Syntax

Visual Basic for Applications (VBA)

Public Function GetStructureSystemMemberCount() As Long

SOLIDWORKS Type Library

GetStructureSystemMembers Method (IProfileGroupFolder)



Visual Basic for Applications (VBA)

```
Public Function GetStructureSystemMembers() As Variant
```

SOLIDWORKS Type Library

ProfileSize Property (IProfileGroupFolder)



Visual Basic for Applications (VBA)

```
Public Property ProfileSize As String
```

SOLIDWORKS Type Library

ProfileStandard Property (IProfileGroupFolder)



Visual Basic for Applications (VBA)

```
Public Property ProfileStandard As String
```

SOLIDWORKS Type Library

ProfileType Property (IProfileGroupFolder)



Visual Basic for Applications (VBA)

```
Public Property ProfileType As String
```

IPropertyManagerPageWindowFromHandle (Type)

SOLIDWORKS Type Library

IPropertyManagerPageWindowFromHandle Object

 Object Model

IPropertyManagerPageWindowFromHandle

SOLIDWORKS Type Library

IPropertyManagerPageWindowFromHandle Object Members



 Public Methods

 [SetWindowHandle](#)

 [SetWindowHandlex64](#)

 Public Properties

 [Height](#)

SOLIDWORKS Type Library

Height Property (IPropertyManagerPageWindowFromHandle)

 Syntax

Visual Basic for Applications (VBA)

Public Property Height As Long

SOLIDWORKS Type Library

SetWindowHandle Method (IPropertyManagerPageWindowFromHandle)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function SetWindowHandle( _  
    ByVal WindowHandle As Long _  
) As Boolean
```

SOLIDWORKS Type Library

SetWindowHandlex64 Method (IPropertyManagerPageWindowFromHandle)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function SetWindowHandlex64( _  
    ByVal WindowHandle As Unknown _  
) As Boolean
```

IPunchTable (Type)

SOLIDWORKS Type Library

IPunchTable Object

Object Model

IPunchTable

GetFeature (Feature)

IGetTableAnnotations (PunchTableAnnotation)

SOLIDWORKS Type Library

IPunchTable Object Members

Public Methods

 [GetFeature](#)

 [GetTableAnnotationCount](#)

 [GetTableAnnotations](#)

 [IGetTableAnnotations](#)

Public Properties

 [CombineSameSize](#)

 [CombineTags](#)

 [DualDimensions](#)

 [ShowUnits](#)

 [StartingValue](#)

 [TagStyle](#)

SOLIDWORKS Type Library

CombineSameSize Property (IPunchTable)

Syntax

Visual Basic for Applications (VBA)

```
Public Property CombineSameSize As Boolean
```

SOLIDWORKS Type Library

CombineTags Property (IPunchTable)

Syntax

Visual Basic for Applications (VBA)

```
Public Property CombineTags As Boolean
```

SOLIDWORKS Type Library

DualDimensions Property (IPunchTable)

Syntax

Visual Basic for Applications (VBA)

```
Public Property DualDimensions As Boolean
```

SOLIDWORKS Type Library

GetFeature Method (IPunchTable)



Visual Basic for Applications (VBA)

```
Public Function GetFeature() As Feature
```

SOLIDWORKS Type Library

GetTableAnnotationCount Method (IPunchTable)



Visual Basic for Applications (VBA)

```
Public Function GetTableAnnotationCount() As Long
```

SOLIDWORKS Type Library

GetTableAnnotations Method (IPunchTable)



Visual Basic for Applications (VBA)

```
Public Function GetTableAnnotations() As Variant
```

SOLIDWORKS Type Library

IGetTableAnnotations Method (IPunchTable)



Visual Basic for Applications (VBA)

```
Public Function IGetTableAnnotations( _  
    ByVal Count As Long _  
    ) As PunchTableAnnotation
```

SOLIDWORKS Type Library

ShowUnits Property (IPunchTable)



Visual Basic for Applications (VBA)

```
Public Property ShowUnits As Boolean
```

SOLIDWORKS Type Library

StartingValue Property (IPunchTable)



Visual Basic for Applications (VBA)

```
Public Property StartingValue As String
```

SOLIDWORKS Type Library

TagStyle Property (IPunchTable)




Visual Basic for Applications (VBA)

```
Public Property TagStyle As Long
```

IPunchTableAnnotation (Type)

SOLIDWORKS Type Library
IPunchTableAnnotation Object



SOLIDWORKS Type Library
IPunchTableAnnotation Object Members



Public Properties

 [PunchTable](#)

SOLIDWORKS Type Library
PunchTable Property (IPunchTableAnnotation)

Syntax

Visual Basic for Applications (VBA)

Public Property PunchTable As [PunchTable](#)

IRackPinionMateFeatureData (Type)

SOLIDWORKS Type Library

IRackPinionMateFeatureData Object

Object Model

IRackPinionMateFeatureData

SOLIDWORKS Type Library

IRackPinionMateFeatureData Object Members

Public Properties

DiameterType

DiameterVal

EntitiesToMate

Reverse

SOLIDWORKS Type Library

DiameterType Property (IRackPinionMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property DiameterType As Long

SOLIDWORKS Type Library

DiameterVal Property (IRackPinionMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property DiameterVal As Double

SOLIDWORKS Type Library

EntitiesToMate Property (IRackPinionMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property EntitiesToMate(_
 ByVal *EntityType* As Long _
) As Object

SOLIDWORKS Type Library

Reverse Property (IRackPinionMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property Reverse As Boolean

IRayTraceRenderer (Type)

SOLIDWORKS Type Library
IRayTraceRenderer Object

 Object Model

IRayTraceRenderer

RayTraceRendererOptions

SOLIDWORKS Type Library
IRayTraceRenderer Object Members

 Public Methods

-  [AbortFinalRender](#)
-  [CloseFinalRenderWindow](#)
-  [CloseRayTraceRender](#)
-  [DisplayPreviewWindow](#)
-  [InvokeFinalRender](#)
-  [RenderToFile](#)

 Public Properties

-  [RayTraceRendererOptions](#)

SOLIDWORKS Type Library
AbortFinalRender Method (IRayTraceRenderer)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function AbortFinalRender() As Boolean
```

SOLIDWORKS Type Library
CloseFinalRenderWindow Method (IRayTraceRenderer)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function CloseFinalRenderWindow() As Boolean
```

SOLIDWORKS Type Library
CloseRayTraceRender Method (IRayTraceRenderer)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function CloseRayTraceRender() As Boolean
```

SOLIDWORKS Type Library
DisplayPreviewWindow Method (IRayTraceRenderer)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function DisplayPreviewWindow() As Boolean
```

SOLIDWORKS Type Library

InvokeFinalRender Method (IRayTraceRenderer)



Visual Basic for Applications (VBA)

```
Public Function InvokeFinalRender() As Boolean
```

SOLIDWORKS Type Library

RayTraceRendererOptions Property (IRayTraceRenderer)



Visual Basic for Applications (VBA)

```
Public Property RayTraceRendererOptions As RayTraceRendererOptions
```

SOLIDWORKS Type Library

RenderToFile Method (IRayTraceRenderer)



Visual Basic for Applications (VBA)

```
Public Function RenderToFile( _  
    ByVal ImageFileName As String, _  
    ByVal Width As Long, _  
    ByVal Height As Long _  
) As Boolean
```