

SOLIDWORKS API (VB6 COM) — Reference (48/102): ITangentMateFeatureData-LayerMgr

SOLIDWORKS API Documentation (converted from CHM)

ITangentMateFeatureData (Type)

SOLIDWORKS Type Library

ITangentMateFeatureData Object

 Object Model

ITangentMateFeatureData

SOLIDWORKS Type Library

ITangentMateFeatureData Object Members



 Public Properties

-  [EntitiesToMate](#)
-  [MateAlignment](#)
-  [PickPoints](#)

SOLIDWORKS Type Library

EntitiesToMate Property (ITangentMateFeatureData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Property EntitiesToMate As Variant
```

SOLIDWORKS Type Library

MateAlignment Property (ITangentMateFeatureData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Property MateAlignment As Long
```

SOLIDWORKS Type Library

PickPoints Property (ITangentMateFeatureData)

 Syntax

Visual Basic for Applications (VBA)

```
Public Property PickPoints As Variant
```

ITaperedTapElementData (Type)

SOLIDWORKS Type Library

ITaperedTapElementData Object

Object Model

ITaperedTapElementData

SOLIDWORKS Type Library

ITaperedTapElementData Object Members

Public Properties

CustomSizing

EndConditionOverride

ThreadClass

ThreadClassOverride

UseStandardDepth

SOLIDWORKS Type Library

CustomSizing Property (ITaperedTapElementData)

Syntax

Visual Basic for Applications (VBA)

Public Property CustomSizing As Long

SOLIDWORKS Type Library

EndConditionOverride Property (ITaperedTapElementData)

Syntax

Visual Basic for Applications (VBA)

Public Property EndCondition0verride As Boolean

SOLIDWORKS Type Library

ThreadClass Property (ITaperedTapElementData)

Syntax

Visual Basic for Applications (VBA)

Public Property ThreadClass As Long

SOLIDWORKS Type Library

ThreadClassOverride Property (ITaperedTapElementData)

Syntax

Visual Basic for Applications (VBA)

Public Property ThreadClass0verride As Boolean

SOLIDWORKS Type Library

UseStandardDepth Property (ITaperedTapElementData)

Syntax

Visual Basic for Applications (VBA)

Public Property UseStandardDepth As Boolean

ITextAndCustomProperty (Type)

SOLIDWORKS Type Library
ITextAndCustomProperty Object

Object Model

ITextAndCustomProperty

SOLIDWORKS Type Library
ITextAndCustomProperty Object Members

Public Properties

 CustomPropertyName
 Description
 IsCustomProperty
 Name
 Value

SOLIDWORKS Type Library
CustomPropertyName Property (ITextAndCustomProperty)

Syntax

```
Visual Basic for Applications (VBA)

Public Property CustomPropertyName As String
```

SOLIDWORKS Type Library
Description Property (ITextAndCustomProperty)

Syntax

```
Visual Basic for Applications (VBA)

Public Property Description As String
```

SOLIDWORKS Type Library
IsCustomProperty Property (ITextAndCustomProperty)

Syntax

```
Visual Basic for Applications (VBA)

Public Property IsCustomProperty As Boolean
```

SOLIDWORKS Type Library
Name Property (ITextAndCustomProperty)

Syntax

```
Visual Basic for Applications (VBA)

Public Property Name As String
```

SOLIDWORKS Type Library
Value Property (ITextAndCustomProperty)

Syntax

```
Visual Basic for Applications (VBA)

Public Property Value As String
```

IThreadFeatureData (Type)

SOLIDWORKS Type Library

IThreadFeatureData Object

 Object Model

IThreadFeatureData

Edge

SOLIDWORKS Type Library

IThreadFeatureData Object Members

 Public Methods

 AccessSelections
 GetEndConditionReference
 InitializeThreadData
 ReleaseSelectionAccess
 SetEndConditionReference

 Public Properties

 BlindDepth
 Diameter
 DiameterOverride
 Edge
 EndCondition
 EndConditionOffset
 EndConditionOffsetDistance
 EndConditionOffsetReverse
 MaintainThreadLength
 MirrorProfile
 MirrorType
 MultipleStart
 NumberOfStarts
 Offset
 OffsetDistance
 Pitch
 PitchOverride
 ProfileLocation
 ReverseDirection
 ReverseOffset
 Revolutions
 RightHanded
 RotationAngle
 Size
StartEntity



[ThreadMethod](#)

[ThreadStartAngle](#)

[TrimEndFace](#)

[TrimStartFace](#)

[Type](#)

SOLIDWORKS Type Library

AccessSelections Method (IThreadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AccessSelections( _  
    ByVal TopDoc As ModelDoc, _  
    ByVal Component As Component _  
    ) As Boolean
```

SOLIDWORKS Type Library

BlindDepth Property (IThreadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property BlindDepth As Double
```

SOLIDWORKS Type Library

Diameter Property (IThreadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Diameter As Double
```

SOLIDWORKS Type Library

DiameterOverride Property (IThreadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property DiameterOverride As Boolean
```

SOLIDWORKS Type Library

Edge Property (IThreadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Edge As Edge
```

SOLIDWORKS Type Library

EndCondition Property (IThreadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property EndCondition As Long
```

SOLIDWORKS Type Library

EndConditionOffset Property (IThreadFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property EndConditionOffset As Boolean

SOLIDWORKS Type Library

EndConditionOffsetDistance Property (IThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property EndConditionOffsetDistance As Double

SOLIDWORKS Type Library

EndConditionOffsetReverse Property (IThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property EndConditionOffsetReverse As Boolean

SOLIDWORKS Type Library

GetEndConditionReference Method (IThreadFeatureData)



Visual Basic for Applications (VBA)

Public Function GetEndConditionReference() As Object

SOLIDWORKS Type Library

InitializeThreadData Method (IThreadFeatureData)



Visual Basic for Applications (VBA)

Public Sub InitializeThreadData()

SOLIDWORKS Type Library

MaintainThreadLength Property (IThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property MaintainThreadLength As Boolean

SOLIDWORKS Type Library

MirrorProfile Property (IThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property MirrorProfile As Boolean

SOLIDWORKS Type Library

MirrorType Property (IThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property MirrorType As Long

SOLIDWORKS Type Library

MultipleStart Property (IThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property MultipleStart As Boolean

SOLIDWORKS Type Library

NumberOfStarts Property (IThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property NumberOfStarts As Long

SOLIDWORKS Type Library

Offset Property (IThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property Offset As Boolean

SOLIDWORKS Type Library

OffsetDistance Property (IThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property OffsetDistance As Double

SOLIDWORKS Type Library

Pitch Property (IThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property Pitch As Double

SOLIDWORKS Type Library

PitchOverride Property (IThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property PitchOverride As Boolean

SOLIDWORKS Type Library

ProfileLocation Property (IThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property ProfileLocation As Object

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (IThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Sub ReleaseSelectionAccess()

SOLIDWORKS Type Library

ReverseDirection Property (IThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property ReverseDirection As Boolean

SOLIDWORKS Type Library

ReverseOffset Property (IThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property ReverseOffset As Boolean

SOLIDWORKS Type Library

Revolutions Property (IThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property Revolutions As Double

SOLIDWORKS Type Library

RightHanded Property (IThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property RightHanded As Boolean

SOLIDWORKS Type Library

RotationAngle Property (IThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property RotationAngle As Double

SOLIDWORKS Type Library

SetEndConditionReference Method (IThreadFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub SetEndConditionReference( _  
    ByVal Value As Object _  
)
```

SOLIDWORKS Type Library

Size Property (IThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property Size As String

SOLIDWORKS Type Library

StartEntity Property (IThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property StartEntity As Object

SOLIDWORKS Type Library

ThreadMethod Property (IThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property ThreadMethod As Long

SOLIDWORKS Type Library

ThreadStartAngle Property (IThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property ThreadStartAngle As Double

SOLIDWORKS Type Library

TrimEndFace Property (IThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property TrimEndFace As Boolean

SOLIDWORKS Type Library

TrimStartFace Property (IThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property TrimStartFace As Boolean

SOLIDWORKS Type Library

Type Property (IThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property Type As String

ITwoMemberCornerTreatmentFeatureData (Type)

SOLIDWORKS Type Library

ITwoMemberCornerTreatmentFeatureData Object

 Object Model

ITwoMemberCornerTreatmentFeatureData

SOLIDWORKS Type Library

ITwoMemberCornerTreatmentFeatureData Object Members

 Public Methods

 [GetCornerGroupMembers](#)

 [SwapMembers](#)

 Public Properties

 [CornerTreatmentTrimType](#)

 [MiterTrimPlanePoint](#)

 [PlanarTrimOption](#)

 [WeldTrimGap](#)

SOLIDWORKS Type Library

CornerTreatmentTrimType Property (ITwoMemberCornerTreatmentFeatureData)

 Syntax

Visual Basic for Applications (VBA)

Public Property CornerTreatmentTrimType As Long

SOLIDWORKS Type Library

GetCornerGroupMembers Method (ITwoMemberCornerTreatmentFeatureData)

 Syntax

Visual Basic for Applications (VBA)

Public Function GetCornerGroupMembers() As Variant

SOLIDWORKS Type Library

MiterTrimPlanePoint Property (ITwoMemberCornerTreatmentFeatureData)

 Syntax

Visual Basic for Applications (VBA)

Public Property MiterTrimPlanePoint As Object

SOLIDWORKS Type Library

PlanarTrimOption Property (ITwoMemberCornerTreatmentFeatureData)

 Syntax

Visual Basic for Applications (VBA)

Public Property PlanarTrimOption As Long

SOLIDWORKS Type Library

SwapMembers Method (ITwoMemberCornerTreatmentFeatureData)

 Syntax

```
Public Sub SwapMembers()
```

WeldTrimGap Property (ITwoMemberCornerTreatmentFeatureData)



Syntax

```
Public Property WeldTrimGap As Double
```

IUniversalJointMateFeatureData (Type)

SOLIDWORKS Type Library

IUniversalJointMateFeatureData Object

Object Model

IUniversalJointMateFeatureData

SOLIDWORKS Type Library

IUniversalJointMateFeatureData Object Members

Public Properties

DefineJointPoint

EntitiesToMate

JointPoint

SOLIDWORKS Type Library

DefineJointPoint Property (IUniversalJointMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property DefineJointPoint As Boolean

SOLIDWORKS Type Library

EntitiesToMate Property (IUniversalJointMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property EntitiesToMate As Variant

SOLIDWORKS Type Library

JointPoint Property (IUniversalJointMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property JointPoint As Object

IUserNotificationDefinition (Type)

SOLIDWORKS Type Library
IUserNotificationDefinition Object

Object Model

IUserNotificationDefinition

SOLIDWORKS Type Library
IUserNotificationDefinition Object Members

Public Properties

-  [IncludeDoNotShowAgain](#)
-  [Message](#)
-  [Position](#)
-  [ResponseAText](#)
-  [ResponseAType](#)
-  [ResponseBText](#)
-  [ResponseBType](#)
-  [Severity](#)
-  [Title](#)
-  [UniqueName](#)

SOLIDWORKS Type Library
IncludeDoNotShowAgain Property (IUserNotificationDefinition)

Syntax

Visual Basic for Applications (VBA)

Public Property IncludeDoNotShowAgain As Boolean

SOLIDWORKS Type Library
Message Property (IUserNotificationDefinition)

Syntax

Visual Basic for Applications (VBA)

Public Property Message As String

SOLIDWORKS Type Library
Position Property (IUserNotificationDefinition)

Syntax

Visual Basic for Applications (VBA)

Public Property Position As Long

SOLIDWORKS Type Library
ResponseAText Property (IUserNotificationDefinition)

Syntax

Visual Basic for Applications (VBA)

Public Property ResponseAText As String

SOLIDWORKS Type Library

ResponseAType Property (IUserNotificationDefinition)



Visual Basic for Applications (VBA)

```
Public Property ResponseAType As Long
```

SOLIDWORKS Type Library

ResponseBText Property (IUserNotificationDefinition)



Visual Basic for Applications (VBA)

```
Public Property ResponseBText As String
```

SOLIDWORKS Type Library

ResponseBType Property (IUserNotificationDefinition)



Visual Basic for Applications (VBA)

```
Public Property ResponseBType As Long
```

SOLIDWORKS Type Library

Severity Property (IUserNotificationDefinition)



Visual Basic for Applications (VBA)

```
Public Property Severity As Long
```

SOLIDWORKS Type Library

Title Property (IUserNotificationDefinition)



Visual Basic for Applications (VBA)

```
Public Property Title As String
```

SOLIDWORKS Type Library

UniqueName Property (IUserNotificationDefinition)



Visual Basic for Applications (VBA)

```
Public Property UniqueName As String
```

IVersionCompatibilityItem (Type)

SOLIDWORKS Type Library

IVersionCompatibilityItem Object

Object Model

IVersionCompatibilityItem

SOLIDWORKS Type Library

IVersionCompatibilityItem Object Members

Public Properties

- Action
- ID
- IncompatibleObject
- Message
- Version

SOLIDWORKS Type Library

Action Property (IVersionCompatibilityItem)

Syntax

Visual Basic for Applications (VBA)

Public Property Action As String

SOLIDWORKS Type Library

ID Property (IVersionCompatibilityItem)

Syntax

Visual Basic for Applications (VBA)

Public Property ID As String

SOLIDWORKS Type Library

IncompatibleObject Property (IVersionCompatibilityItem)

Syntax

Visual Basic for Applications (VBA)

Public Property IncompatibleObject As Object

SOLIDWORKS Type Library

Message Property (IVersionCompatibilityItem)

Syntax

Visual Basic for Applications (VBA)

Public Property Message As String

SOLIDWORKS Type Library

Version Property (IVersionCompatibilityItem)

Syntax

Visual Basic for Applications (VBA)


Public Property Version As String

IView3D (Type)

SOLIDWORKS Type Library

IView3D Object

Object Model



SOLIDWORKS Type Library

IView3D Object Members

Public Methods

-  [Activate](#)
-  [Deactivate](#)
-  [Get3DViewAnnotationTextScale](#)

Public Properties

-  [AnnotationViews](#)
-  [AnnotationViews2](#)
-  [ConfigurationName](#)
-  [DisplayMode](#)
-  [DisplayState](#)
-  [ModelBreakViewName](#)
-  [Name](#)
-  [Rotation](#)
-  [Scale](#)
-  [Translation](#)

SOLIDWORKS Type Library

Activate Method (IView3D)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub Activate( _  
    ByVal SaveLastState As Boolean _  
)
```

SOLIDWORKS Type Library

AnnotationViews Property (IView3D)

Syntax

Visual Basic for Applications (VBA)

```
Public Property AnnotationViews As Variant
```

SOLIDWORKS Type Library

AnnotationViews2 Property (IView3D)

Syntax

Visual Basic for Applications (VBA)

Public Property AnnotationViews2 As Variant

SOLIDWORKS Type Library

ConfigurationName Property (IView3D)



Visual Basic for Applications (VBA)

Public Property ConfigurationName As String

SOLIDWORKS Type Library

Deactivate Method (IView3D)



Visual Basic for Applications (VBA)

Public Sub Deactivate()

SOLIDWORKS Type Library

DisplayMode Property (IView3D)



Visual Basic for Applications (VBA)

Public Property DisplayMode As Long

SOLIDWORKS Type Library

DisplayState Property (IView3D)



Visual Basic for Applications (VBA)

Public Property DisplayState As String

SOLIDWORKS Type Library

Get3DViewAnnotationTextScale Method (IView3D)



Visual Basic for Applications (VBA)

```
Public Sub Get3DViewAnnotationTextScale( _  
    ByRef Scale1 As Double, _  
    ByRef Scale2 As Double _  
)
```

SOLIDWORKS Type Library

ModelBreakViewName Property (IView3D)



Visual Basic for Applications (VBA)

Public Property ModelBreakViewName As String

SOLIDWORKS Type Library

Name Property (IView3D)



Visual Basic for Applications (VBA)

Public Property Name As String

SOLIDWORKS Type Library

Rotation Property (IView3D)



Visual Basic for Applications (VBA)

Public Property Rotation As [MathTransform](#)

SOLIDWORKS Type Library

Scale Property (IView3D)



Visual Basic for Applications (VBA)

Public Property Scale As Double

SOLIDWORKS Type Library

Translation Property (IView3D)



Visual Basic for Applications (VBA)

Public Property Translation As [MathVector](#)

IWidthMateFeatureData (Type)

SOLIDWORKS Type Library
IWidthMateFeatureData Object

Object Model

IWidthMateFeatureData

SOLIDWORKS Type Library
IWidthMateFeatureData Object Members

Public Properties

- ConstraintType
- DistanceFromEnd
- FlipDimension
- PercentDistanceFromEnd
- TabSelection
- WidthSelection

SOLIDWORKS Type Library
ConstraintType Property (IWidthMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property ConstraintType As Long

SOLIDWORKS Type Library
DistanceFromEnd Property (IWidthMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property DistanceFromEnd As Double

SOLIDWORKS Type Library
FlipDimension Property (IWidthMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property FlipDimension As Boolean

SOLIDWORKS Type Library
PercentDistanceFromEnd Property (IWidthMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property PercentDistanceFromEnd As Double

SOLIDWORKS Type Library
TabSelection Property (IWidthMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property TabSelection As Variant

SOLIDWORKS Type Library

WidthSelection Property (IWidthMateFeatureData)



Visual Basic for Applications (VBA)

Public Property WidthSelection As Variant

JogFeatureData (Type)

SOLIDWORKS Type Library
JogFeatureData Object

Object Model

JogFeatureData

GetCustomBendAllowance (CustomBendAllowance)

SOLIDWORKS Type Library
JogFeatureData Object Members

Public Methods

	AccessSelections
	GetCustomBendAllowance
	GetOffsetReferenceType
	IAccessSelections
	IGetFixedPoint
	ISetFixedPoint
	ReleaseSelectionAccess
	SetCustomBendAllowance

Public Properties

	BendRadius
	DimensionPositionType
	FixedFace
	FixedPoint
	FixProjectedLength
	JogAngle
	JogPositionType
	OffsetDistance
	OffsetReference
	OffsetType
	ReverseDirection
	ReverseOffset
	UseDefaultBendAllowance
	UseDefaultBendRadius

SOLIDWORKS Type Library
AccessSelections Method (JogFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AccessSelections( _  
    ByVal TopDoc As Object, _  
    ByVal Component As Object _  
) As Boolean
```

SOLIDWORKS Type Library

BendRadius Property (JogFeatureData)



Visual Basic for Applications (VBA)

```
Public Property BendRadius As Double
```

SOLIDWORKS Type Library

DimensionPositionType Property (JogFeatureData)



Visual Basic for Applications (VBA)

```
Public Property DimensionPositionType As Long
```

SOLIDWORKS Type Library

FixedFace Property (JogFeatureData)



Visual Basic for Applications (VBA)

```
Public Property FixedFace As Object
```

SOLIDWORKS Type Library

FixedPoint Property (JogFeatureData)



Visual Basic for Applications (VBA)

```
Public Property FixedPoint As Variant
```

SOLIDWORKS Type Library

FixProjectedLength Property (JogFeatureData)



Visual Basic for Applications (VBA)

```
Public Property FixProjectedLength As Boolean
```

SOLIDWORKS Type Library

GetCustomBendAllowance Method (JogFeatureData)



Visual Basic for Applications (VBA)

```
Public Function GetCustomBendAllowance() As CustomBendAllowance
```

SOLIDWORKS Type Library

GetOffsetReferenceType Method (JogFeatureData)



Visual Basic for Applications (VBA)

```
Public Function GetOffsetReferenceType() As Long
```

SOLIDWORKS Type Library

IAccessSelections Method (JogFeatureData)



Visual Basic for Applications (VBA)

```
Public Function IAccessSelections( _  
    ByVal TopDoc As ModelDoc2, _
```

```
ByVal Component As Component2 _  
) As Boolean
```

SOLIDWORKS Type Library

IGetFixedPoint Method (JogFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetFixedPoint() As Double
```

SOLIDWORKS Type Library

ISetFixedPoint Method (JogFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ISetFixedPoint( _  
    ByRef Point As Double _  
)
```

SOLIDWORKS Type Library

JogAngle Property (JogFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property JogAngle As Double
```

SOLIDWORKS Type Library

JogPositionType Property (JogFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property JogPositionType As Long
```

SOLIDWORKS Type Library

OffsetDistance Property (JogFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property OffsetDistance As Double
```

SOLIDWORKS Type Library

OffsetReference Property (JogFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property OffsetReference As Object
```

SOLIDWORKS Type Library

OffsetType Property (JogFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property OffsetType As Long
```

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (JogFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ReleaseSelectionAccess()
```

SOLIDWORKS Type Library

ReverseDirection Property (JogFeatureData)



Visual Basic for Applications (VBA)

```
Public Property ReverseDirection As Boolean
```

SOLIDWORKS Type Library

ReverseOffset Property (JogFeatureData)



Visual Basic for Applications (VBA)

```
Public Property ReverseOffset As Boolean
```

SOLIDWORKS Type Library

SetCustomBendAllowance Method (JogFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub SetCustomBendAllowance( _  
    ByVal PBendData As CustomBendAllowance _  
)
```

SOLIDWORKS Type Library

UseDefaultBendAllowance Property (JogFeatureData)



Visual Basic for Applications (VBA)

```
Public Property UseDefaultBendAllowance As Boolean
```

SOLIDWORKS Type Library

UseDefaultBendRadius Property (JogFeatureData)



Visual Basic for Applications (VBA)

```
Public Property UseDefaultBendRadius As Boolean
```

JoinFeatureData (Type)

SOLIDWORKS Type Library
JoinFeatureData Object

Object Model

JoinFeatureData

IGetJoinedParts (Component2)

SOLIDWORKS Type Library
JoinFeatureData Object Members

Public Methods

- AccessSelections
- GetJoinedPartsCount
- IGetJoinedParts
- ISetJoinedParts
- ReleaseSelectionAccess

Public Properties

- ForceSurfaceContact
- HideParts
- JoinedParts

SOLIDWORKS Type Library
AccessSelections Method (JoinFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Function AccessSelections( _
    ByVal TopDoc As ModelDoc2, _
    ByVal Component As Component2 _
) As Boolean
```

SOLIDWORKS Type Library
ForceSurfaceContact Property (JoinFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property ForceSurfaceContact As Boolean
```

SOLIDWORKS Type Library
GetJoinedPartsCount Method (JoinFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Function GetJoinedPartsCount() As Long
```

SOLIDWORKS Type Library
HideParts Property (JoinFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property HideParts As Boolean

SOLIDWORKS Type Library

IGetJoinedParts Method (JoinFeatureData)



Visual Basic for Applications (VBA)

```
Public Function IGetJoinedParts( _  
    ByVal Count As Long _  
) As Component2
```

SOLIDWORKS Type Library

ISetJoinedParts Method (JoinFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub ISetJoinedParts( _  
    ByVal Count As Long, _  
    ByVal Parts As Component2 _  
)
```

SOLIDWORKS Type Library

JoinedParts Property (JoinFeatureData)



Visual Basic for Applications (VBA)

Public Property JoinedParts As Variant

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (JoinFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub ReleaseSelectionAccess()
```

Layer (Type)

SOLIDWORKS Type Library

Layer Object

Object Model

Layer

SOLIDWORKS Type Library

Layer Object Members

Public Methods

 [GetID](#)

 [GetItems](#)

Public Properties

 [Color](#)

 [Description](#)

 [Name](#)

 [Printable](#)

 [Style](#)

 [Visible](#)

 [Width](#)

SOLIDWORKS Type Library

Color Property (Layer)

Syntax

Visual Basic for Applications (VBA)

Public Property Color As Long

SOLIDWORKS Type Library

Description Property (Layer)

Syntax

Visual Basic for Applications (VBA)

Public Property Description As String

SOLIDWORKS Type Library

GetID Method (Layer)

Syntax

Visual Basic for Applications (VBA)

Public Function GetID() As Long

SOLIDWORKS Type Library

GetItems Method (Layer)

Syntax

Visual Basic for Applications (VBA)

Public Function GetItems(_
 ByVal *ItemType* As Long _

) As Variant

SOLIDWORKS Type Library

Name Property (Layer)

 Syntax

Visual Basic for Applications (VBA)

Public Property Name As String

SOLIDWORKS Type Library

Printable Property (Layer)

 Syntax

Visual Basic for Applications (VBA)

Public Property Printable As Boolean

SOLIDWORKS Type Library

Style Property (Layer)

 Syntax

Visual Basic for Applications (VBA)

Public Property Style As Integer

SOLIDWORKS Type Library

Visible Property (Layer)

 Syntax

Visual Basic for Applications (VBA)

Public Property Visible As Boolean

SOLIDWORKS Type Library

Width Property (Layer)

 Syntax

Visual Basic for Applications (VBA)


Public Property Width As Integer

LayerMgr (Type)

SOLIDWORKS Type Library

LayerMgr Object

Object Model



SOLIDWORKS Type Library

LayerMgr Object Members

Public Methods

	AddLayer
	DeleteLayer
	GetCount
	GetCurrentLayer
	GetLayer
	GetLayerById
	GetLayerList
	IGetLayer
	IGetLayerById
	IGetLayerList
	SetCurrentLayer

SOLIDWORKS Type Library

AddLayer Method (LayerMgr)

Syntax

```
Visual Basic for Applications (VBA)

Public Function AddLayer( _
    ByVal NameIn As String, _
    ByVal DescIn As String, _
    ByVal ColorIn As Long, _
    ByVal StyleIn As Long, _
    ByVal WidthIn As Long _
) As Integer
```

SOLIDWORKS Type Library

DeleteLayer Method (LayerMgr)

Syntax

```
Visual Basic for Applications (VBA)

Public Function DeleteLayer( _
    ByVal Name As String _
) As Boolean
```

SOLIDWORKS Type Library

GetCount Method (LayerMgr)



Visual Basic for Applications (VBA)

```
Public Function GetCount() As Integer
```

SOLIDWORKS Type Library

GetCurrentLayer Method (LayerMgr)



Visual Basic for Applications (VBA)

```
Public Function GetCurrentLayer() As String
```

SOLIDWORKS Type Library

GetLayer Method (LayerMgr)



Visual Basic for Applications (VBA)

```
Public Function GetLayer( _  
    ByVal NameIn As String _  
) As Object
```

SOLIDWORKS Type Library

GetLayerById Method (LayerMgr)



Visual Basic for Applications (VBA)

```
Public Function GetLayerById( _  
    ByVal LayerId As Integer _  
) As Object
```

SOLIDWORKS Type Library

GetLayerList Method (LayerMgr)



Visual Basic for Applications (VBA)

```
Public Function GetLayerList() As Variant
```

SOLIDWORKS Type Library

IGetLayer Method (LayerMgr)



Visual Basic for Applications (VBA)

```
Public Function IGetLayer( _  
    ByVal NameIn As String _  
) As Layer
```

SOLIDWORKS Type Library

IGetLayerById Method (LayerMgr)



Visual Basic for Applications (VBA)

```
Public Function IGetLayerById( _  
    ByVal LayerId As Integer _  
) As Layer
```

SOLIDWORKS Type Library

IGetLayerList Method (LayerMgr)



```
Public Function IGetLayerList() As String
```



Syntax

```
Public Function SetCurrentLayer( _  
    ByVal NameIn As String _  
) As Integer
```