

SOLIDWORKS API (VB6 COM) — Reference (51/102): Loop2-MassProperty


SOLIDWORKS API Documentation (converted from CHM)

Loop2 (Type)

SOLIDWORKS Type Library

Loop2 Object

Object Model



SOLIDWORKS Type Library

Loop2 Object Members

Public Methods

	EnumCoEdges
	EnumEdges
	GetCoEdgeCount
	GetCoEdges
	GetEdgeCount
	GetEdges
	GetFace
	GetFirstCoEdge
	GetNext
	GetTrackingIDs
	GetTrackingIDsCount
	GetVertexCount
	GetVertices
	IGetCoEdges
	IGetEdges
	IGetFace
	IGetFirstCoEdge
	IGetNext
	IGetTrackingIDs

 IGetVertices
 IRevolvePlanarLoop
 IsOuter
 IsSingular
 ISweepPlanarLoop
 RemoveTrackingID
 RevolvePlanarLoop
 Select
 SetTrackingID
 SweepPlanarLoop

SOLIDWORKS Type Library

EnumCoEdges Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function EnumCoEdges() As EnumCoEdges
```

SOLIDWORKS Type Library

EnumEdges Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function EnumEdges() As EnumEdges
```

SOLIDWORKS Type Library

GetCoEdgeCount Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCoEdgeCount() As Long
```

SOLIDWORKS Type Library

GetCoEdges Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCoEdges() As Variant
```

SOLIDWORKS Type Library

GetEdgeCount Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetEdgeCount() As Long
```

SOLIDWORKS Type Library

GetEdges Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetEdges() As Variant
```

SOLIDWORKS Type Library

GetFace Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFace() As Object
```

SOLIDWORKS Type Library

GetFirstCoEdge Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFirstCoEdge() As Object
```

SOLIDWORKS Type Library

GetNext Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNext() As Object
```

SOLIDWORKS Type Library

GetTrackingIDs Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTrackingIDs( _  
    ByVal TrackingCookie As Long, _  
    ByRef TrackingIDs As Variant _  
    ) As Long
```

SOLIDWORKS Type Library

GetTrackingIDsCount Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTrackingIDsCount( _  
    ByVal TrackingCookie As Long _  
    ) As Long
```

SOLIDWORKS Type Library

GetVertexCount Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetVertexCount() As Long
```

SOLIDWORKS Type Library

GetVertices Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetVertices() As Variant
```

SOLIDWORKS Type Library

IGetCoEdges Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetCoEdges( _  
    ByVal NumCoEdges As Long _  
) As CoEdge
```

SOLIDWORKS Type Library

IGetEdges Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetEdges() As Edge
```

SOLIDWORKS Type Library

IGetFace Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetFace() As Face2
```

SOLIDWORKS Type Library

IGetFirstCoEdge Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetFirstCoEdge() As CoEdge
```

SOLIDWORKS Type Library

IGetNext Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetNext() As Loop2
```

SOLIDWORKS Type Library

IGetTrackingIDs Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetTrackingIDs( _  
    ByVal TrackingCookie As Long, _  
    ByVal Count As Long, _  
    ByRef TrackingIDs As Long _  
) As Long
```

SOLIDWORKS Type Library

IGetVertices Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub IGetVertices( _  
    ByVal NumVertices As Long, _  
    ByRef Vertices As Vertex _  
)
```

SOLIDWORKS Type Library

IRevolvePlanarLoop Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IRevolvePlanarLoop( _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double, _  
    ByVal Axisx As Double, _  
    ByVal Axisy As Double, _  
    ByVal Axisz As Double, _  
    ByVal RevAngle As Double, _  
    ByRef StopFacesOut As Face2 _  
) As Body2
```

SOLIDWORKS Type Library

IsOuter Method (Loop2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IsOuter() As Boolean
```

SOLIDWORKS Type Library

IsSingular Method (Loop2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IsSingular() As Boolean
```

SOLIDWORKS Type Library

ISweepPlanarLoop Method (Loop2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function ISweepPlanarLoop( _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double, _  
    ByVal DraftAngle As Double, _  
    ByVal StopFacesOut As Face2 _  
) As Body2
```

SOLIDWORKS Type Library

RemoveTrackingID Method (Loop2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function RemoveTrackingID( _  
    ByVal TrackingCookie As Long _  
) As Long
```

SOLIDWORKS Type Library

RevolvePlanarLoop Method (Loop2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function RevolvePlanarLoop( _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double, _  
    ByVal Axisx As Double, _  
    ByVal Axisy As Double, _  
    ByVal Axisz As Double, _  
    ByVal RevAngle As Double _  
) As Variant
```

SOLIDWORKS Type Library

Select Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function Select( _  
    ByVal Edge As Object, _  
    ByVal Append As Boolean, _  
    ByVal SelectionData As Object _  
) As Boolean
```

SOLIDWORKS Type Library

SetTrackingID Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetTrackingID( _  
    ByVal TrackingCookie As Long, _  
    ByVal TrackingID As Long _  
) As Long
```

SOLIDWORKS Type Library

SweepPlanarLoop Method (Loop2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SweepPlanarLoop( _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double, _  
    ByVal DraftAngle As Double _  
) As Variant
```

MacroFeatureData (Type)

SOLIDWORKS Type Library

MacroFeatureData Object

Object Model

MacroFeatureData

CurrentConfiguration (Configuration)

EditBody (Body2)

FeatureTransform (MathTransform)

GetEditTargetTransform (MathTransform)

PatternTransform (MathTransform)

SOLIDWORKS Type Library

MacroFeatureData Object Members

Public Methods

 AccessSelections
 EmbedMacroFile
 GetBaseName
 GetDisplayDimensionCount
 GetDisplayDimensions
 GetDoubleByName
 GetEdgeIdType
 GetEdgeUserId
 GetEditBodiesCount
 GetEditTargetTransform
 GetEntitiesNeedUserId
 GetEntitiesNeedUserIdCount
 GetFaceIdType
 GetFaceUserId
 GetIconFileCount
 GetIntegerByName
 GetModuleCount
 GetModuleNames
 GetParameterCount
 GetParameters
 GetParentsCount
 GetProcedureCount
 GetProcedureNames
 GetProgid
 GetPropertyManagerHandleModuleCount

	<u>GetPropertyManagerHandleModuleNames</u>
	<u>GetPropertyManagerHandleProcedureCount</u>
	<u>GetPropertyManagerHandleProcedureNames</u>
	<u>GetSelectionCount</u>
	<u>GetSelections</u>
	<u>GetSelections2</u>
	<u>GetSelections3</u>
	<u>GetStringByName</u>
	<u>IAccessSelections</u>
	<u>IAddDisplayDimensions</u>
	<u>IGetDisplayDimensions</u>
	<u>IGetEditBodies</u>
	<u>IGetEntitiesNeedUserId</u>
	<u>IGetIconFiles</u>
	<u>IGetModuleNames</u>
	<u>IGetParameters</u>
	<u>IGetParents</u>
	<u>IGetProcedureNames</u>
	<u>IGetPropertyManagerHandleModuleNames</u>
	<u>IGetPropertyManagerHandleProcedureNames</u>
	<u>IGetSelections</u>
	<u>IGetSelections2</u>
	<u>IGetSelections3</u>
	<u>IsCOMFeature</u>
	<u>ISetEditBodies</u>
	<u>ISetIconFiles</u>
	<u>ISetParameters</u>
	<u>ISetParents</u>
	<u>ISetSelections</u>
	<u>ISetSelections2</u>
	<u>ReleaseSelectionAccess</u>
	<u>SetDoubleByName</u>
	<u>SetEdgeUserId</u>
	<u>SetFaceUserId</u>
	<u>SetIntegerByName</u>
	<u>SetParameters</u>
	<u>SetPropId</u>
	<u>SetSelections</u>
	<u>SetSelections2</u>
	<u>SetStringByName</u>

Public Properties

	<u>CurrentConfiguration</u>
---	---

 EditBodies
 EditBody
 EnableMultiBodyConsume
 FeatureTransform
 IconFiles
 MacroFileEmbedded
 MacroFileName
 ModuleName
 Parents
 PatternTransform
 ProcedureName
 PropertyManagerHandleMacroFileName
 PropertyManagerHandleModuleName
 PropertyManagerHandleProcedureName
 Provider
 SecurityHandleMacroFileName
 SecurityHandleModuleName
 SecurityHandleProcedureName

SOLIDWORKS Type Library

AccessSelections Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AccessSelections( _
    ByVal TopDoc As Object, _
    ByVal Component As Object _
) As Boolean
```

SOLIDWORKS Type Library

CurrentConfiguration Property (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property CurrentConfiguration As Configuration
```

SOLIDWORKS Type Library

EditBodies Property (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property EditBodies As Variant
```

SOLIDWORKS Type Library

EditBody Property (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property EditBody As Body2
```

SOLIDWORKS Type Library

EmbedMacroFile Method (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Function EmbedMacroFile() As Boolean
```

SOLIDWORKS Type Library

EnableMultiBodyConsume Property (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Property EnableMultiBodyConsume As Boolean
```

SOLIDWORKS Type Library

FeatureTransform Property (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Property FeatureTransform As MathTransform
```

SOLIDWORKS Type Library

GetBaseName Method (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Function GetBaseName() As String
```

SOLIDWORKS Type Library

GetDisplayDimensionCount Method (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Function GetDisplayDimensionCount() As Long
```

SOLIDWORKS Type Library

GetDisplayDimensions Method (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Function GetDisplayDimensions() As Variant
```

SOLIDWORKS Type Library

GetDoubleByName Method (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub GetDoubleByName( _  
    ByVal ParamName As String, _  
    ByRef ParamValue As Double _  
)
```

SOLIDWORKS Type Library

GetEdgeldType Method (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Function GetEdgeIdType( _  
    ByVal Edge As Edge _  
    ) As Long
```

SOLIDWORKS Type Library

GetEdgeUserId Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetEdgeUserId( _  
    ByVal Edge As Edge, _  
    ByRef Id1 As Long, _  
    ByRef Id2 As Long _  
    ) As Boolean
```

SOLIDWORKS Type Library

GetEditBodiesCount Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetEditBodiesCount() As Long
```

SOLIDWORKS Type Library

GetEditTargetTransform Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetEditTargetTransform() As MathTransform
```

SOLIDWORKS Type Library

GetEntitiesNeedUserId Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub GetEntitiesNeedUserId( _  
    ByVal Body As Object, _  
    ByRef Faces As Variant, _  
    ByRef Edges As Variant _  
    )
```

SOLIDWORKS Type Library

GetEntitiesNeedUserIdCount Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub GetEntitiesNeedUserIdCount( _  
    ByVal Body As Body2, _  
    ByRef FaceCount As Long, _  
    ByRef EdgeCount As Long _  
    )
```

SOLIDWORKS Type Library

GetFacIdType Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFaceIdType( _  
    ByVal Face As Face2 _  
    ) As Long
```

SOLIDWORKS Type Library

GetFaceUserId Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFaceUserId( _  
    ByVal Face As Face2, _  
    ByRef Id1 As Long, _  
    ByRef Id2 As Long _  
    ) As Boolean
```

SOLIDWORKS Type Library

GetIconFileCount Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetIconFileCount() As Long
```

SOLIDWORKS Type Library

GetIntegerByName Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub GetIntegerByName( _  
    ByVal ParamName As String, _  
    ByRef ParamValue As Long _  
    )
```

SOLIDWORKS Type Library

GetModuleCount Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetModuleCount() As Long
```

SOLIDWORKS Type Library

GetModuleNames Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetModuleNames() As Variant
```

SOLIDWORKS Type Library

GetParameterCount Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetParameterCount() As Long
```

SOLIDWORKS Type Library

GetParameters Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub GetParameters( _  
    ByRef ParamNames As Variant, _  
    ByRef ParamTypes As Variant, _  
    ByRef ParamValues As Variant _  
)
```

SOLIDWORKS Type Library

GetParentsCount Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetParentsCount() As Long
```

SOLIDWORKS Type Library

GetProcedureCount Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetProcedureCount( _  
    ByVal ModuleName As String _  
) As Long
```

SOLIDWORKS Type Library

GetProcedureNames Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetProcedureNames( _  
    ByVal ModuleName As String _  
) As Variant
```

SOLIDWORKS Type Library

GetProgId Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetProgId() As String
```

SOLIDWORKS Type Library

GetPropertyManagerHandleModuleCount Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPropertyManagerHandleModuleCount() As Long
```

SOLIDWORKS Type Library

GetPropertyManagerHandleModuleNames Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPropertyManagerHandleModuleNames() As Variant
```

SOLIDWORKS Type Library

GetPropertyManagerHandleProcedureCount Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPropertyManagerHandleProcedureCount( _  
    ByVal ModuleName As String _  
    ) As Long
```

SOLIDWORKS Type Library

GetPropertyManagerHandleProcedureNames Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPropertyManagerHandleProcedureNames( _  
    ByVal ModuleName As String _  
    ) As Variant
```

SOLIDWORKS Type Library

GetSelectionCount Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSelectionCount() As Long
```

SOLIDWORKS Type Library

GetSelections Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub GetSelections( _  
    ByRef Objects As Variant, _  
    ByRef ObjectTypes As Variant, _  
    ByRef SelMarks As Variant _  
    )
```

SOLIDWORKS Type Library

GetSelections2 Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub GetSelections2( _  
    ByRef Objects As Variant, _  
    ByRef ObjectTypes As Variant, _  
    ByRef SelMarks As Variant, _  
    ByRef DrViews As Variant _  
    )
```

SOLIDWORKS Type Library

GetSelections3 Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub GetSelections3( _  
    ByRef Objects As Variant, _  
    ByRef ObjectTypes As Variant, _  
    ByRef SelMarks As Variant, _  
    ByRef DrViews As Variant, _  
    ByRef ComponentXForms As Variant _  
    )
```

SOLIDWORKS Type Library

GetStringByName Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub GetStringByName( _  
    ByVal ParamName As String, _  
    ByRef ParamValue As String _  
)
```

SOLIDWORKS Type Library

IAccessSelections Method (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Function IAccessSelections( _  
    ByVal TopDoc As ModelDoc2, _  
    ByVal Component As Component2 _  
) As Boolean
```

SOLIDWORKS Type Library

IAddDisplayDimensions Method (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub IAddDisplayDimensions( _  
    ByVal DimCount As Long, _  
    ByRef DimTypes As Long, _  
    ByRef DimValues As Double _  
)
```

SOLIDWORKS Type Library

IconFiles Property (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Property IconFiles As Variant
```

SOLIDWORKS Type Library

IGetDisplayDimensions Method (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub IGetDisplayDimensions( _  
    ByVal DimCount As Long, _  
    ByRef Dims As DisplayDimension _  
)
```

SOLIDWORKS Type Library

IGetEditBodies Method (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub IGetEditBodies( _  
    ByVal BodiesCount As Long, _  
    ByRef PBodies As Body2 _  
)
```

SOLIDWORKS Type Library

IGetEntitiesNeedUserId Method (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub IGetEntitiesNeedUserId( _  
    ByVal Body As Body2, _  
    ByVal FaceCount As Long, _  
    ByRef Faces As Face2, _  
    ByVal EdgeCount As Long, _  
    ByRef Edges As Edge _  
)
```

SOLIDWORKS Type Library

IGetIconFiles Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub IGetIconFiles( _  
    ByVal IconCount As Long, _  
    ByRef IconFiles As String _  
)
```

SOLIDWORKS Type Library

IGetModuleNames Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub IGetModuleNames( _  
    ByVal ModuleCount As Long, _  
    ByRef ModuleNames As String _  
)
```

SOLIDWORKS Type Library

IGetParameters Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub IGetParameters( _  
    ByVal ParamCount As Long, _  
    ByRef ParamNames As String, _  
    ByRef ParamTypes As Long, _  
    ByRef ParamValues As String _  
)
```

SOLIDWORKS Type Library

IGetParents Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub IGetParents( _  
    ByVal ParentCount As Long, _  
    ByRef PFeatures As Feature _  
)
```

SOLIDWORKS Type Library

IGetProcedureNames Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub IGetProcedureNames( _  
    ByVal ModuleName As String, _  
    ByVal ProcedureCount As Long, _  
    ByRef ProcedureNames As String _  
)
```

IGetPropertyManagerHandleModuleNames Method (MacroFeatureData) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub IGetPropertyManagerHandleModuleNames( _
    ByVal ModuleCount As Long, _
    ByRef ModuleNames As String _
)
```

IGetPropertyManagerHandleProcedureNames Method (MacroFeatureData) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub IGetPropertyManagerHandleProcedureNames( _
    ByVal ModuleName As String, _
    ByVal ProcedureCount As Long, _
    ByRef ProcedureNames As String _
)
```

IGetSelections Method (MacroFeatureData) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub IGetSelections( _
    ByVal SelCount As Long, _
    ByRef Objects As Object, _
    ByRef ObjectTypes As Long, _
    ByRef SelMarks As Long _
)
```

IGetSelections2 Method (MacroFeatureData) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub IGetSelections2( _
    ByVal SelCount As Long, _
    ByRef Objects As Object, _
    ByRef ObjectTypes As Long, _
    ByRef SelMarks As Long, _
    ByRef DrViews As View _
)
```

IGetSelections3 Method (MacroFeatureData) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub IGetSelections3( _
    ByVal SelCount As Long, _
    ByRef Objects As Object, _
    ByRef ObjectTypes As Long, _
    ByRef SelMarks As Long, _
    ByRef DrViews As View, _
    ByRef ComponentXForms As MathTransform _
)
```

IsCOMFeature Method (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Function IsCOMFeature() As Boolean
```

SOLIDWORKS Type Library

ISetEditBodies Method (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub ISetEditBodies( _  
    ByVal BodiesCount As Long, _  
    ByVal PBodies As Body2 _  
)
```

SOLIDWORKS Type Library

ISetIconFiles Method (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub ISetIconFiles( _  
    ByVal IconCount As Long, _  
    ByRef IconFiles As String _  
)
```

SOLIDWORKS Type Library

ISetParameters Method (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub ISetParameters( _  
    ByVal ParamCount As Long, _  
    ByRef ParamNames As String, _  
    ByRef ParamTypes As Long, _  
    ByRef ParamValues As String _  
)
```

SOLIDWORKS Type Library

ISetParents Method (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub ISetParents( _  
    ByVal ParentCount As Long, _  
    ByVal PFeatures As Feature _  
)
```

SOLIDWORKS Type Library

ISetSelections Method (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub ISetSelections( _  
    ByVal SelCount As Long, _  
    ByRef Objects As Object, _  
    ByRef SelMarks As Long _  
)
```

SOLIDWORKS Type Library

ISetSelections2 Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ISetSelections2( _  
    ByVal SelCount As Long, _  
    ByRef Objects As Object, _  
    ByRef SelMarks As Long, _  
    ByVal DrViews As View _  
)
```

SOLIDWORKS Type Library

MacroFileEmbedded Property (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property MacroFileEmbedded As Boolean
```

SOLIDWORKS Type Library

MacroFileName Property (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property MacroFileName As String
```

SOLIDWORKS Type Library

ModuleName Property (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property ModuleName As String
```

SOLIDWORKS Type Library

Parents Property (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Parents As Variant
```

SOLIDWORKS Type Library

PatternTransform Property (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property PatternTransform As MathTransform
```

SOLIDWORKS Type Library

ProcedureName Property (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property ProcedureName As String
```

SOLIDWORKS Type Library

PropertyManagerHandleMacroFileName Property (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property PropertyManagerHandleMacroFileName As String
```

SOLIDWORKS Type Library

PropertyManagerHandleModuleName Property (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Property PropertyManagerHandleModuleName As String
```

SOLIDWORKS Type Library

PropertyManagerHandleProcedureName Property (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Property PropertyManagerHandleProcedureName As String
```

SOLIDWORKS Type Library

Provider Property (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Property Provider As String
```

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub ReleaseSelectionAccess()
```

SOLIDWORKS Type Library

SecurityHandleMacroFileName Property (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Property SecurityHandleMacroFileName As String
```

SOLIDWORKS Type Library

SecurityHandleModuleName Property (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Property SecurityHandleModuleName As String
```

SOLIDWORKS Type Library

SecurityHandleProcedureName Property (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Property SecurityHandleProcedureName As String
```

SOLIDWORKS Type Library

SetDoubleByName Method (MacroFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub SetDoubleByName( _  
    ByVal ParamName As String, _  
    ByVal ParamValue As Double _  
)
```

SOLIDWORKS Type Library

SetEdgeUserId Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetEdgeUserId( _  
    ByVal Edge As Edge, _  
    ByVal Id1 As Long, _  
    ByVal Id2 As Long _  
) As Boolean
```

SOLIDWORKS Type Library

SetFaceUserId Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetFaceUserId( _  
    ByVal Face As Face2, _  
    ByVal Id1 As Long, _  
    ByVal Id2 As Long _  
) As Boolean
```

SOLIDWORKS Type Library

SetIntegerByName Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetIntegerByName( _  
    ByVal ParamName As String, _  
    ByVal ParamValue As Long _  
)
```

SOLIDWORKS Type Library

SetParameters Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetParameters( _  
    ByVal ParamNames As Variant, _  
    ByVal ParamTypes As Variant, _  
    ByVal ParamValues As Variant _  
)
```

SOLIDWORKS Type Library

SetProgId Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetProgId( _  
    ByVal ProgId As String _  
)
```

SOLIDWORKS Type Library

SetSelections Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetSelections( _  
    ByVal Objects As Variant, _  
    ByVal SelMarks As Variant _  
)
```

SOLIDWORKS Type Library

SetSelections2 Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetSelections2( _  
    ByVal Objects As Variant, _  
    ByVal SelMarks As Variant, _  
    ByVal DrViews As Variant _  
)
```

SOLIDWORKS Type Library

SetStringByName Method (MacroFeatureData)

Syntax

Visual Basic for Applications (VBA)


```
Public Sub SetStringByName( _  
    ByVal ParamName As String, _  
    ByVal ParamValue As String _  
)
```

MagneticLine (Type)

SOLIDWORKS Type Library

MagneticLine Object

Object Model



SOLIDWORKS Type Library

MagneticLine Object Members



Public Methods

- [AddNote](#)
- [GetNotes](#)
- [GetNotesCount](#)
- [IGetNotes](#)
- [RemoveNote](#)

Public Properties

- [Angle](#)
- [EndPoint](#)
- [EqualSpacing](#)
- [Length](#)
- [StartPoint](#)

SOLIDWORKS Type Library

AddNote Method (MagneticLine)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddNote( _  
    ByVal Note As Note, _  
    ByVal Position As Double _  
) As Boolean
```

SOLIDWORKS Type Library

Angle Property (MagneticLine)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Angle As Double
```

SOLIDWORKS Type Library

EndPoint Property (MagneticLine)

Syntax

Visual Basic for Applications (VBA)

Public Property EndPoint As [MathPoint](#)

SOLIDWORKS Type Library

EqualSpacing Property (MagneticLine)



Visual Basic for Applications (VBA)

Public Property EqualSpacing As Boolean

SOLIDWORKS Type Library

GetNotes Method (MagneticLine)



Visual Basic for Applications (VBA)

Public Function GetNotes() As Variant

SOLIDWORKS Type Library

GetNotesCount Method (MagneticLine)



Visual Basic for Applications (VBA)

Public Function GetNotesCount() As Long

SOLIDWORKS Type Library

IGetNotes Method (MagneticLine)



Visual Basic for Applications (VBA)

```
Public Function IGetNotes( _  
    ByVal Count As Long _  
) As Note
```

SOLIDWORKS Type Library

Length Property (MagneticLine)



Visual Basic for Applications (VBA)

Public Property Length As Double

SOLIDWORKS Type Library

RemoveNote Method (MagneticLine)



Visual Basic for Applications (VBA)

```
Public Function RemoveNote( _  
    ByVal Note As Note, _  
    ByVal Location As MathPoint _  
) As Boolean
```

SOLIDWORKS Type Library

StartPoint Property (MagneticLine)



Visual Basic for Applications (VBA)

Public Property StartPoint As [MathPoint](#)

Manipulator (Type)

SOLIDWORKS Type Library

Manipulator Object

Object Model

Manipulator

SOLIDWORKS Type Library

Manipulator Object Members

Public Methods

GetSpecificManipulator

Remove

Select

Show

Public Properties

Name

Options

Selectable

Visible

SOLIDWORKS Type Library

GetSpecificManipulator Method (Manipulator)

Syntax

Visual Basic for Applications (VBA)

Public Function GetSpecificManipulator() As Object

SOLIDWORKS Type Library

Name Property (Manipulator)

Syntax

Visual Basic for Applications (VBA)

Public Property Name As String

SOLIDWORKS Type Library

Options Property (Manipulator)

Syntax

Visual Basic for Applications (VBA)

Public Property Options As Long

SOLIDWORKS Type Library

Remove Method (Manipulator)

Syntax

Visual Basic for Applications (VBA)

Public Sub Remove()

SOLIDWORKS Type Library

Select Method (Manipulator)

Syntax

Visual Basic for Applications (VBA)

```
Public Function Select( _  
    ByVal Append As Boolean, _  
    ByVal Data As SelectData _  
) As Boolean
```

SOLIDWORKS Type Library

Selectable Property (Manipulator)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Selectable As Boolean
```

SOLIDWORKS Type Library

Show Method (Manipulator)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub Show( _  
    ByVal PModelDoc As Object _  
)
```

SOLIDWORKS Type Library

Visible Property (Manipulator)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Visible As Boolean
```

MassProperty (Type)

SOLIDWORKS Type Library
MassProperty Object

Object Model

MassProperty

SOLIDWORKS Type Library
MassProperty Object Members

Public Methods

	AddBodies
	GetMomentOfInertia
	IAddBodies
	IGetCenterOfMass
	IGetMomentOfInertia
	IGetPrincipleAxesOfInertia
	IGetPrincipleMomentsOfInertia
	ISetAssignedMassProp
	ISetOverrideCenterOfMassValue
	ISetOverrideMassValue
	ISetOverrideMomentsOfInertiaValue
	ISetOverridePrincipleAxesOrientation
	ISetOverridePrincipleMomentsOfInertia
	SetAssignedMassProp
	SetCoordinateSystem
	SetOverrideCenterOfMassValue
	SetOverrideMassValue
	SetOverrideMomentsOfInertiaValue
	SetOverridePrincipleAxesOrientation
	SetOverridePrincipleMomentsOfInertia

Public Properties

	CenterOfMass
	Density
	Mass
	OverrideCenterOfMass
	OverrideMass
	OverrideMomentsOfInertia
	PrincipleAxesOfInertia
	PrincipleMomentsOfInertia
	SurfaceArea
	UserAssigned



[UseSystemUnits](#)



[Volume](#)

SOLIDWORKS Type Library

AddBodies Method (MassProperty)



Syntax

Visual Basic for Applications (VBA)

```
Public Function AddBodies( _  
    ByVal BodyListIn As Variant _  
    ) As Boolean
```

SOLIDWORKS Type Library

CenterOfMass Property (MassProperty)



Syntax

Visual Basic for Applications (VBA)

```
Public Property CenterOfMass As Variant
```

SOLIDWORKS Type Library

Density Property (MassProperty)



Syntax

Visual Basic for Applications (VBA)

```
Public Property Density As Double
```

SOLIDWORKS Type Library

GetMomentOfInertia Method (MassProperty)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetMomentOfInertia( _  
    ByVal WhereTaken As Long _  
    ) As Variant
```

SOLIDWORKS Type Library

IAddBodies Method (MassProperty)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IAddBodies( _  
    ByVal NumBodies As Long, _  
    ByVal BodyListIn As Body2 _  
    ) As Boolean
```

SOLIDWORKS Type Library

IGetCenterOfMass Method (MassProperty)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetCenterOfMass() As Double
```

SOLIDWORKS Type Library

IGetMomentOfInertia Method (MassProperty)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetMomentOfInertia( _  
    ByVal WhereTaken As Long _  
) As Double
```

SOLIDWORKS Type Library

IGetPrincipleAxesOfInertia Method (MassProperty)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetPrincipleAxesOfInertia( _  
    ByVal Axis As Long _  
) As Double
```

SOLIDWORKS Type Library

IGetPrincipleMomentsOfInertia Method (MassProperty)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetPrincipleMomentsOfInertia() As Double
```

SOLIDWORKS Type Library

ISetAssignedMassProp Method (MassProperty)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ISetAssignedMassProp( _  
    ByVal Mass As Double, _  
    ByVal Center_x As Double, _  
    ByVal Center_y As Double, _  
    ByVal Center_z As Double, _  
    ByVal Config_opt As Long, _  
    ByVal ConfigNum As Long, _  
    ByRef Config_names As String _  
) As Boolean
```

SOLIDWORKS Type Library

ISetOverrideCenterOfMassValue Method (MassProperty)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ISetOverrideCenterOfMassValue( _  
    ByRef Value As Double, _  
    ByVal CoordinateSystemName As String, _  
    ByVal Config_option As Long, _  
    ByVal Config_numbers As Long, _  
    ByRef Config_names As String _  
) As Boolean
```

SOLIDWORKS Type Library

ISetOverrideMassValue Method (MassProperty)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ISetOverrideMassValue( _  
    ByVal Value As Double, _  
    ByVal Config_option As Long, _  
    ByVal Config_numbers As Long, _  
    ByRef Config_names As String _  
) As Boolean
```

ISetOverrideMomentsOfInertiaValue Method (MassProperty) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function ISetOverrideMomentsOfInertiaValue( _  
    ByVal ReferenceFrame As Long, _  
    ByVal CoordinateSystemName As String, _  
    ByRef Value As Double, _  
    ByVal Config_option As Long, _  
    ByVal Config_numbers As Long, _  
    ByRef Config_names As String _  
) As Boolean
```

ISetOverridePrincipleAxesOrientation Method (MassProperty) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function ISetOverridePrincipleAxesOrientation( _  
    ByVal Axis As Long, _  
    ByRef Value As Double, _  
    ByVal Config_option As Long, _  
    ByVal Config_numbers As Long, _  
    ByRef Config_names As String _  
) As Boolean
```

ISetOverridePrincipleMomentsOfInertia Method (MassProperty) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function ISetOverridePrincipleMomentsOfInertia( _  
    ByRef Value As Double, _  
    ByVal Config_option As Long, _  
    ByVal Config_numbers As Long, _  
    ByRef Config_names As String _  
) As Boolean
```

Mass Property (MassProperty) **Syntax**

Visual Basic for Applications (VBA)

```
Public Property Mass As Double
```

OverrideCenterOfMass Property (MassProperty) **Syntax**

Visual Basic for Applications (VBA)

```
Public Property OverrideCenterOfMass As Boolean
```

OverrideMass Property (MassProperty) **Syntax**

Visual Basic for Applications (VBA)

```
Public Property OverrideMass As Boolean
```

OverrideMomentsOfInertia Property (MassProperty)

Syntax

Visual Basic for Applications (VBA)

```
Public Property OverrideMomentsOfInertia As Boolean
```

PrincipleAxesOfInertia Property (MassProperty)

Syntax

Visual Basic for Applications (VBA)

```
Public Property PrincipleAxesOfInertia( _  
    ByVal Axis As Long _  
) As Variant
```

PrincipleMomentsOfInertia Property (MassProperty)

Syntax

Visual Basic for Applications (VBA)

```
Public Property PrincipleMomentsOfInertia As Variant
```

SetAssignedMassProp Method (MassProperty)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetAssignedMassProp( _  
    ByVal Mass As Double, _  
    ByVal Center_x As Double, _  
    ByVal Center_y As Double, _  
    ByVal Center_z As Double, _  
    ByVal Config_opt As Long, _  
    ByVal Config_names As Variant _  
) As Boolean
```

SetCoordinateSystem Method (MassProperty)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetCoordinateSystem( _  
    ByVal Coords As MathTransform _  
) As Boolean
```

SetOverrideCenterOfMassValue Method (MassProperty)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetOverrideCenterOfMassValue( _  
    ByVal Value As Variant, _  
    ByVal CoordinateSystemName As String, _  
    ByVal Config_option As Long, _  
    ByVal Config_names As Variant _  
) As Boolean
```

SetOverrideMassValue Method (MassProperty)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetOverrideMassValue( _  
    ByVal Value As Double, _  
    ByVal Config_option As Long, _  
    ByVal Config_names As Variant _  
    ) As Boolean
```

SOLIDWORKS Type Library

SetOverrideMomentsOfInertiaValue Method (MassProperty)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetOverrideMomentsOfInertiaValue( _  
    ByVal ReferenceFrame As Long, _  
    ByVal CoordinateSystemName As String, _  
    ByVal Value As Variant, _  
    ByVal Config_option As Long, _  
    ByVal Config_names As Variant _  
    ) As Boolean
```

SOLIDWORKS Type Library

SetOverridePrincipleAxesOrientation Method (MassProperty)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetOverridePrincipleAxesOrientation( _  
    ByVal Axis As Long, _  
    ByVal Value As Variant, _  
    ByVal Config_option As Long, _  
    ByVal Config_names As Variant _  
    ) As Boolean
```

SOLIDWORKS Type Library

SetOverridePrincipleMomentsOfInertia Method (MassProperty)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetOverridePrincipleMomentsOfInertia( _  
    ByVal Value As Variant, _  
    ByVal Config_option As Long, _  
    ByVal Config_names As Variant _  
    ) As Boolean
```

SOLIDWORKS Type Library

SurfaceArea Property (MassProperty)

Syntax

Visual Basic for Applications (VBA)

```
Public Property SurfaceArea As Double
```

SOLIDWORKS Type Library

UserAssigned Property (MassProperty)

Syntax

Visual Basic for Applications (VBA)

```
Public Property UserAssigned As Boolean
```

SOLIDWORKS Type Library

UseSystemUnits Property (MassProperty)



Visual Basic for Applications (VBA)

Public Property UseSystemUnits As Boolean

SOLIDWORKS Type Library

Volume Property (MassProperty)



Visual Basic for Applications (VBA)

Public Property Volume As Double