

SOLIDWORKS API (VB6 COM) — Reference (58/102): ModelDoc (part 4 of 4)

SOLIDWORKS API Documentation (converted from CHM)

ModelDoc (part 4 of 4) (Type)

SOLIDWORKS Type Library

Save2 Method (ModelDoc)



Visual Basic for Applications (VBA)

```
Public Function Save2( _  
    ByVal Silent As Boolean _  
    ) As Long
```

SOLIDWORKS Type Library

SaveAs Method (ModelDoc)



Visual Basic for Applications (VBA)

```
Public Function SaveAs( _  
    ByVal NewName As String _  
    ) As Boolean
```

SOLIDWORKS Type Library

SaveAs2 Method (ModelDoc)



Visual Basic for Applications (VBA)

```
Public Function SaveAs2( _  
    ByVal NewName As String, _  
    ByVal SaveAsVersion As Long, _  
    ByVal SaveAsCopy As Boolean, _  
    ByVal Silent As Boolean _  
    ) As Long
```

SOLIDWORKS Type Library

SaveAs3 Method (ModelDoc)



Visual Basic for Applications (VBA)

```
Public Function SaveAs3( _  
    ByVal NewName As String, _  
    ByVal SaveAsVersion As Long, _  
    ByVal Options As Long _  
    ) As Long
```

SOLIDWORKS Type Library

SaveAsSilent Method (ModelDoc)



Visual Basic for Applications (VBA)

```
Public Function SaveAsSilent( _  
    ByVal NewName As String, _  
    ByVal SaveAsCopy As Boolean _  
    ) As Long
```

SOLIDWORKS Type Library

SaveBMP Method (ModelDoc)



Visual Basic for Applications (VBA)

```
Public Function SaveBMP( _  
    ByVal FileNameIn As String, _  
    ByVal WidthIn As Long, _  
    ByVal HeightIn As Long _  
) As Boolean
```

SOLIDWORKS Type Library

SaveSilent Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SaveSilent() As Long
```

SOLIDWORKS Type Library

Scale Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub Scale()
```

SOLIDWORKS Type Library

SceneBkgImageFileName Property (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Property SceneBkgImageFileName As String
```

SOLIDWORKS Type Library

SceneName Property (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Property SceneName As String
```

SOLIDWORKS Type Library

SceneUserName Property (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Property SceneUserName As String
```

SOLIDWORKS Type Library

ScreenRotate Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ScreenRotate()
```

SOLIDWORKS Type Library

Select Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub Select( _  
    ByVal SelID As String, _  
    ByVal SelParams As String, _  
    ByVal X As Double, _
```

```
    ByVal Y As Double, _  
    ByVal Z As Double _  
)
```

SOLIDWORKS Type Library

SelectAt Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SelectAt( _  
    ByVal Flags As Long, _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
)
```

SOLIDWORKS Type Library

SelectByID Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SelectByID( _  
    ByVal SelID As String, _  
    ByVal SelParams As String, _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
) As Boolean
```

SOLIDWORKS Type Library

SelectByMark Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SelectByMark( _  
    ByVal SelID As String, _  
    ByVal SelParams As String, _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double, _  
    ByVal Mark As Long _  
) As Boolean
```

SOLIDWORKS Type Library

SelectByName Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SelectByName( _  
    ByVal Flags As Long, _  
    ByVal IdStr As String _  
)
```

SOLIDWORKS Type Library

SelectByRay Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SelectByRay( _  
    ByVal DoubleInfoIn As Variant, _  
    ByVal TypeWanted As Long _  
) As Boolean
```

SOLIDWORKS Type Library

SelectedEdgeProperties Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SelectedEdgeProperties( _  
    ByVal EdgeName As String _  
) As Boolean
```

SOLIDWORKS Type Library

SelectedFaceProperties Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SelectedFaceProperties( _  
    ByVal RgbColor As Long, _  
    ByVal Ambient As Double, _  
    ByVal Diffuse As Double, _  
    ByVal Specular As Double, _  
    ByVal Shininess As Double, _  
    ByVal Transparency As Double, _  
    ByVal Emission As Double, _  
    ByVal UsePartProps As Boolean, _  
    ByVal FaceName As String _  
) As Boolean
```

SOLIDWORKS Type Library

SelectedFeatureProperties Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SelectedFeatureProperties( _  
    ByVal RgbColor As Long, _  
    ByVal Ambient As Double, _  
    ByVal Diffuse As Double, _  
    ByVal Specular As Double, _  
    ByVal Shininess As Double, _  
    ByVal Transparency As Double, _  
    ByVal Emission As Double, _  
    ByVal UsePartProps As Boolean, _  
    ByVal Suppressed As Boolean, _  
    ByVal FeatureName As String _  
) As Boolean
```

SOLIDWORKS Type Library

SelectionManager Property (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Property SelectionManager As Object
```

SOLIDWORKS Type Library

SelectLoop Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SelectLoop()
```

SOLIDWORKS Type Library

SelectMidpoint Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SelectMidpoint()
```

SOLIDWORKS Type Library

SelectSketchArc Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SelectSketchArc( _  
    ByVal X0 As Double, _  
    ByVal Y0 As Double, _  
    ByVal Inc0 As Long, _  
    ByVal X1 As Double, _  
    ByVal Y1 As Double, _  
    ByVal Inc1 As Long, _  
    ByVal XC As Double, _  
    ByVal YC As Double, _  
    ByVal IncC As Long, _  
    ByVal RotDir As Long _  
)
```

SOLIDWORKS Type Library

SelectSketchItem Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SelectSketchItem( _  
    ByVal SelOpt As Long, _  
    ByVal Name As String, _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
) As Boolean
```

SOLIDWORKS Type Library

SelectSketchLine Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SelectSketchLine( _  
    ByVal X0 As Double, _  
    ByVal Y0 As Double, _  
    ByVal Inc0 As Long, _  
    ByVal X1 As Double, _  
    ByVal Y1 As Double, _  
    ByVal Inc1 As Long _  
)
```

SOLIDWORKS Type Library

SelectSketchPoint Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SelectSketchPoint( _  
    ByVal X As Double, _
```

```
    ByVal Y As Double, _  
    ByVal Incidence As Long _  
)
```

SOLIDWORKS Type Library

SelectSketchSpline Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SelectSketchSpline( _  
    ByVal Size As Long, _  
    ByVal X0 As Double, _  
    ByVal Y0 As Double, _  
    ByVal Inc0 As Long, _  
    ByVal X1 As Double, _  
    ByVal Y1 As Double, _  
    ByVal Inc1 As Long, _  
    ByVal XC As Double, _  
    ByVal YC As Double, _  
    ByVal IncC As Long _  
)
```

SOLIDWORKS Type Library

SelectTangency Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SelectTangency()
```

SOLIDWORKS Type Library

SetAddToDB Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetAddToDB( _  
    ByVal Setting As Boolean _  
)
```

SOLIDWORKS Type Library

SetAmbientLightProperties Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetAmbientLightProperties( _  
    ByVal Name As String, _  
    ByVal Ambient As Double, _  
    ByVal Diffuse As Double, _  
    ByVal Specular As Double, _  
    ByVal Colour As Long, _  
    ByVal Enabled As Boolean, _  
    ByVal Fixed As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

SetAngularUnits Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetAngularUnits( _  
    ByVal UType As Integer, _  
    ByVal FractBase As Integer, _  
    ByVal FractDenom As Integer, _
```

```
    ByVal SigDigits As Integer _  
)
```

SOLIDWORKS Type Library

SetArcCentersDisplayed Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetArcCentersDisplayed( _  
    ByVal Setting As Boolean _  
)
```

SOLIDWORKS Type Library

SetBendState Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetBendState( _  
    ByVal BendState As Long _  
) As Long
```

SOLIDWORKS Type Library

SetBlockingState Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetBlockingState( _  
    ByVal StateIn As Long _  
)
```

SOLIDWORKS Type Library

SetConsiderLeadersAsLines Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetConsiderLeadersAsLines( _  
    ByVal LeadersAsLines As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

SetDirectionLightProperties Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetDirectionLightProperties( _  
    ByVal Name As String, _  
    ByVal Ambient As Double, _  
    ByVal Diffuse As Double, _  
    ByVal Specular As Double, _  
    ByVal Colour As Long, _  
    ByVal Enabled As Boolean, _  
    ByVal Fixed As Boolean, _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
) As Boolean
```

SOLIDWORKS Type Library

SetDisplayWhenAdded Method (ModelDoc)

Syntax

```
Public Sub SetDisplayWhenAdded( _
    ByVal Setting As Boolean _
)
```

SetFeatureManagerWidth Method (ModelDoc) **Syntax**

```
Public Function SetFeatureManagerWidth( _
    ByVal Width As Long _
) As Long
```

SetInferenceMode Method (ModelDoc) **Syntax**

```
Public Sub SetInferenceMode( _
    ByVal InferenceMode As Boolean _
)
```

SetLightSourceName Method (ModelDoc) **Syntax**

```
Public Function SetLightSourceName( _
    ByVal ID As Long, _
    ByVal NewName As String _
) As Boolean
```

SetLightSourcePropertyValuesVB Method (ModelDoc) **Syntax**

```
Public Function SetLightSourcePropertyValuesVB( _
    ByVal IdName As String, _
    ByVal LType As Integer, _
    ByVal Diff As Double, _
    ByVal RgbColor As Long, _
    ByVal Dist As Double, _
    ByVal DirX As Double, _
    ByVal DirY As Double, _
    ByVal DirZ As Double, _
    ByVal SpotDirX As Double, _
    ByVal SpotDirY As Double, _
    ByVal SpotDirZ As Double, _
    ByVal SpotAngle As Double, _
    ByVal Falloff0 As Double, _
    ByVal Falloff1 As Double, _
    ByVal Falloff2 As Double, _
    ByVal Ambient As Double, _
    ByVal Specular As Double, _
    ByVal SpotExponent As Double, _
    ByVal BDisable As Boolean _
) As Boolean
```

SetNextSelectionGroupId Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetNextSelectionGroupId( _  
    ByVal ID As Long _  
)
```

SOLIDWORKS Type Library

SetParamValue Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetParamValue( _  
    ByVal Val As Double _  
)
```

SOLIDWORKS Type Library

SetPickMode Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetPickMode()
```

SOLIDWORKS Type Library

SetPointLightProperties Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetPointLightProperties( _  
    ByVal Name As String, _  
    ByVal Ambient As Double, _  
    ByVal Diffuse As Double, _  
    ByVal Specular As Double, _  
    ByVal Colour As Long, _  
    ByVal Enabled As Boolean, _  
    ByVal Fixed As Boolean, _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
) As Boolean
```

SOLIDWORKS Type Library

SetPopupMenuMode Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetPopupMenuMode( _  
    ByVal ModeIn As Integer _  
)
```

SOLIDWORKS Type Library

SetReadOnlyState Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetReadOnlyState( _  
    ByVal SetReadOnly As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

SetSaveAsFileName Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetSaveAsFileName( _  
    ByVal FileName As String _  
)
```

SOLIDWORKS Type Library

SetSaveFlag Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetSaveFlag()
```

SOLIDWORKS Type Library

SetSceneBkgDIB Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetSceneBkgDIB( _  
    ByVal L_dib As Long _  
)
```

SOLIDWORKS Type Library

SetSpotlightProperties Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetSpotlightProperties( _  
    ByVal Name As String, _  
    ByVal Ambient As Double, _  
    ByVal Diffuse As Double, _  
    ByVal Specular As Double, _  
    ByVal Colour As Long, _  
    ByVal Enabled As Boolean, _  
    ByVal Fixed As Boolean, _  
    ByVal Posx As Double, _  
    ByVal Posy As Double, _  
    ByVal Posz As Double, _  
    ByVal Targetx As Double, _  
    ByVal Targety As Double, _  
    ByVal Targetz As Double, _  
    ByVal ConeAngle As Double _  
) As Boolean
```

SOLIDWORKS Type Library

SetTessellationQuality Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetTessellationQuality( _  
    ByVal QualityNum As Long _  
)
```

SOLIDWORKS Type Library

SetTitle2 Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetTitle2( _  
    ByVal NewTitle As String _  
    ) As Boolean
```

SOLIDWORKS Type Library

SetToolBarVisibility Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetToolBarVisibility( _  
    ByVal ToolBar As Long, _  
    ByVal Visibility As Boolean _  
    )
```

SOLIDWORKS Type Library

SetUnits Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetUnits( _  
    ByVal UType As Integer, _  
    ByVal FractBase As Integer, _  
    ByVal FractDenom As Integer, _  
    ByVal SigDigits As Integer, _  
    ByVal RoundToFraction As Boolean _  
    )
```

SOLIDWORKS Type Library

SetUserPreferenceDoubleValue Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetUserPreferenceDoubleValue( _  
    ByVal UserPreferenceValue As Long, _  
    ByVal Value As Double _  
    ) As Boolean
```

SOLIDWORKS Type Library

SetUserPreferenceIntegerValue Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetUserPreferenceIntegerValue( _  
    ByVal UserPreferenceValue As Long, _  
    ByVal Value As Long _  
    ) As Boolean
```

SOLIDWORKS Type Library

SetUserPreferenceStringValue Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetUserPreferenceStringValue( _  
    ByVal UserPreference As Long, _  
    ByVal Value As String _  
    ) As Boolean
```

SOLIDWORKS Type Library

SetUserPreferenceTextFormat Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetUserPreferenceTextFormat( _  
    ByVal UserPreferenceValue As Long, _  
    ByVal Value As Object _  
    ) As Boolean
```

SOLIDWORKS Type Library

SetUserPreferenceToggle Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetUserPreferenceToggle( _  
    ByVal UserPreferenceValue As Long, _  
    ByVal OnFlag As Boolean _  
    ) As Boolean
```

SOLIDWORKS Type Library

ShowComponent2 Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ShowComponent2()
```

SOLIDWORKS Type Library

ShowConfiguration Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ShowConfiguration( _  
    ByVal ConfigurationName As String _  
    )
```

SOLIDWORKS Type Library

ShowConfiguration2 Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ShowConfiguration2( _  
    ByVal ConfigurationName As String _  
    ) As Boolean
```

SOLIDWORKS Type Library

ShowCosmeticThread Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ShowCosmeticThread()
```

SOLIDWORKS Type Library

ShowFeatureDimensions Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ShowFeatureDimensions()
```

SOLIDWORKS Type Library

ShowFeatureErrorDialog Property (ModelDoc)



Visual Basic for Applications (VBA)

```
Public Property ShowFeatureErrorDialog As Boolean
```

SOLIDWORKS Type Library

ShowNamedView Method (ModelDoc)



Visual Basic for Applications (VBA)

```
Public Sub ShowNamedView( _  
    ByVal VName As String _  
)
```

SOLIDWORKS Type Library

ShowNamedView2 Method (ModelDoc)



Visual Basic for Applications (VBA)

```
Public Sub ShowNamedView2( _  
    ByVal VName As String, _  
    ByVal ViewId As Long _  
)
```

SOLIDWORKS Type Library

ShowSolidBody Method (ModelDoc)



Visual Basic for Applications (VBA)

```
Public Sub ShowSolidBody()
```

SOLIDWORKS Type Library

SimpleHole Method (ModelDoc)



Visual Basic for Applications (VBA)

```
Public Sub SimpleHole( _  
    ByVal Sd As Boolean, _  
    ByVal Flip As Boolean, _  
    ByVal Dir As Boolean, _  
    ByVal T1 As Long, _  
    ByVal T2 As Long, _  
    ByVal D1 As Double, _  
    ByVal D2 As Double, _  
    ByVal Dchk1 As Boolean, _  
    ByVal Dchk2 As Boolean, _  
    ByVal Ddir1 As Boolean, _  
    ByVal Ddir2 As Boolean, _  
    ByVal Dang1 As Double, _  
    ByVal Dang2 As Double, _  
    ByVal OffsetReverse1 As Boolean, _  
    ByVal OffsetReverse2 As Boolean _  
)
```

SOLIDWORKS Type Library

SimpleHole2 Method (ModelDoc)



Visual Basic for Applications (VBA)

```
Public Sub SimpleHole2( _  
    ByVal Dia As Double, _  
    ByVal Sd As Boolean, _
```

```
ByVal Flip As Boolean, _  
ByVal Dir As Boolean, _  
ByVal T1 As Long, _  
ByVal T2 As Long, _  
ByVal D1 As Double, _  
ByVal D2 As Double, _  
ByVal Dchk1 As Boolean, _  
ByVal Dchk2 As Boolean, _  
ByVal Ddir1 As Boolean, _  
ByVal Ddir2 As Boolean, _  
ByVal Dang1 As Double, _  
ByVal Dang2 As Double, _  
ByVal OffsetReverse1 As Boolean, _  
ByVal OffsetReverse2 As Boolean _  
)
```

SOLIDWORKS Type Library

SimplifySpline Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SimplifySpline( _  
    ByVal ToleranceIn As Double _  
)
```

SOLIDWORKS Type Library

Sketch3DIntersections Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub Sketch3DIntersections()
```

SOLIDWORKS Type Library

SketchAddConstraints Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchAddConstraints( _  
    ByVal IdStr As String _  
)
```

SOLIDWORKS Type Library

SketchAlign Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchAlign()
```

SOLIDWORKS Type Library

SketchArc Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchArc()
```

SOLIDWORKS Type Library

SketchCenterline Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchCenterline()
```

SOLIDWORKS Type Library

SketchChamfer Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchChamfer( _  
    ByVal AngleORdist As Double, _  
    ByVal Dist1 As Double, _  
    ByVal Options As Long _  
)
```

SOLIDWORKS Type Library

SketchCircle Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchCircle()
```

SOLIDWORKS Type Library

SketchConstrainCoincident Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchConstrainCoincident()
```

SOLIDWORKS Type Library

SketchConstrainConcentric Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchConstrainConcentric()
```

SOLIDWORKS Type Library

SketchConstrainParallel Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchConstrainParallel()
```

SOLIDWORKS Type Library

SketchConstrainPerp Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchConstrainPerp()
```

SOLIDWORKS Type Library

SketchConstrainTangent Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchConstrainTangent()
```

SOLIDWORKS Type Library

SketchConstraintsDel Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchConstraintsDel( _  
    ByVal ConstrInd As Long, _  
    ByVal IdStr As String _  
)
```

SOLIDWORKS Type Library

SketchConstraintsDelAll Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchConstraintsDelAll()
```

SOLIDWORKS Type Library

SketchConvertIsoCurves Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchConvertIsoCurves( _  
    ByVal PercentRatio As Double, _  
    ByVal VORuDir As Boolean, _  
    ByVal DoConstrain As Boolean, _  
    ByVal SkipHoles As Boolean _  
)
```

SOLIDWORKS Type Library

SketchFillet Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchFillet( _  
    ByVal Rad As Double _  
)
```

SOLIDWORKS Type Library

SketchFillet1 Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchFillet1( _  
    ByVal Rad As Double _  
)
```

SOLIDWORKS Type Library

SketchFillet2 Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SketchFillet2( _  
    ByVal Rad As Double, _  
    ByVal ConstrainedCorners As Integer _  
) As Boolean
```

SOLIDWORKS Type Library

SketchMirror Method (ModelDoc)

Syntax

```
Public Sub SketchMirror()
```

SketchModifyFlip Method (ModelDoc) **Syntax**

```
Public Sub SketchModifyFlip( _  
    ByVal AxisFlag As Integer _  
)
```

SketchModifyRotate Method (ModelDoc) **Syntax**

```
Public Sub SketchModifyRotate( _  
    ByVal CenterX As Double, _  
    ByVal CenterY As Double, _  
    ByVal Angle As Double _  
)
```

SketchModifyScale Method (ModelDoc) **Syntax**

```
Public Function SketchModifyScale( _  
    ByVal ScaleFactor As Double _  
) As Boolean
```

SketchModifyTranslate Method (ModelDoc) **Syntax**

```
Public Sub SketchModifyTranslate( _  
    ByVal StartX As Double, _  
    ByVal StartY As Double, _  
    ByVal EndX As Double, _  
    ByVal EndY As Double _  
)
```

SketchOffset Method (ModelDoc) **Syntax**

```
Public Sub SketchOffset( _  
    ByVal Offset As Double, _  
    ByVal ContourMode As Boolean _  
)
```

SketchOffset2 Method (ModelDoc) **Syntax**

```
Public Function SketchOffset2( _  
    ByVal Offset As Double, _  
    ByVal BothDirections As Boolean, _  
    ByVal Chain As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

SketchOffsetEdges Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchOffsetEdges( _  
    ByVal Val As Double _  
)
```

SOLIDWORKS Type Library

SketchOffsetEntities Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchOffsetEntities( _  
    ByVal Offset As Double, _  
    ByVal Flip As Boolean _  
)
```

SOLIDWORKS Type Library

SketchOffsetEntities2 Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SketchOffsetEntities2( _  
    ByVal Offset As Double, _  
    ByVal BothDirections As Boolean, _  
    ByVal Chain As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

SketchParabola Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchParabola( _  
    ByVal Val1 As Double, _  
    ByVal Val2 As Double, _  
    ByVal Z1 As Double, _  
    ByVal Val3 As Double, _  
    ByVal Val4 As Double, _  
    ByVal Z2 As Double, _  
    ByVal Val5 As Double, _  
    ByVal Val6 As Double, _  
    ByVal Z3 As Double, _  
    ByVal Val7 As Double, _  
    ByVal Val8 As Double, _  
    ByVal Z4 As Double _  
)
```

SOLIDWORKS Type Library

SketchPoint Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchPoint( _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
)
```

SOLIDWORKS Type Library

SketchPolygon Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SketchPolygon( _  
    ByVal XCenter As Double, _  
    ByVal YCenter As Double, _  
    ByVal XEdge As Double, _  
    ByVal YEdge As Double, _  
    ByVal NSides As Integer, _  
    ByVal BInscribed As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

SketchRectangle Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchRectangle( _  
    ByVal Val1 As Double, _  
    ByVal Val2 As Double, _  
    ByVal Z1 As Double, _  
    ByVal Val3 As Double, _  
    ByVal Val4 As Double, _  
    ByVal Z2 As Double, _  
    ByVal Val5 As Boolean _  
)
```

SOLIDWORKS Type Library

SketchRectangleAtAnyAngle Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchRectangleAtAnyAngle( _  
    ByVal Val1 As Double, _  
    ByVal Val2 As Double, _  
    ByVal Z1 As Double, _  
    ByVal Val3 As Double, _  
    ByVal Val4 As Double, _  
    ByVal Z2 As Double, _  
    ByVal Val3x As Double, _  
    ByVal Val3y As Double, _  
    ByVal Z3 As Double, _  
    ByVal Val5 As Boolean _  
)
```

SOLIDWORKS Type Library

SketchSpline Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchSpline( _  
    ByVal MorePts As Long, _  
    ByVal X As Double, _  
    ByVal Y As Double, _
```

```
ByVal Z As Double _  
)
```

SOLIDWORKS Type Library

SketchSplineByEqnParams Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SketchSplineByEqnParams( _  
    ByVal ParamsIn As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

SketchSplineByEqnParams2 Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SketchSplineByEqnParams2( _  
    ByVal ParamsIn As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

SketchTangentArc Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchTangentArc()
```

SOLIDWORKS Type Library

SketchTrim Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchTrim( _  
    ByVal Op As Long, _  
    ByVal SelEnd As Long, _  
    ByVal X As Double, _  
    ByVal Y As Double _  
)
```

SOLIDWORKS Type Library

SketchUndo Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchUndo()
```

SOLIDWORKS Type Library

SketchUseEdge Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchUseEdge()
```

SOLIDWORKS Type Library

SketchUseEdge2 Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SketchUseEdge2( _  
    ByVal Chain As Boolean _  
    ) As Boolean
```

SOLIDWORKS Type Library

SketchUseEdgeCtrline Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchUseEdgeCtrline()
```

SOLIDWORKS Type Library

SkToolsAutoConstr Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SkToolsAutoConstr()
```

SOLIDWORKS Type Library

SplitClosedSegment Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SplitClosedSegment( _  
    ByVal X0 As Double, _  
    ByVal Y0 As Double, _  
    ByVal Z0 As Double, _  
    ByVal X1 As Double, _  
    ByVal Y1 As Double, _  
    ByVal Z1 As Double _  
    )
```

SOLIDWORKS Type Library

SplitOpenSegment Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SplitOpenSegment( _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
    )
```

SOLIDWORKS Type Library

SummaryInfo Property (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Property SummaryInfo( _  
    ByVal FieldId As Long _  
    ) As String
```

SOLIDWORKS Type Library

Toolbars Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub Toolbars( _  
    ByVal M As Boolean, _
```

```
ByVal Vw As Boolean, _  
ByVal SkMain As Boolean, _  
ByVal Sk As Boolean, _  
ByVal Feat As Boolean, _  
ByVal Constr As Boolean, _  
ByVal Macro As Boolean _  
)
```

SOLIDWORKS Type Library

ToolsConfiguration Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ToolsConfiguration()
```

SOLIDWORKS Type Library

ToolsDistance Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ToolsDistance()
```

SOLIDWORKS Type Library

ToolsGrid Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ToolsGrid()
```

SOLIDWORKS Type Library

ToolsMacro Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ToolsMacro()
```

SOLIDWORKS Type Library

ToolsMassProps Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ToolsMassProps()
```

SOLIDWORKS Type Library

ToolsSketchScale Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ToolsSketchScale()
```

SOLIDWORKS Type Library

ToolsSketchTranslate Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ToolsSketchTranslate()
```

SOLIDWORKS Type Library

SOLIDWORKS Type Library

UnBlankRefGeom Method (ModelDoc)



Visual Basic for Applications (VBA)

```
Public Sub UnBlankRefGeom()
```

SOLIDWORKS Type Library

UnblankSketch Method (ModelDoc)



Visual Basic for Applications (VBA)

```
Public Sub UnblankSketch()
```

SOLIDWORKS Type Library

UnderiveSketch Method (ModelDoc)



Visual Basic for Applications (VBA)

```
Public Sub UnderiveSketch()
```

SOLIDWORKS Type Library

UnLock Method (ModelDoc)



Visual Basic for Applications (VBA)

```
Public Sub UnLock()
```

SOLIDWORKS Type Library

UnlockAllExternalReferences Method (ModelDoc)



Visual Basic for Applications (VBA)

```
Public Sub UnlockAllExternalReferences()
```

SOLIDWORKS Type Library

UnlockFramePoint Method (ModelDoc)



Visual Basic for Applications (VBA)

```
Public Sub UnlockFramePoint()
```

SOLIDWORKS Type Library

UserFavors Method (ModelDoc)



Visual Basic for Applications (VBA)

```
Public Sub UserFavors()
```

SOLIDWORKS Type Library

UserPreferences Method (ModelDoc)



Visual Basic for Applications (VBA)

```
Public Sub UserPreferences()
```

SOLIDWORKS Type Library

VersionHistory Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Function VersionHistory() As Variant
```

SOLIDWORKS Type Library

ViewConstraint Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewConstraint()
```

SOLIDWORKS Type Library

ViewDispCoordinateSystems Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDispCoordinateSystems()
```

SOLIDWORKS Type Library

ViewDisplayCurvature Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDisplayCurvature()
```

SOLIDWORKS Type Library

ViewDisplayFaceted Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDisplayFaceted()
```

SOLIDWORKS Type Library

ViewDisplayHiddengreyed Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDisplayHiddengreyed()
```

SOLIDWORKS Type Library

ViewDisplayHiddenremoved Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDisplayHiddenremoved()
```

SOLIDWORKS Type Library

ViewDisplayShaded Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDisplayShaded()
```

SOLIDWORKS Type Library

ViewDisplayWireframe Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDisplayWireframe()
```

SOLIDWORKS Type Library

ViewDispOrigins Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDispOrigins()
```

SOLIDWORKS Type Library

ViewDispRefaxes Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDispRefaxes()
```

SOLIDWORKS Type Library

ViewDispRefplanes Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDispRefplanes()
```

SOLIDWORKS Type Library

ViewDispRefPoints Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDispRefPoints()
```

SOLIDWORKS Type Library

ViewDispTempRefaxes Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDispTempRefaxes()
```

SOLIDWORKS Type Library

ViewOglShading Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewOglShading()
```

SOLIDWORKS Type Library

ViewOrientationUndo Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewOrientationUndo()
```

SOLIDWORKS Type Library

SOLIDWORKS Type Library

ViewRotate Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotate()
```

SOLIDWORKS Type Library

ViewRotateminusx Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotateminusx()
```

SOLIDWORKS Type Library

ViewRotateminusy Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotateminusy()
```

SOLIDWORKS Type Library

ViewRotateminusz Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotateminusz()
```

SOLIDWORKS Type Library

ViewRotateplusx Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotateplusx()
```

SOLIDWORKS Type Library

ViewRotateplusy Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotateplusy()
```

SOLIDWORKS Type Library

ViewRotateplusz Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotateplusz()
```

SOLIDWORKS Type Library

ViewRotXMinusNinety Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotXMinusNinety()
```

SOLIDWORKS Type Library

ViewRotXPlusNinety Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotXPlusNinety()
```

SOLIDWORKS Type Library

ViewRotYMinusNinety Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotYMinusNinety()
```

SOLIDWORKS Type Library

ViewRotYPlusNinety Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotYPlusNinety()
```

SOLIDWORKS Type Library

ViewRwShading Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRwShading()
```

SOLIDWORKS Type Library

ViewTranslate Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewTranslate()
```

SOLIDWORKS Type Library

ViewTranslateminusx Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewTranslateminusx()
```

SOLIDWORKS Type Library

ViewTranslateminusy Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewTranslateminusy()
```

SOLIDWORKS Type Library

ViewTranslateplusx Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewTranslateplusx()
```

SOLIDWORKS Type Library

ViewTranslateplusy Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewTranslateplusy()
```

SOLIDWORKS Type Library

ViewZoomin Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewZoomin()
```

SOLIDWORKS Type Library

ViewZoomout Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewZoomout()
```

SOLIDWORKS Type Library

ViewZoomto Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewZoomto()
```

SOLIDWORKS Type Library

ViewZoomTo2 Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewZoomTo2( _  
    ByVal X1 As Double, _  
    ByVal Y1 As Double, _  
    ByVal Z1 As Double, _  
    ByVal X2 As Double, _  
    ByVal Y2 As Double, _  
    ByVal Z2 As Double _  
)
```

SOLIDWORKS Type Library

ViewZoomtofit Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewZoomtofit()
```

SOLIDWORKS Type Library

ViewZoomtofit2 Method (ModelDoc)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewZoomtofit2()
```

SOLIDWORKS Type Library

ViewZoomToSelection Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewZoomToSelection()
```

SOLIDWORKS Type Library

Visible Property (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Property Visible As Boolean
```

SOLIDWORKS Type Library

WindowRedraw Method (ModelDoc)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub WindowRedraw()
```