

SOLIDWORKS API (VB6 COM) — Reference (60/102): ModelDoc2 (part 2 of 5)

SOLIDWORKS API Documentation (converted from CHM)

ModelDoc2 (part 2 of 5) (Type)

SOLIDWORKS Type Library

DimPreferences Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Sub DimPreferences()
```

SOLIDWORKS Type Library

DissolveLibraryFeature Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function DissolveLibraryFeature() As Boolean
```

SOLIDWORKS Type Library

DissolveSketchText Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Sub DissolveSketchText()
```

SOLIDWORKS Type Library

DragTo Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Sub DragTo( _  
    ByVal Flags As Long, _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
)
```

SOLIDWORKS Type Library

DrawLightIcons Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Sub DrawLightIcons()
```

SOLIDWORKS Type Library

EditBalloonProperties Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function EditBalloonProperties( _  
    ByVal Style As Long, _  
    ByVal Size As Long, _  
    ByVal UpperTextStyle As Long, _  
    ByVal UpperText As String, _  
    ByVal LowerTextStyle As Long, _  
    ByVal LowerText As String _  
) As Object
```

SOLIDWORKS Type Library

EditClearAll Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Sub EditClearAll()
```

SOLIDWORKS Type Library

EditConfiguration Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Sub EditConfiguration( _  
    ByVal Name As String, _  
    ByVal NewName As String, _  
    ByVal Comment As String, _  
    ByVal AlternateName As String, _  
    ByVal SuppressByDefault As Boolean, _  
    ByVal HideByDefault As Boolean, _  
    ByVal MinFeatureManager As Boolean, _  
    ByVal InheritProperties As Boolean, _  
    ByVal Flags As ULong _  
)
```

SOLIDWORKS Type Library

EditConfiguration2 Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function EditConfiguration2( _  
    ByVal Name As String, _  
    ByVal NewName As String, _  
    ByVal Comment As String, _  
    ByVal AlternateName As String, _  
    ByVal SuppressByDefault As Boolean, _  
    ByVal HideByDefault As Boolean, _  
    ByVal MinFeatureManager As Boolean, _  
    ByVal InheritProperties As Boolean, _  
    ByVal Flags As ULong _  
) As Boolean
```

SOLIDWORKS Type Library

EditConfiguration3 Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function EditConfiguration3( _  
    ByVal Name As String, _  
    ByVal NewName As String, _  
    ByVal Comment As String, _  
    ByVal AlternateName As String, _  
    ByVal Options As Long _  
) As Boolean
```

SOLIDWORKS Type Library

EditCopy Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Sub EditCopy()
```

SOLIDWORKS Type Library

EditCut Method (ModelDoc2)



```
Public Sub EditCut()
```

EditDatumTargetSymbol Method (ModelDoc2)

```
Public Function EditDatumTargetSymbol( _
    ByVal Datum1 As String, _
    ByVal Datum2 As String, _
    ByVal Datum3 As String, _
    ByVal AreaStyle As Integer, _
    ByVal AreaOutside As Boolean, _
    ByVal Value1 As Double, _
    ByVal Value2 As Double, _
    ByVal ValueStr1 As String, _
    ByVal ValueStr2 As String, _
    ByVal ArrowsSmart As Boolean, _
    ByVal ArrowStyle As Integer, _
    ByVal LeaderLineStyle As Integer, _
    ByVal LeaderBent As Boolean, _
    ByVal ShowArea As Boolean, _
    ByVal ShowSymbol As Boolean _
) As Boolean
```

EditDelete Method (ModelDoc2)

```
Public Sub EditDelete()
```

EditDimensionProperties Method (ModelDoc2)

```
Public Function EditDimensionProperties( _
    ByVal TolType As Long, _
    ByVal TolMax As Double, _
    ByVal TolMin As Double, _
    ByVal TolMaxFit As String, _
    ByVal TolMinFit As String, _
    ByVal UseDocPrec As Boolean, _
    ByVal Precision As Long, _
    ByVal ArrowsIn As Long, _
    ByVal UseDocArrows As Boolean, _
    ByVal Arrow1 As Long, _
    ByVal Arrow2 As Long _
) As Boolean
```

EditDimensionProperties2 Method (ModelDoc2)

```
Public Function EditDimensionProperties2( _
    ByVal TolType As Long, _
    ByVal TolMax As Double, _
    ByVal TolMin As Double, _
    ByVal TolMaxFit As String, _
    ByVal TolMinFit As String, _
```

```

    ByVal UseDocPrec As Boolean, _
    ByVal Precision As Long, _
    ByVal ArrowsIn As Long, _
    ByVal UseDocArrows As Boolean, _
    ByVal Arrow1 As Long, _
    ByVal Arrow2 As Long, _
    ByVal PrefixText As String, _
    ByVal SuffixText As String, _
    ByVal ShowValue As Boolean, _
    ByVal CalloutText1 As String, _
    ByVal CalloutText2 As String, _
    ByVal CenterText As Boolean _
) As Boolean

```

SOLIDWORKS Type Library

EditDimensionProperties3 Method (ModelDoc2)



Visual Basic for Applications (VBA)

```

Public Function EditDimensionProperties3( _
    ByVal TolType As Long, _
    ByVal TolMax As Double, _
    ByVal TolMin As Double, _
    ByVal TolMaxFit As String, _
    ByVal TolMinFit As String, _
    ByVal UseDocPrec As Boolean, _
    ByVal Precision As Long, _
    ByVal ArrowsIn As Long, _
    ByVal UseDocArrows As Boolean, _
    ByVal Arrow1 As Long, _
    ByVal Arrow2 As Long, _
    ByVal PrefixText As String, _
    ByVal SuffixText As String, _
    ByVal ShowValue As Boolean, _
    ByVal CalloutText1 As String, _
    ByVal CalloutText2 As String, _
    ByVal CenterText As Boolean, _
    ByVal ConfigOption As Long, _
    ByVal ConfigNames As Variant _
) As Boolean

```

SOLIDWORKS Type Library

EditOrdinate Method (ModelDoc2)



Visual Basic for Applications (VBA)

```

Public Sub EditOrdinate()

```

SOLIDWORKS Type Library

EditRebuild3 Method (ModelDoc2)



Visual Basic for Applications (VBA)

```

Public Function EditRebuild3() As Boolean

```

SOLIDWORKS Type Library

EditRedo Method (ModelDoc2)



Visual Basic for Applications (VBA)

```

Public Sub EditRedo( _
    ByVal NSteps As ULong _
)

```

SOLIDWORKS Type Library

EditRedo2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub EditRedo2( _  
    ByVal Steps As Long _  
)
```

SOLIDWORKS Type Library

EditRollback Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function EditRollback() As Boolean
```

SOLIDWORKS Type Library

EditRollback2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function EditRollback2() As Boolean
```

SOLIDWORKS Type Library

EditRoute Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub EditRoute()
```

SOLIDWORKS Type Library

EditSeedFeat Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub EditSeedFeat()
```

SOLIDWORKS Type Library

EditSketch Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub EditSketch()
```

SOLIDWORKS Type Library

EditSketchOrSingleSketchFeature Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub EditSketchOrSingleSketchFeature()
```

SOLIDWORKS Type Library

EditSuppress Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function EditSuppress() As Boolean
```

SOLIDWORKS Type Library

EditSuppress2 Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function EditSuppress2() As Boolean
```

SOLIDWORKS Type Library

EditUndo Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub EditUndo( _  
    ByVal NSteps As ULong _  
)
```

SOLIDWORKS Type Library

EditUndo2 Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub EditUndo2( _  
    ByVal Steps As Long _  
)
```

SOLIDWORKS Type Library

EditUnsuppress Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function EditUnsuppress() As Boolean
```

SOLIDWORKS Type Library

EditUnsuppress2 Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function EditUnsuppress2() As Boolean
```

SOLIDWORKS Type Library

EditUnsuppressDependent Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function EditUnsuppressDependent() As Boolean
```

SOLIDWORKS Type Library

EditUnsuppressDependent2 Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function EditUnsuppressDependent2() As Boolean
```

SOLIDWORKS Type Library

EntityProperties Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Sub EntityProperties()
```

SOLIDWORKS Type Library

EnumModelViews Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function EnumModelViews() As EnumModelViews
```

SOLIDWORKS Type Library

Extension Property (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Property Extension As ModelDocExtension
```

SOLIDWORKS Type Library

FeatEdit Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Sub FeatEdit()
```

SOLIDWORKS Type Library

FeatEditDef Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Sub FeatEditDef()
```

SOLIDWORKS Type Library

FeatureBoss Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Sub FeatureBoss( _  
    ByVal Sd As Boolean, _  
    ByVal Flip As Boolean, _  
    ByVal Dir As Boolean, _  
    ByVal T1 As Long, _  
    ByVal T2 As Long, _  
    ByVal D1 As Double, _  
    ByVal D2 As Double, _  
    ByVal Dchk1 As Boolean, _  
    ByVal Dchk2 As Boolean, _  
    ByVal Ddir1 As Boolean, _  
    ByVal Ddir2 As Boolean, _  
    ByVal Dang1 As Double, _  
    ByVal Dang2 As Double, _  
    ByVal OffsetReverse1 As Boolean, _  
    ByVal OffsetReverse2 As Boolean _  
)
```

SOLIDWORKS Type Library

FeatureBoss2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub FeatureBoss2( _  
    ByVal Sd As Boolean, _  
    ByVal Flip As Boolean, _  
    ByVal Dir As Boolean, _  
    ByVal T1 As Long, _  
    ByVal T2 As Long, _  
    ByVal D1 As Double, _  
    ByVal D2 As Double, _  
    ByVal Dchk1 As Boolean, _  
    ByVal Dchk2 As Boolean, _  
    ByVal Ddir1 As Boolean, _  
    ByVal Ddir2 As Boolean, _  
    ByVal Dang1 As Double, _  
    ByVal Dang2 As Double, _  
    ByVal OffsetReverse1 As Boolean, _  
    ByVal OffsetReverse2 As Boolean, _  
    ByVal TranslateSurface1 As Boolean, _  
    ByVal TranslateSurface2 As Boolean _  
)
```

SOLIDWORKS Type Library

FeatureBossThicken Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub FeatureBossThicken( _  
    ByVal Thickness As Double, _  
    ByVal Direction As Long, _  
    ByVal FaceIndex As Long _  
)
```

SOLIDWORKS Type Library

FeatureBossThicken2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub FeatureBossThicken2( _  
    ByVal Thickness As Double, _  
    ByVal Direction As Long, _  
    ByVal FaceIndex As Long, _  
    ByVal FillVolume As Boolean _  
)
```

SOLIDWORKS Type Library

FeatureBossThin Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub FeatureBossThin( _  
    ByVal Sd As Boolean, _  
    ByVal Flip As Boolean, _  
    ByVal Dir As Boolean, _  
    ByVal T1 As Long, _  
    ByVal T2 As Long, _  
    ByVal D1 As Double, _  
    ByVal D2 As Double, _  
    ByVal Dchk1 As Boolean, _  
    ByVal Dchk2 As Boolean, _  
    ByVal Ddir1 As Boolean, _  
    ByVal Ddir2 As Boolean, _  
    ByVal Dang1 As Double, _  
    ByVal Dang2 As Double, _
```

```

    ByVal OffsetReverse1 As Boolean, _
    ByVal OffsetReverse2 As Boolean, _
    ByVal Thk1 As Double, _
    ByVal Thk2 As Double, _
    ByVal EndThk As Double, _
    ByVal RevThinDir As Long, _
    ByVal CapEnds As Long, _
    ByVal AddBends As Boolean, _
    ByVal BendRad As Double _
)

```

SOLIDWORKS Type Library

FeatureBossThin2 Method (ModelDoc2)



Visual Basic for Applications (VBA)

```

Public Sub FeatureBossThin2( _
    ByVal Sd As Boolean, _
    ByVal Flip As Boolean, _
    ByVal Dir As Boolean, _
    ByVal T1 As Long, _
    ByVal T2 As Long, _
    ByVal D1 As Double, _
    ByVal D2 As Double, _
    ByVal Dchk1 As Boolean, _
    ByVal Dchk2 As Boolean, _
    ByVal Ddir1 As Boolean, _
    ByVal Ddir2 As Boolean, _
    ByVal Dang1 As Double, _
    ByVal Dang2 As Double, _
    ByVal OffsetReverse1 As Boolean, _
    ByVal OffsetReverse2 As Boolean, _
    ByVal TranslateSurface1 As Boolean, _
    ByVal TranslateSurface2 As Boolean, _
    ByVal Thk1 As Double, _
    ByVal Thk2 As Double, _
    ByVal EndThk As Double, _
    ByVal RevThinDir As Long, _
    ByVal CapEnds As Long, _
    ByVal AddBends As Boolean, _
    ByVal BendRad As Double _
)

```

SOLIDWORKS Type Library

FeatureByPositionReverse Method (ModelDoc2)



Visual Basic for Applications (VBA)

```

Public Function FeatureByPositionReverse( _
    ByVal Num As Long _
) As Object

```

SOLIDWORKS Type Library

FeatureChamfer Method (ModelDoc2)



Visual Basic for Applications (VBA)

```

Public Sub FeatureChamfer( _
    ByVal Width As Double, _
    ByVal Angle As Double, _
    ByVal Flip As Boolean _
)

```

SOLIDWORKS Type Library

FeatureChamferType Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub FeatureChamferType( _  
    ByVal ChamferType As Integer, _  
    ByVal Width As Double, _  
    ByVal Angle As Double, _  
    ByVal Flip As Boolean, _  
    ByVal OtherDist As Double, _  
    ByVal VertexChamDist1 As Double, _  
    ByVal VertexChamDist2 As Double, _  
    ByVal VertexChamDist3 As Double _  
)
```

SOLIDWORKS Type Library

FeatureCirPattern Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub FeatureCirPattern( _  
    ByVal Num As Long, _  
    ByVal Spacing As Double, _  
    ByVal FlipDir As Boolean, _  
    ByVal DName As String _  
)
```

SOLIDWORKS Type Library

FeatureCurvePattern Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub FeatureCurvePattern( _  
    ByVal Num1 As Long, _  
    ByVal Spacing1 As Double, _  
    ByVal Num2 As Long, _  
    ByVal Spacing2 As Double, _  
    ByVal FlipDir1 As Boolean, _  
    ByVal FlipDir2 As Boolean, _  
    ByVal EqualSpacing1 As Boolean, _  
    ByVal EqualSpacing2 As Boolean, _  
    ByVal UseCentroid As Boolean, _  
    ByVal AlignToSeed As Boolean, _  
    ByVal OffsetCurve As Boolean, _  
    ByVal PatternSeedOnly As Boolean _  
)
```

SOLIDWORKS Type Library

FeatureCut Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub FeatureCut( _  
    ByVal Sd As Boolean, _  
    ByVal Flip As Boolean, _  
    ByVal Dir As Boolean, _  
    ByVal T1 As Long, _  
    ByVal T2 As Long, _  
    ByVal D1 As Double, _  
    ByVal D2 As Double, _  
    ByVal Dchk1 As Boolean, _  
    ByVal Dchk2 As Boolean, _  
    ByVal Ddir1 As Boolean, _  
    ByVal Ddir2 As Boolean, _  
    ByVal Dang1 As Double, _  
    ByVal Dang2 As Double, _  
)
```

```
ByVal OffsetReverse1 As Boolean, _  
ByVal OffsetReverse2 As Boolean _  
)
```

SOLIDWORKS Type Library

FeatureCut2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub FeatureCut2( _  
    ByVal Sd As Boolean, _  
    ByVal Flip As Boolean, _  
    ByVal Dir As Boolean, _  
    ByVal T1 As Long, _  
    ByVal T2 As Long, _  
    ByVal D1 As Double, _  
    ByVal D2 As Double, _  
    ByVal Dchk1 As Boolean, _  
    ByVal Dchk2 As Boolean, _  
    ByVal Ddir1 As Boolean, _  
    ByVal Ddir2 As Boolean, _  
    ByVal Dang1 As Double, _  
    ByVal Dang2 As Double, _  
    ByVal OffsetReverse1 As Boolean, _  
    ByVal OffsetReverse2 As Boolean, _  
    ByVal KeepPieceIndex As Long _  
)
```

SOLIDWORKS Type Library

FeatureCut3 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub FeatureCut3( _  
    ByVal Sd As Boolean, _  
    ByVal Flip As Boolean, _  
    ByVal Dir As Boolean, _  
    ByVal T1 As Long, _  
    ByVal T2 As Long, _  
    ByVal D1 As Double, _  
    ByVal D2 As Double, _  
    ByVal Dchk1 As Boolean, _  
    ByVal Dchk2 As Boolean, _  
    ByVal Ddir1 As Boolean, _  
    ByVal Ddir2 As Boolean, _  
    ByVal Dang1 As Double, _  
    ByVal Dang2 As Double, _  
    ByVal OffsetReverse1 As Boolean, _  
    ByVal OffsetReverse2 As Boolean, _  
    ByVal KeepPieceIndex As Long _  
)
```

SOLIDWORKS Type Library

FeatureCut4 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub FeatureCut4( _  
    ByVal Sd As Boolean, _  
    ByVal Flip As Boolean, _  
    ByVal Dir As Boolean, _  
    ByVal T1 As Long, _  
    ByVal T2 As Long, _  
    ByVal D1 As Double, _  
    ByVal D2 As Double, _  
)
```

```

ByVal Dchk1 As Boolean, _
ByVal Dchk2 As Boolean, _
ByVal Ddir1 As Boolean, _
ByVal Ddir2 As Boolean, _
ByVal Dang1 As Double, _
ByVal Dang2 As Double, _
ByVal OffsetReverse1 As Boolean, _
ByVal OffsetReverse2 As Boolean, _
ByVal KeepPieceIndex As Long, _
ByVal NormalCut As Boolean _
)

```

SOLIDWORKS Type Library

FeatureCut5 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```

Public Sub FeatureCut5( _
    ByVal Sd As Boolean, _
    ByVal Flip As Boolean, _
    ByVal Dir As Boolean, _
    ByVal T1 As Long, _
    ByVal T2 As Long, _
    ByVal D1 As Double, _
    ByVal D2 As Double, _
    ByVal Dchk1 As Boolean, _
    ByVal Dchk2 As Boolean, _
    ByVal Ddir1 As Boolean, _
    ByVal Ddir2 As Boolean, _
    ByVal Dang1 As Double, _
    ByVal Dang2 As Double, _
    ByVal OffsetReverse1 As Boolean, _
    ByVal OffsetReverse2 As Boolean, _
    ByVal TranslateSurface1 As Boolean, _
    ByVal TranslateSurface2 As Boolean, _
    ByVal KeepPieceIndex As Long, _
    ByVal NormalCut As Boolean _
)

```

SOLIDWORKS Type Library

FeatureCutThicken Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```

Public Sub FeatureCutThicken( _
    ByVal Thickness As Double, _
    ByVal Direction As Long, _
    ByVal FaceIndex As Long _
)

```

SOLIDWORKS Type Library

FeatureCutThicken2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```

Public Sub FeatureCutThicken2( _
    ByVal Thickness As Double, _
    ByVal Direction As Long, _
    ByVal FaceIndex As Long, _
    ByVal FillVolume As Boolean _
)

```

SOLIDWORKS Type Library

FeatureCutThin Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Sub FeatureCutThin( _  
    ByVal Sd As Boolean, _  
    ByVal Flip As Boolean, _  
    ByVal Dir As Boolean, _  
    ByVal T1 As Long, _  
    ByVal T2 As Long, _  
    ByVal D1 As Double, _  
    ByVal D2 As Double, _  
    ByVal Dchk1 As Boolean, _  
    ByVal Dchk2 As Boolean, _  
    ByVal Ddir1 As Boolean, _  
    ByVal Ddir2 As Boolean, _  
    ByVal Dang1 As Double, _  
    ByVal Dang2 As Double, _  
    ByVal OffsetReverse1 As Boolean, _  
    ByVal OffsetReverse2 As Boolean, _  
    ByVal Thk1 As Double, _  
    ByVal Thk2 As Double, _  
    ByVal EndThk As Double, _  
    ByVal RevThinDir As Long, _  
    ByVal CapEnds As Long, _  
    ByVal AddBends As Boolean, _  
    ByVal BendRad As Double _  
)
```

SOLIDWORKS Type Library

FeatureCutThin2 Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Sub FeatureCutThin2( _  
    ByVal Sd As Boolean, _  
    ByVal Flip As Boolean, _  
    ByVal Dir As Boolean, _  
    ByVal T1 As Long, _  
    ByVal T2 As Long, _  
    ByVal D1 As Double, _  
    ByVal D2 As Double, _  
    ByVal Dchk1 As Boolean, _  
    ByVal Dchk2 As Boolean, _  
    ByVal Ddir1 As Boolean, _  
    ByVal Ddir2 As Boolean, _  
    ByVal Dang1 As Double, _  
    ByVal Dang2 As Double, _  
    ByVal OffsetReverse1 As Boolean, _  
    ByVal OffsetReverse2 As Boolean, _  
    ByVal TranslateSurface1 As Boolean, _  
    ByVal TranslateSurface2 As Boolean, _  
    ByVal Thk1 As Double, _  
    ByVal Thk2 As Double, _  
    ByVal EndThk As Double, _  
    ByVal RevThinDir As Long, _  
    ByVal CapEnds As Long, _  
    ByVal AddBends As Boolean, _  
    ByVal BendRad As Double _  
)
```

SOLIDWORKS Type Library

FeatureExtruRefSurface Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Sub FeatureExtruRefSurface( _  
    ByVal Sd As Boolean, _
```

```

    ByVal Flip As Boolean, _
    ByVal Dir As Boolean, _
    ByVal T1 As Long, _
    ByVal T2 As Long, _
    ByVal D1 As Double, _
    ByVal D2 As Double, _
    ByVal Dchk1 As Boolean, _
    ByVal Dchk2 As Boolean, _
    ByVal Ddir1 As Boolean, _
    ByVal Ddir2 As Boolean, _
    ByVal Dang1 As Double, _
    ByVal Dang2 As Double, _
    ByVal OffsetReverse1 As Boolean, _
    ByVal OffsetReverse2 As Boolean _
)

```

SOLIDWORKS Type Library

FeatureExtruRefSurface2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```

Public Sub FeatureExtruRefSurface2( _
    ByVal Sd As Boolean, _
    ByVal Flip As Boolean, _
    ByVal Dir As Boolean, _
    ByVal T1 As Long, _
    ByVal T2 As Long, _
    ByVal D1 As Double, _
    ByVal D2 As Double, _
    ByVal Dchk1 As Boolean, _
    ByVal Dchk2 As Boolean, _
    ByVal Ddir1 As Boolean, _
    ByVal Ddir2 As Boolean, _
    ByVal Dang1 As Double, _
    ByVal Dang2 As Double, _
    ByVal OffsetReverse1 As Boolean, _
    ByVal OffsetReverse2 As Boolean, _
    ByVal TranslateSurface1 As Boolean, _
    ByVal TranslateSurface2 As Boolean _
)

```

SOLIDWORKS Type Library

FeatureFillet Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```

Public Sub FeatureFillet( _
    ByVal R1 As Double, _
    ByVal Propagate As Boolean, _
    ByVal Ftyp As Boolean, _
    ByVal VarRadTyp As Boolean, _
    ByVal OverflowType As Long _
)

```

SOLIDWORKS Type Library

FeatureFillet2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```

Public Function FeatureFillet2( _
    ByVal R1 As Double, _
    ByVal Propagate As Boolean, _
    ByVal Ftyp As Boolean, _
    ByVal VarRadTyp As Boolean, _
    ByVal OverflowType As Long, _
) As Variant

```

```
    ByVal NRadii As Integer, _  
    ByVal Radii As Variant _  
) As Long
```

SOLIDWORKS Type Library

FeatureFillet3 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function FeatureFillet3( _  
    ByVal R1 As Double, _  
    ByVal Propagate As Boolean, _  
    ByVal Ftyp As Integer, _  
    ByVal VarRadTyp As Boolean, _  
    ByVal OverflowType As Long, _  
    ByVal NRadii As Integer, _  
    ByVal Radii As Variant, _  
    ByVal UseHelpPoint As Boolean, _  
    ByVal UseTangentHoldLine As Boolean _  
) As Long
```

SOLIDWORKS Type Library

FeatureFillet4 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function FeatureFillet4( _  
    ByVal R1 As Double, _  
    ByVal Propagate As Boolean, _  
    ByVal UniformRadius As Boolean, _  
    ByVal Ftyp As Integer, _  
    ByVal VarRadTyp As Boolean, _  
    ByVal OverflowType As Long, _  
    ByVal NRadii As Integer, _  
    ByVal Radii As Variant, _  
    ByVal UseHelpPoint As Boolean, _  
    ByVal UseTangentHoldLine As Boolean, _  
    ByVal CornerType As Boolean, _  
    ByVal SetbackDistCount As Integer, _  
    ByVal SetBackDistances As Variant _  
) As Long
```

SOLIDWORKS Type Library

FeatureFillet5 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function FeatureFillet5( _  
    ByVal Options As Long, _  
    ByVal R1 As Double, _  
    ByVal Ftyp As Long, _  
    ByVal OverflowType As Long, _  
    ByVal Radii As Variant, _  
    ByVal SetBackDistances As Variant, _  
    ByVal PointRadiusArray As Variant _  
) As Long
```

SOLIDWORKS Type Library

FeatureLinearPattern Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub FeatureLinearPattern( _  
    ByVal Num1 As Long, _
```

```
ByVal Spacing1 As Double, _  
ByVal Num2 As Long, _  
ByVal Spacing2 As Double, _  
ByVal FlipDir1 As Boolean, _  
ByVal FlipDir2 As Boolean, _  
ByVal DName1 As String, _  
ByVal DName2 As String _  
)
```

SOLIDWORKS Type Library

FeatureManager Property (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property FeatureManager As FeatureManager
```

SOLIDWORKS Type Library

FeatureManagerSplitterPosition Property (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property FeatureManagerSplitterPosition As Double
```

SOLIDWORKS Type Library

FeatureReferenceCurve Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function FeatureReferenceCurve( _  
    ByVal NumOfCurves As Long, _  
    ByVal BaseCurves As Variant, _  
    ByVal Merge As Boolean, _  
    ByVal FromFileName As String, _  
    ByRef ErrorCode As Long _  
) As Object
```

SOLIDWORKS Type Library

FeatureRevolve2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function FeatureRevolve2( _  
    ByVal Angle As Double, _  
    ByVal ReverseDir As Boolean, _  
    ByVal Angle2 As Double, _  
    ByVal RevType As Long, _  
    ByVal Options As Long _  
) As Long
```

SOLIDWORKS Type Library

FeatureRevolveCut2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function FeatureRevolveCut2( _  
    ByVal Angle As Double, _  
    ByVal ReverseDir As Boolean, _  
    ByVal Angle2 As Double, _  
    ByVal RevType As Long, _  
    ByVal Options As Long _  
) As Long
```

FeatureSketchDrivenPattern Method (ModelDoc2) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub FeatureSketchDrivenPattern( _  
    ByVal UseCentroid As Boolean _  
)
```

FileReload Method (ModelDoc2) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub FileReload()
```

FileSummaryInfo Method (ModelDoc2) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub FileSummaryInfo()
```

FirstFeature Method (ModelDoc2) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function FirstFeature() As Object
```

FontBold Method (ModelDoc2) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub FontBold( _  
    ByVal Bold As Boolean _  
)
```

FontFace Method (ModelDoc2) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub FontFace( _  
    ByVal Face As String _  
)
```

FontItalic Method (ModelDoc2) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub FontItalic( _  
    ByVal Italic As Boolean _  
)
```

FontPoints Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub FontPoints( _  
    ByVal Points As Integer _  
)
```

SOLIDWORKS Type Library

FontUnderline Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub FontUnderline( _  
    ByVal Underline As Boolean _  
)
```

SOLIDWORKS Type Library

FontUnits Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub FontUnits( _  
    ByVal Units As Double _  
)
```

SOLIDWORKS Type Library

ForceRebuild3 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ForceRebuild3( _  
    ByVal TopOnly As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

ForceReleaseLocks Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ForceReleaseLocks() As Long
```

SOLIDWORKS Type Library

GetActiveConfiguration Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetActiveConfiguration() As Object
```

SOLIDWORKS Type Library

GetActiveSketch Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetActiveSketch() As Object
```

SOLIDWORKS Type Library

GetActiveSketch2 Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function GetActiveSketch2() As Object
```

SOLIDWORKS Type Library

GetAddToDB Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function GetAddToDB() As Boolean
```

SOLIDWORKS Type Library

GetAmbientLightProperties Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function GetAmbientLightProperties( _  
    ByVal Name As String, _  
    ByRef Ambient As Double, _  
    ByRef Diffuse As Double, _  
    ByRef Specular As Double, _  
    ByRef Colour As Long, _  
    ByRef Enabled As Boolean, _  
    ByRef Fixed As Boolean _  
    ) As Boolean
```

SOLIDWORKS Type Library

GetAngularUnits Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function GetAngularUnits() As Variant
```

SOLIDWORKS Type Library

GetArcCentersDisplayed Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function GetArcCentersDisplayed() As Boolean
```

SOLIDWORKS Type Library

GetBendState Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function GetBendState() As Long
```

SOLIDWORKS Type Library

GetBlockingState Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function GetBlockingState() As Long
```

SOLIDWORKS Type Library

GetColorTable Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function GetColorTable() As Object
```

SOLIDWORKS Type Library

GetConfigurationByName Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function GetConfigurationByName( _  
    ByVal Name As String _  
) As Object
```

SOLIDWORKS Type Library

GetConfigurationCount Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function GetConfigurationCount() As Long
```

SOLIDWORKS Type Library

GetConfigurationNames Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function GetConfigurationNames() As Variant
```

SOLIDWORKS Type Library

GetConsiderLeadersAsLines Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function GetConsiderLeadersAsLines() As Boolean
```

SOLIDWORKS Type Library

GetCoordinateSystemXformByName Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function GetCoordinateSystemXformByName( _  
    ByVal NameIn As String _  
) As Variant
```

SOLIDWORKS Type Library

GetCurrentCoordinateSystemName Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function GetCurrentCoordinateSystemName() As String
```

SOLIDWORKS Type Library

GetCustomInfoCount Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function GetCustomInfoCount() As Long
```

SOLIDWORKS Type Library

GetCustomInfoCount2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCustomInfoCount2( _  
    ByVal Configuration As String _  
) As Long
```

SOLIDWORKS Type Library

GetCustomInfoNames Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCustomInfoNames() As Variant
```

SOLIDWORKS Type Library

GetCustomInfoNames2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCustomInfoNames2( _  
    ByVal Configuration As String _  
) As Variant
```

SOLIDWORKS Type Library

GetCustomInfoType Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCustomInfoType( _  
    ByVal FieldName As String _  
) As String
```

SOLIDWORKS Type Library

GetCustomInfoType2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCustomInfoType2( _  
    ByVal FieldName As String _  
) As Long
```

SOLIDWORKS Type Library

GetCustomInfoType3 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCustomInfoType3( _  
    ByVal Configuration As String, _  
    ByVal FieldName As String _  
) As Long
```

SOLIDWORKS Type Library

GetCustomInfoValue Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCustomInfoValue( _  
    ByVal Configuration As String, _
```

```
ByVal FieldName As String _  
) As String
```

SOLIDWORKS Type Library

GetDefaultTextHeight Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDefaultTextHeight() As Double
```

SOLIDWORKS Type Library

GetDependencies Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDependencies( _  
    ByVal Traverseflag As Long, _  
    ByVal Searchflag As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetDependencies2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDependencies2( _  
    ByVal Traverseflag As Boolean, _  
    ByVal Searchflag As Boolean, _  
    ByVal AddReadOnlyInfo As Boolean _  
) As Variant
```

SOLIDWORKS Type Library

GetDesignTable Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDesignTable() As Object
```

SOLIDWORKS Type Library

GetDetailingDefaults Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDetailingDefaults() As Object
```

SOLIDWORKS Type Library

GetDirectionLightProperties Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDirectionLightProperties( _  
    ByVal Name As String, _  
    ByRef Ambient As Double, _  
    ByRef Diffuse As Double, _  
    ByRef Specular As Double, _  
    ByRef Colour As Long, _  
    ByRef Enabled As Boolean, _  
    ByRef Fixed As Boolean, _  
    ByRef X As Double, _  
    ByRef Y As Double, _
```

```
ByRef Z As Double _  
) As Boolean
```

SOLIDWORKS Type Library

GetDisplayWhenAdded Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDisplayWhenAdded() As Boolean
```

SOLIDWORKS Type Library

GetEntityName Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetEntityName( _  
    ByVal Entity As Object _  
) As String
```

SOLIDWORKS Type Library

GetEquationMgr Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetEquationMgr() As EquationMgr
```

SOLIDWORKS Type Library

GetExternalReferenceName Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetExternalReferenceName() As String
```

SOLIDWORKS Type Library

GetFeatureCount Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFeatureCount() As Long
```

SOLIDWORKS Type Library

GetFeatureManagerWidth Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFeatureManagerWidth() As Long
```

SOLIDWORKS Type Library

GetFirstAnnotation Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFirstAnnotation() As Object
```

SOLIDWORKS Type Library

GetFirstAnnotation2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFirstAnnotation2() As Object
```

SOLIDWORKS Type Library

GetFirstModelView Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFirstModelView() As Object
```

SOLIDWORKS Type Library

GetGridSettings Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetGridSettings() As Variant
```

SOLIDWORKS Type Library

GetInferenceMode Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetInferenceMode() As Boolean
```

SOLIDWORKS Type Library

GetLayerManager Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetLayerManager() As Object
```

SOLIDWORKS Type Library

GetLightSourceCount Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetLightSourceCount() As Long
```

SOLIDWORKS Type Library

GetLightSourceExtProperty Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetLightSourceExtProperty( _  
    ByVal ID As Long, _  
    ByVal PropertyId As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetLightSourceIdFromName Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetLightSourceIdFromName( _  
    ByVal LightName As String _  
) As Long
```

SOLIDWORKS Type Library

GetLightSourceName Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetLightSourceName( _  
    ByVal ID As Long _  
) As String
```

SOLIDWORKS Type Library

GetLineCount Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetLineCount() As Long
```

SOLIDWORKS Type Library

GetLines Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetLines() As Variant
```

SOLIDWORKS Type Library

GetMassProperties Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetMassProperties() As Variant
```

SOLIDWORKS Type Library

GetMassProperties2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetMassProperties2( _  
    ByRef Status As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetModelViewCount Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetModelViewCount() As Integer
```

SOLIDWORKS Type Library

GetModelViewNames Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetModelViewNames() As Variant
```

SOLIDWORKS Type Library

GetNext Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNext() As Object
```

SOLIDWORKS Type Library

GetNumDependencies Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNumDependencies( _  
    ByVal Traverseflag As Long, _  
    ByVal Searchflag As Long _  
    ) As Long
```

SOLIDWORKS Type Library

GetPathName Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPathName() As String
```

SOLIDWORKS Type Library

GetPointLightProperties Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPointLightProperties( _  
    ByVal Name As String, _  
    ByRef Ambient As Double, _  
    ByRef Diffuse As Double, _  
    ByRef Specular As Double, _  
    ByRef Colour As Long, _  
    ByRef Enabled As Boolean, _  
    ByRef Fixed As Boolean, _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double _  
    ) As Boolean
```

SOLIDWORKS Type Library

GetPopupMenuMode Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPopupMenuMode() As Integer
```

SOLIDWORKS Type Library

GetPropertyExtension Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPropertyExtension( _  
    ByVal ID As Long _  
    ) As Variant
```

SOLIDWORKS Type Library

GetPropertyManagerPage Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPropertyManagerPage( _  
    ByVal DialogId As Long, _  
    ByVal Title As String, _  
    ByVal Handler As Unknown _  
) As PropertyManagerPage
```

SOLIDWORKS Type Library

GetRayIntersectionsPoints Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetRayIntersectionsPoints() As Variant
```

SOLIDWORKS Type Library

GetRayIntersectionsTopology Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetRayIntersectionsTopology() As Variant
```

SOLIDWORKS Type Library

GetSaveFlag Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSaveFlag() As Boolean
```

SOLIDWORKS Type Library

GetSceneBkgDIB Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSceneBkgDIB() As Long
```

SOLIDWORKS Type Library

GetSceneExtProperty Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSceneExtProperty( _  
    ByVal PropertyId As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetSpotlightProperties Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSpotlightProperties( _  
    ByVal Name As String, _  
    ByRef Ambient As Double, _  
    ByRef Diffuse As Double, _  
    ByRef Specular As Double, _  
    ByRef Colour As Long, _  
    ByRef Enabled As Boolean, _  
    ByRef Fixed As Boolean, _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _
```

```
ByRef Targetx As Double, _  
ByRef Targety As Double, _  
ByRef Targetz As Double, _  
ByRef ConeAngle As Double _  
) As Boolean
```

SOLIDWORKS Type Library

GetStandardViewRotation Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetStandardViewRotation( _  
    ByVal ViewId As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetTessellationQuality Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTessellationQuality() As Long
```

SOLIDWORKS Type Library

GetTitle Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTitle() As String
```

SOLIDWORKS Type Library

GetToolbarVisibility Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetToolbarVisibility( _  
    ByVal Toolbar As Long _  
) As Boolean
```

SOLIDWORKS Type Library

GetType Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetType() As Long
```

SOLIDWORKS Type Library

GetUnits Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetUnits() As Variant
```

SOLIDWORKS Type Library

GetUpdateStamp Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetUpdateStamp() As Long
```

GetUserPreferenceDoubleValue Method (ModelDoc2) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetUserPreferenceDoubleValue( _  
    ByVal UserPreferenceValue As Long _  
) As Double
```

GetUserPreferenceIntegerValue Method (ModelDoc2) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetUserPreferenceIntegerValue( _  
    ByVal UserPreferenceValue As Long _  
) As Long
```

GetUserPreferenceStringValue Method (ModelDoc2) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetUserPreferenceStringValue( _  
    ByVal UserPreference As Long _  
) As String
```

GetUserPreferenceTextFormat Method (ModelDoc2) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetUserPreferenceTextFormat( _  
    ByVal UserPreferenceValue As Long _  
) As Object
```

GetUserPreferenceToggle Method (ModelDoc2) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetUserPreferenceToggle( _  
    ByVal UserPreferenceToggle As Long _  
) As Boolean
```

GetUserUnit Method (ModelDoc2) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetUserUnit( _  
    ByVal UnitType As Long _  
) As Object
```

GetVisibilityOfConstructPlanes Method (ModelDoc2) **Syntax**

Visual Basic for Applications (VBA)

Public Function GetVisibilityOfConstructPlanes() As Boolean

SOLIDWORKS Type Library

GetZebraStripeData Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub GetZebraStripeData( _  
    ByRef Size As Double, _  
    ByRef Ratio As Double, _  
    ByRef Color1 As Long, _  
    ByRef Color2 As Long _  
)
```

SOLIDWORKS Type Library

GraphicsRedraw Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub GraphicsRedraw()
```

SOLIDWORKS Type Library

GraphicsRedraw2 Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub GraphicsRedraw2()
```

SOLIDWORKS Type Library

GridOptions Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub GridOptions( _  
    ByVal DispGrid As Boolean, _  
    ByVal GridSpacing As Double, _  
    ByVal Snap As Boolean, _  
    ByVal DotStyle As Boolean, _  
    ByVal NMajor As Integer, _  
    ByVal NMinor As Integer, _  
    ByVal Align2edge As Boolean, _  
    ByVal AngleSnap As Boolean, _  
    ByVal AngleUnit As Double, _  
    ByVal MinorAuto As Boolean _  
)
```

SOLIDWORKS Type Library

HideComponent2 Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub HideComponent2()
```

SOLIDWORKS Type Library

HideCosmeticThread Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub HideCosmeticThread()
```

SOLIDWORKS Type Library

HideDimension Method (ModelDoc2)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub HideDimension()
```

SOLIDWORKS Type Library

HideFeatureDimensions Method (ModelDoc2)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub HideFeatureDimensions()
```

SOLIDWORKS Type Library

HideShowBodies Method (ModelDoc2)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub HideShowBodies()
```

SOLIDWORKS Type Library

HideSolidBody Method (ModelDoc2)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub HideSolidBody()
```

SOLIDWORKS Type Library

HoleWizard Method (ModelDoc2)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub HoleWizard( _  
    ByVal Depth As Double, _  
    ByVal EndType As Integer, _  
    ByVal Flip As Boolean, _  
    ByVal Dir As Boolean, _  
    ByVal HType As Long, _  
    ByVal D1 As Double, _  
    ByVal D2 As Double, _  
    ByVal D3 As Double, _  
    ByVal D4 As Double, _  
    ByVal D5 As Double, _  
    ByVal D6 As Double, _  
    ByVal D7 As Double, _  
    ByVal D8 As Double, _  
    ByVal D9 As Double, _  
    ByVal D10 As Double, _  
    ByVal D11 As Double, _  
    ByVal D12 As Double _  
)
```

SOLIDWORKS Type Library

IActiveView Property (ModelDoc2)

 **Syntax**

Visual Basic for Applications (VBA)

Public Property IActiveView As [ModelView](#)

SOLIDWORKS Type Library

IAddConfiguration3 Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function IAddConfiguration3( _  
    ByVal Name As String, _  
    ByVal Comment As String, _  
    ByVal AlternateName As String, _  
    ByVal Options As Long _  
) As Configuration
```

SOLIDWORKS Type Library

IAddDiameterDimension2 Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function IAddDiameterDimension2( _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
) As DisplayDimension
```

SOLIDWORKS Type Library

IAddDimension2 Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function IAddDimension2( _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
) As DisplayDimension
```