

SOLIDWORKS API (VB6 COM) — Reference (61/102): ModelDoc2 (part 3 of 5)

SOLIDWORKS API Documentation (converted from CHM)

ModelDoc2 (part 3 of 5) (Type)

SOLIDWORKS Type Library

IAddHorizontalDimension2 Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IAddHorizontalDimension2( _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
) As DisplayDimension
```

SOLIDWORKS Type Library

IAddOrEditConfiguration Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IAddOrEditConfiguration( _  
    ByVal ConfigName As String, _  
    ByVal ParamCount As Long, _  
    ByRef ParamNames As String, _  
    ByRef ParamValues As String _  
) As Long
```

SOLIDWORKS Type Library

IAddRadialDimension2 Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IAddRadialDimension2( _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
) As DisplayDimension
```

SOLIDWORKS Type Library

IAddVerticalDimension2 Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IAddVerticalDimension2( _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
) As DisplayDimension
```

SOLIDWORKS Type Library

IClosestDistance Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IClosestDistance( _  
    ByVal Object1 As Object, _  
    ByVal Object2 As Object, _  
    ByRef Point1 As Double, _  
    ByRef Point2 As Double _  
) As Double
```

SOLIDWORKS Type Library

ICreateArc Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ICreateArc( _  
    ByRef P1 As Double, _  
    ByRef P2 As Double, _  
    ByRef P3 As Double, _  
    ByVal Dir As Integer _  
)
```

SOLIDWORKS Type Library

ICreateArc2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateArc2( _  
    ByVal XC As Double, _  
    ByVal YC As Double, _  
    ByVal Zc As Double, _  
    ByVal Xp1 As Double, _  
    ByVal Yp1 As Double, _  
    ByVal Zp1 As Double, _  
    ByVal Xp2 As Double, _  
    ByVal Yp2 As Double, _  
    ByVal Zp2 As Double, _  
    ByVal Direction As Integer _  
) As SketchSegment
```

SOLIDWORKS Type Library

ICreateCenterLine Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ICreateCenterLine( _  
    ByRef P1 As Double, _  
    ByRef P2 As Double _  
)
```

SOLIDWORKS Type Library

ICreateCircle2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateCircle2( _  
    ByVal XC As Double, _  
    ByVal YC As Double, _  
    ByVal Zc As Double, _  
    ByVal Xp As Double, _  
    ByVal Yp As Double, _  
    ByVal Zp As Double _  
) As SketchSegment
```

SOLIDWORKS Type Library

ICreateCircleByRadius Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ICreateCircleByRadius( _  
    ByRef P1 As Double, _  
    ByVal Radius As Double _  
)
```

SOLIDWORKS Type Library

ICreateCircleByRadius2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateCircleByRadius2( _  
    ByVal XC As Double, _  
    ByVal YC As Double, _  
    ByVal Zc As Double, _  
    ByVal Radius As Double _  
    ) As SketchSegment
```

SOLIDWORKS Type Library

ICreateClippedSplines Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateClippedSplines( _  
    ByRef PropArray As Integer, _  
    ByRef KnotsArray As Double, _  
    ByRef CntrlPntCoordArray As Double, _  
    ByVal X1 As Double, _  
    ByVal Y1 As Double, _  
    ByVal X2 As Double, _  
    ByVal Y2 As Double _  
    ) As EnumSketchSegments
```

SOLIDWORKS Type Library

ICreateEllipse Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ICreateEllipse( _  
    ByRef Center As Double, _  
    ByRef Major As Double, _  
    ByRef Minor As Double _  
    )
```

SOLIDWORKS Type Library

ICreateEllipse2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateEllipse2( _  
    ByVal CenterX As Double, _  
    ByVal CenterY As Double, _  
    ByVal CenterZ As Double, _  
    ByVal MajorX As Double, _  
    ByVal MajorY As Double, _  
    ByVal MajorZ As Double, _  
    ByVal MinorX As Double, _  
    ByVal MinorY As Double, _  
    ByVal MinorZ As Double _  
    ) As SketchSegment
```

SOLIDWORKS Type Library

ICreateEllipticalArc2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateEllipticalArc2( _  
    ByVal CenterX As Double, _  
    ByVal CenterY As Double, _
```

```
ByVal CenterZ As Double, _  
ByVal MajorX As Double, _  
ByVal MajorY As Double, _  
ByVal MajorZ As Double, _  
ByVal MinorX As Double, _  
ByVal MinorY As Double, _  
ByVal MinorZ As Double, _  
ByVal StartX As Double, _  
ByVal StartY As Double, _  
ByVal StartZ As Double, _  
ByVal EndX As Double, _  
ByVal EndY As Double, _  
ByVal EndZ As Double _  
) As SketchSegment
```

SOLIDWORKS Type Library

ICreateEllipticalArcByCenter Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ICreateEllipticalArcByCenter( _  
ByRef Center As Double, _  
ByRef Major As Double, _  
ByRef Minor As Double, _  
ByRef Start As Double, _  
ByRef End As Double _  
)
```

SOLIDWORKS Type Library

ICreateFeatureMgrView Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateFeatureMgrView( _  
ByRef Bitmap As Long _  
) As FeatMgrView
```

SOLIDWORKS Type Library

ICreateFeatureMgrView2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateFeatureMgrView2( _  
ByRef Bitmap As Long, _  
ByVal ToolTip As String _  
) As FeatMgrView
```

SOLIDWORKS Type Library

ICreateFeatureMgrView3 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateFeatureMgrView3( _  
ByRef Bitmap As Long, _  
ByVal ToolTip As String, _  
ByVal WhichPane As Long _  
) As FeatMgrView
```

SOLIDWORKS Type Library

ICreateLine Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ICreateLine( _  
    ByRef P1 As Double, _  
    ByRef P2 As Double _  
)
```

SOLIDWORKS Type Library

ICreateLine2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateLine2( _  
    ByVal P1x As Double, _  
    ByVal P1y As Double, _  
    ByVal P1z As Double, _  
    ByVal P2x As Double, _  
    ByVal P2y As Double, _  
    ByVal P2z As Double _  
) As SketchSegment
```

SOLIDWORKS Type Library

ICreatePlaneAtAngle2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreatePlaneAtAngle2( _  
    ByVal Val As Double, _  
    ByVal FlipDir As Boolean _  
) As RefPlane
```

SOLIDWORKS Type Library

ICreatePlaneAtAngle3 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreatePlaneAtAngle3( _  
    ByVal Val As Double, _  
    ByVal FlipDir As Boolean, _  
    ByVal AutoSize As Boolean _  
) As RefPlane
```

SOLIDWORKS Type Library

ICreatePlaneAtOffset2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreatePlaneAtOffset2( _  
    ByVal Val As Double, _  
    ByVal FlipDir As Boolean _  
) As RefPlane
```

SOLIDWORKS Type Library

ICreatePlaneAtOffset3 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreatePlaneAtOffset3( _  
    ByVal Val As Double, _  
    ByVal FlipDir As Boolean, _  
    ByVal AutoSize As Boolean _  
) As RefPlane
```

ICreatePlaneAtSurface2 Method (ModelDoc2)

Visual Basic for Applications (VBA)

```
Public Function ICreatePlaneAtSurface2( _
    ByVal InterIndex As Integer, _
    ByVal ProjOpt As Boolean, _
    ByVal ReverseDir As Boolean, _
    ByVal NormalPlane As Boolean, _
    ByVal Angle As Double _
) As RefPlane
```

ICreatePlaneAtSurface3 Method (ModelDoc2)

Visual Basic for Applications (VBA)

```
Public Function ICreatePlaneAtSurface3( _
    ByVal InterIndex As Integer, _
    ByVal ProjOpt As Boolean, _
    ByVal ReverseDir As Boolean, _
    ByVal NormalPlane As Boolean, _
    ByVal Angle As Double, _
    ByVal AutoSize As Boolean _
) As RefPlane
```

ICreatePlaneFixed Method (ModelDoc2)

Visual Basic for Applications (VBA)

```
Public Sub ICreatePlaneFixed( _
    ByRef P1 As Double, _
    ByRef P2 As Double, _
    ByRef P3 As Double, _
    ByVal UseGlobal As Boolean _
)
```

ICreatePlaneFixed2 Method (ModelDoc2)

Visual Basic for Applications (VBA)

```
Public Function ICreatePlaneFixed2( _
    ByRef P1 As Double, _
    ByRef P2 As Double, _
    ByRef P3 As Double, _
    ByVal UseGlobal As Boolean _
) As RefPlane
```

ICreatePlanePerCurveAndPassPoint2 Method (ModelDoc2)

Visual Basic for Applications (VBA)

```
Public Function ICreatePlanePerCurveAndPassPoint2( _
    ByVal OrigAtCurve As Boolean _
) As RefPlane
```

ICreatePlanePerCurveAndPassPoint3 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreatePlanePerCurveAndPassPoint3( _  
    ByVal OrigAtCurve As Boolean, _  
    ByVal AutoSize As Boolean _  
    ) As RefPlane
```

SOLIDWORKS Type Library

ICreatePlaneThru3Points2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreatePlaneThru3Points2() As RefPlane
```

SOLIDWORKS Type Library

ICreatePlaneThru3Points3 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreatePlaneThru3Points3( _  
    ByVal AutoSize As Boolean _  
    ) As RefPlane
```

SOLIDWORKS Type Library

ICreatePlaneThruLineAndPt Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreatePlaneThruLineAndPt( _  
    ByVal AutoSize As Boolean _  
    ) As RefPlane
```

SOLIDWORKS Type Library

ICreatePlaneThruPtParallelToPlane Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreatePlaneThruPtParallelToPlane( _  
    ByVal AutoSize As Boolean _  
    ) As RefPlane
```

SOLIDWORKS Type Library

ICreatePoint2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreatePoint2( _  
    ByVal PointX As Double, _  
    ByVal PointY As Double, _  
    ByVal PointZ As Double _  
    ) As SketchPoint
```

SOLIDWORKS Type Library

ICreateSpline Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateSpline( _  
    ByVal PointCount As Long, _
```

```
ByRef PointData As Double _  
) As SketchSegment
```

SOLIDWORKS Type Library

ICreateSplineByEqnParams Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateSplineByEqnParams( _  
    ByRef PropArray As Integer, _  
    ByRef KnotsArray As Double, _  
    ByRef CntrlPntCoordArray As Double _  
) As SketchSegment
```

SOLIDWORKS Type Library

ICreateSplinesByEqnParams Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateSplinesByEqnParams( _  
    ByRef PropArray As Integer, _  
    ByRef KnotsArray As Double, _  
    ByRef CntrlPntCoordArray As Double _  
) As EnumSketchSegments
```

SOLIDWORKS Type Library

IEditDimensionProperties3 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IEditDimensionProperties3( _  
    ByVal TolType As Long, _  
    ByVal TolMax As Double, _  
    ByVal TolMin As Double, _  
    ByVal TolMaxFit As String, _  
    ByVal TolMinFit As String, _  
    ByVal UseDocPrec As Boolean, _  
    ByVal Precision As Long, _  
    ByVal ArrowsIn As Long, _  
    ByVal UseDocArrows As Boolean, _  
    ByVal Arrow1 As Long, _  
    ByVal Arrow2 As Long, _  
    ByVal PrefixText As String, _  
    ByVal SuffixText As String, _  
    ByVal ShowValue As Boolean, _  
    ByVal CalloutText1 As String, _  
    ByVal CalloutText2 As String, _  
    ByVal CenterText As Boolean, _  
    ByVal ConfigOption As Long, _  
    ByVal Count As Long, _  
    ByRef ConfigNames As String _  
) As Boolean
```

SOLIDWORKS Type Library

IFeatureByPositionReverse Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IFeatureByPositionReverse( _  
    ByVal Num As Long _  
) As Feature
```

SOLIDWORKS Type Library

IFeatureFillet2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IFeatureFillet2( _  
    ByVal R1 As Double, _  
    ByVal Propagate As Boolean, _  
    ByVal Ftyp As Boolean, _  
    ByVal VarRadTyp As Boolean, _  
    ByVal OverflowType As Long, _  
    ByVal NRadii As Integer, _  
    ByRef Radii As Double _  
) As Long
```

SOLIDWORKS Type Library

IFeatureFillet3 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IFeatureFillet3( _  
    ByVal R1 As Double, _  
    ByVal Propagate As Boolean, _  
    ByVal Ftyp As Integer, _  
    ByVal VarRadTyp As Boolean, _  
    ByVal OverflowType As Long, _  
    ByVal NRadii As Integer, _  
    ByRef Radii As Double, _  
    ByVal UseHelpPoint As Boolean, _  
    ByVal UseTangentHoldLine As Boolean _  
) As Long
```

SOLIDWORKS Type Library

IFeatureFillet4 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IFeatureFillet4( _  
    ByVal R1 As Double, _  
    ByVal Propagate As Boolean, _  
    ByVal UniformRadius As Boolean, _  
    ByVal Ftyp As Integer, _  
    ByVal VarRadTyp As Boolean, _  
    ByVal OverflowType As Long, _  
    ByVal NRadii As Integer, _  
    ByRef Radii As Double, _  
    ByVal UseHelpPoint As Boolean, _  
    ByVal UseTangentHoldLine As Boolean, _  
    ByVal CornerType As Boolean, _  
    ByVal SetbackDistCount As Integer, _  
    ByRef SetBackDistances As Double _  
) As Long
```

SOLIDWORKS Type Library

IFeatureFillet5 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IFeatureFillet5( _  
    ByVal Options As Long, _  
    ByVal R1 As Double, _  
    ByVal Ftyp As Long, _  
    ByVal OverflowType As Long, _  
    ByVal NRadii As Long, _  
    ByRef Radii As Double, _
```

```
ByVal SetbackDistCount As Long, _  
ByRef SetBackDistances As Double, _  
ByVal PointCount As Long, _  
ByRef PointRadiusArray As Double _  
) As Long
```

SOLIDWORKS Type Library

IFeatureReferenceCurve Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IFeatureReferenceCurve( _  
    ByVal NumOfCurves As Long, _  
    ByVal BaseCurves As Curve, _  
    ByVal Merge As Boolean, _  
    ByVal FromFileName As String, _  
    ByRef ErrorCode As Long _  
) As ReferenceCurve
```

SOLIDWORKS Type Library

IFirstFeature Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IFirstFeature() As Feature
```

SOLIDWORKS Type Library

IGet3rdPartyStorage Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGet3rdPartyStorage( _  
    ByVal StringIn As String, _  
    ByVal IsStoring As Boolean _  
) As Unknown
```

SOLIDWORKS Type Library

IGetActiveConfiguration Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetActiveConfiguration() As Configuration
```

SOLIDWORKS Type Library

IGetActiveSketch Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetActiveSketch() As Sketch
```

SOLIDWORKS Type Library

IGetActiveSketch2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetActiveSketch2() As Sketch
```

SOLIDWORKS Type Library

IGetAngularUnits Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetAngularUnits() As Integer
```

SOLIDWORKS Type Library

IGetColorTable Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetColorTable() As ColorTable
```

SOLIDWORKS Type Library

IGetConfigurationByName Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetConfigurationByName( _  
    ByVal Name As String _  
) As Configuration
```

SOLIDWORKS Type Library

IGetConfigurationNames Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetConfigurationNames( _  
    ByRef Count As Long _  
) As String
```

SOLIDWORKS Type Library

IGetCoordinateSystemXformByName Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetCoordinateSystemXformByName( _  
    ByVal NameIn As String _  
) As Double
```

SOLIDWORKS Type Library

IGetCustomInfoNames Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetCustomInfoNames() As String
```

SOLIDWORKS Type Library

IGetCustomInfoNames2 Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetCustomInfoNames2( _  
    ByVal Configuration As String _  
) As String
```

SOLIDWORKS Type Library

IGetDependencies Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetDependencies( _  
    ByVal Traverseflag As Long, _  
    ByVal Searchflag As Long _  
    ) As String
```

SOLIDWORKS Type Library

IGetDependencies2 Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function IGetDependencies2( _  
    ByVal Traverseflag As Boolean, _  
    ByVal Searchflag As Boolean, _  
    ByVal AddReadOnlyInfo As Boolean _  
    ) As String
```

SOLIDWORKS Type Library

IGetDesignTable Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function IGetDesignTable() As DesignTable
```

SOLIDWORKS Type Library

IGetDetailingDefaults Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function IGetDetailingDefaults() As DetailingDefaults
```

SOLIDWORKS Type Library

IGetEntityName Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function IGetEntityName( _  
    ByVal Entity As Entity _  
    ) As String
```

SOLIDWORKS Type Library

IGetFirstAnnotation Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function IGetFirstAnnotation() As Annotation
```

SOLIDWORKS Type Library

IGetFirstAnnotation2 Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function IGetFirstAnnotation2() As Annotation
```

SOLIDWORKS Type Library

IGetFirstModelView Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function IGetFirstModelView() As ModelView
```

SOLIDWORKS Type Library

IGetLayerManager Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function IGetLayerManager() As LayerMgr
```

SOLIDWORKS Type Library

IGetLines Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function IGetLines() As Double
```

SOLIDWORKS Type Library

IGetMassProperties Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function IGetMassProperties( _  
    ByRef MPropsData As Double _  
    ) As Boolean
```

SOLIDWORKS Type Library

IGetMassProperties2 Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function IGetMassProperties2( _  
    ByRef Status As Long _  
    ) As Double
```

SOLIDWORKS Type Library

IGetModelViewNames Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function IGetModelViewNames() As String
```

SOLIDWORKS Type Library

IGetNext Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function IGetNext() As ModelDoc2
```

SOLIDWORKS Type Library

IGetNumDependencies Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function IGetNumDependencies( _  
    ByVal Traverseflag As Long, _  
    ByVal Searchflag As Long _  
    ) As Long
```

SOLIDWORKS Type Library

IGetNumDependencies2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetNumDependencies2( _  
    ByVal Traverseflag As Boolean, _  
    ByVal Searchflag As Boolean, _  
    ByVal AddReadOnlyInfo As Boolean _  
    ) As Long
```

SOLIDWORKS Type Library

IGetRayIntersectionsPoints Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetRayIntersectionsPoints() As Double
```

SOLIDWORKS Type Library

IGetRayIntersectionsTopology Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetRayIntersectionsTopology() As Unknown
```

SOLIDWORKS Type Library

IGetStandardViewRotation Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetStandardViewRotation( _  
    ByVal ViewId As Long _  
    ) As Double
```

SOLIDWORKS Type Library

IGetUnits Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetUnits() As Integer
```

SOLIDWORKS Type Library

IGetUserPreferenceTextFormat Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetUserPreferenceTextFormat( _  
    ByVal UserPreferenceValue As Long _  
    ) As TextFormat
```

SOLIDWORKS Type Library

IGetUserUnit Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetUserUnit( _  
    ByVal UnitType As Long _  
    ) As UserUnit
```

SOLIDWORKS Type Library

IGetVersionHistoryCount Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetVersionHistoryCount() As Integer
```

SOLIDWORKS Type Library

IInsertBOMBalloon2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IInsertBOMBalloon2( _  
    ByVal Style As Long, _  
    ByVal Size As Long, _  
    ByVal UpperTextStyle As Long, _  
    ByVal UpperText As String, _  
    ByVal LowerTextStyle As Long, _  
    ByVal LowerText As String _  
    ) As Note
```

SOLIDWORKS Type Library

IInsertDatumTag2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IInsertDatumTag2() As DatumTag
```

SOLIDWORKS Type Library

IInsertGtol Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IInsertGtol() As Gtol
```

SOLIDWORKS Type Library

IInsertMacroFeature Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IInsertMacroFeature( _  
    ByVal CmdFile As String, _  
    ByVal CmdModule As String, _  
    ByVal CmdProcedure As String, _  
    ByVal ParamCount As Long, _  
    ByRef ParamNames As String, _  
    ByRef ParamTypes As Long, _  
    ByRef ParamValues As String, _  
    ByVal PmFile As String, _  
    ByVal PmModule As String, _  
    ByVal PmProcedure As String _  
    ) As Feature
```

SOLIDWORKS Type Library

InsertMidSurfaceExt Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IInsertMidSurfaceExt( _  
    ByVal Placement As Double, _  
    ByVal KnitFlag As Boolean _  
) As MidSurface2
```

SOLIDWORKS Type Library

InsertNote Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IInsertNote( _  
    ByVal Text As String _  
) As Note
```

SOLIDWORKS Type Library

InsertProjectedSketch2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IInsertProjectedSketch2( _  
    ByVal Reverse As Long _  
) As Feature
```

SOLIDWORKS Type Library

InsertSheetMetalEdgeFlange Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IInsertSheetMetalEdgeFlange( _  
    ByVal FlangeEdge As Edge, _  
    ByVal SketchFeat As Feature, _  
    ByVal BooleanOptions As Long, _  
    ByVal DAngle As Double, _  
    ByVal DRadius As Double, _  
    ByVal BendPosition As Long, _  
    ByVal DOffsetDist As Double, _  
    ByVal ReliefType As Long, _  
    ByVal DReliefRatio As Double, _  
    ByVal DReliefWidth As Double, _  
    ByVal DReliefDepth As Double _  
) As Feature
```

SOLIDWORKS Type Library

InsertSketchForEdgeFlange Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IInsertSketchForEdgeFlange( _  
    ByVal FlangeEdge As Edge, _  
    ByVal DAngle As Double, _  
    ByVal FlipDir As Boolean _  
) As Feature
```

SOLIDWORKS Type Library

InsertSketchText Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IInsertSketchText( _
    ByVal Ptx As Double, _
    ByVal Pty As Double, _
    ByVal Ptz As Double, _
    ByVal Text As String, _
    ByVal Alignment As Long, _
    ByVal FlipDirection As Long, _
    ByVal HorizontalMirror As Long, _
    ByVal WidthFactor As Long, _
    ByVal SpaceBetweenChars As Long _
) As SketchText
```

SOLIDWORKS Type Library

IInsertWeldSymbol3 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IInsertWeldSymbol3() As WeldSymbol1
```

SOLIDWORKS Type Library

ILightSourcePropertyValues Property (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property ILightSourcePropertyValues( _
    ByVal ID As Long _
) As Double
```

SOLIDWORKS Type Library

IListAuxiliaryExternalFileReferences Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub IListAuxiliaryExternalFileReferences( _
    ByVal NumRefs As Long, _
    ByRef Feature As String, _
    ByRef ExternalFileName As String _
)
```

SOLIDWORKS Type Library

IListExternalFileReferences Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IListExternalFileReferences( _
    ByVal UseSearchRules As Boolean, _
    ByVal NumRefs As Long _
) As String
```

SOLIDWORKS Type Library

IListExternalFileReferences2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub IListExternalFileReferences2( _
    ByVal NumRefs As Long, _
    ByRef ModelPathName As String, _
    ByRef CompPathName As String, _
    ByRef Feature As String, _
    ByRef DataType As String, _
    ByRef Status As Long, _
```

```
ByRef RefEntity As String, _  
ByRef FeatComp As String _  
)
```

SOLIDWORKS Type Library

IMaterialPropertyValues Property (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property IMaterialPropertyValues As Double
```

SOLIDWORKS Type Library

IMultiSelectByRay Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IMultiSelectByRay( _  
    ByRef PointIn As Double, _  
    ByRef VectorIn As Double, _  
    ByVal RadiusIn As Double, _  
    ByVal TypeWanted As Long, _  
    ByVal Append As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

Insert3DSketch Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub Insert3DSketch()
```

SOLIDWORKS Type Library

Insert3DSketch2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub Insert3DSketch2( _  
    ByVal UpdateEditRebuild As Boolean _  
)
```

SOLIDWORKS Type Library

Insert3DSplineCurve Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub Insert3DSplineCurve( _  
    ByVal CurveClosed As Boolean _  
)
```

SOLIDWORKS Type Library

InsertAxis Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertAxis() As Boolean
```

SOLIDWORKS Type Library

InsertAxis2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertAxis2( _  
    ByVal AutoSize As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

InsertBendTableEdit Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertBendTableEdit()
```

SOLIDWORKS Type Library

InsertBendTableNew Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertBendTableNew( _  
    ByVal FileName As String, _  
    ByVal Units As String, _  
    ByVal Type As String _  
) As Boolean
```

SOLIDWORKS Type Library

InsertBendTableOpen Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertBendTableOpen( _  
    ByVal FileName As String _  
) As Boolean
```

SOLIDWORKS Type Library

InsertBkgImage Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertBkgImage( _  
    ByVal NewName As String _  
)
```

SOLIDWORKS Type Library

InsertBOMBalloon Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertBOMBalloon()
```

SOLIDWORKS Type Library

InsertBOMBalloon2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertBOMBalloon2( _  
    ByVal Style As Long, _  
    ByVal Size As Long, _  
    ByVal UpperTextStyle As Long, _  
    ByVal UpperText As String, _
```

```
ByVal LowerTextStyle As Long, _  
ByVal LowerText As String _  
) As Object
```

SOLIDWORKS Type Library

InsertCompositeCurve Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertCompositeCurve() As Boolean
```

SOLIDWORKS Type Library

InsertConnectionPoint Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertConnectionPoint()
```

SOLIDWORKS Type Library

InsertCoordinateSystem Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertCoordinateSystem( _  
ByVal XFlippedIn As Boolean, _  
ByVal YFlippedIn As Boolean, _  
ByVal ZFlippedIn As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

InsertCosmeticThread Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertCosmeticThread( _  
ByVal Type As Integer, _  
ByVal Depth As Double, _  
ByVal Length As Double, _  
ByVal Note As String _  
)
```

SOLIDWORKS Type Library

InsertCurveFile Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertCurveFile( _  
ByVal FileName As String _  
) As Boolean
```

SOLIDWORKS Type Library

InsertCurveFileBegin Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertCurveFileBegin()
```

SOLIDWORKS Type Library

InsertCurveFileEnd Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertCurveFileEnd() As Boolean
```

SOLIDWORKS Type Library

InsertCurveFilePoint Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertCurveFilePoint( _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
) As Boolean
```

SOLIDWORKS Type Library

InsertCutBlend Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertCutBlend( _  
    ByVal Closed As Boolean _  
)
```

SOLIDWORKS Type Library

InsertCutBlend2 Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertCutBlend2( _  
    ByVal Closed As Boolean, _  
    ByVal KeepTangency As Boolean, _  
    ByVal ForceNonRational As Boolean _  
)
```

SOLIDWORKS Type Library

InsertCutBlend3 Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertCutBlend3( _  
    ByVal Closed As Boolean, _  
    ByVal KeepTangency As Boolean, _  
    ByVal ForceNonRational As Boolean, _  
    ByVal TessToleranceFactor As Double, _  
    ByVal StartMatchingType As Integer, _  
    ByVal EndMatchingType As Integer _  
)
```

SOLIDWORKS Type Library

InsertCutBlend4 Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertCutBlend4( _  
    ByVal Closed As Boolean, _  
    ByVal KeepTangency As Boolean, _  
    ByVal ForceNonRational As Boolean, _  
    ByVal TessToleranceFactor As Double, _  
    ByVal StartMatchingType As Integer, _  
    ByVal EndMatchingType As Integer, _
```

```
ByVal IsThinBody As Boolean, _  
ByVal Thickness1 As Double, _  
ByVal Thickness2 As Double, _  
ByVal ThinType As Integer _  
)
```

SOLIDWORKS Type Library

InsertCutSurface Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertCutSurface( _  
    ByVal Flip As Boolean, _  
    ByVal KeepPieceIndex As Long _  
)
```

SOLIDWORKS Type Library

InsertCutSwept Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertCutSwept( _  
    ByVal Propagate As Boolean, _  
    ByVal Alignment As Boolean, _  
    ByVal KeepNormalConstant As Boolean _  
)
```

SOLIDWORKS Type Library

InsertCutSwept2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertCutSwept2( _  
    ByVal Propagate As Boolean, _  
    ByVal Alignment As Boolean, _  
    ByVal TwistCtrlOption As Integer, _  
    ByVal KeepTangency As Boolean, _  
    ByVal ForceNonRational As Boolean _  
)
```

SOLIDWORKS Type Library

InsertCutSwept3 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertCutSwept3( _  
    ByVal Propagate As Boolean, _  
    ByVal Alignment As Boolean, _  
    ByVal TwistCtrlOption As Integer, _  
    ByVal KeepTangency As Boolean, _  
    ByVal ForceNonRational As Boolean, _  
    ByVal StartMatchingType As Integer, _  
    ByVal EndMatchingType As Integer _  
)
```

SOLIDWORKS Type Library

InsertCutSwept4 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertCutSwept4( _  
    ByVal Propagate As Boolean, _
```

```
ByVal Alignment As Boolean, _  
ByVal TwistCtrlOption As Integer, _  
ByVal KeepTangency As Boolean, _  
ByVal ForceNonRational As Boolean, _  
ByVal StartMatchingType As Integer, _  
ByVal EndMatchingType As Integer, _  
ByVal IsThinBody As Boolean, _  
ByVal Thickness1 As Double, _  
ByVal Thickness2 As Double, _  
ByVal ThinType As Integer _  
)
```

SOLIDWORKS Type Library

InsertDatumTag2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertDatumTag2() As Object
```

SOLIDWORKS Type Library

InsertDatumTargetSymbol Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertDatumTargetSymbol( _  
    ByVal Datum1 As String, _  
    ByVal Datum2 As String, _  
    ByVal Datum3 As String, _  
    ByVal AreaStyle As Integer, _  
    ByVal AreaOutside As Boolean, _  
    ByVal Value1 As Double, _  
    ByVal Value2 As Double, _  
    ByVal ValueStr1 As String, _  
    ByVal ValueStr2 As String, _  
    ByVal ArrowsSmart As Boolean, _  
    ByVal ArrowStyle As Integer, _  
    ByVal LeaderLineStyle As Integer, _  
    ByVal LeaderBent As Boolean, _  
    ByVal ShowArea As Boolean, _  
    ByVal ShowSymbol As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

InsertDeleteFace Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertDeleteFace()
```

SOLIDWORKS Type Library

InsertDeleteFace2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertDeleteFace2( _  
    ByVal Refill As Long _  
) As Boolean
```

SOLIDWORKS Type Library

InsertDeleteHole Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertDeleteHole()
```

SOLIDWORKS Type Library

InsertDome Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertDome( _  
    ByVal Height As Double, _  
    ByVal ReverseDir As Boolean, _  
    ByVal DoEllipticSurface As Boolean _  
)
```

SOLIDWORKS Type Library

InsertExtendSurface Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertExtendSurface( _  
    ByVal ExtendLinear As Boolean, _  
    ByVal EndCondition As Long, _  
    ByVal Distance As Double _  
)
```

SOLIDWORKS Type Library

InsertFamilyTableEdit Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertFamilyTableEdit()
```

SOLIDWORKS Type Library

InsertFamilyTableNew Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertFamilyTableNew()
```

SOLIDWORKS Type Library

InsertFamilyTableOpen Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertFamilyTableOpen( _  
    ByVal FileName As String _  
) As Boolean
```

SOLIDWORKS Type Library

InsertFeatureReplaceFace Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertFeatureReplaceFace()
```

SOLIDWORKS Type Library

InsertFeatureShell Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertFeatureShell( _  
    ByVal Thickness As Double, _  
    ByVal Outward As Boolean _  
)
```

SOLIDWORKS Type Library

InsertFeatureShellAddThickness Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Sub InsertFeatureShellAddThickness( _  
    ByVal Thickness As Double _  
)
```

SOLIDWORKS Type Library

InsertFramePoint Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Sub InsertFramePoint( _  
    ByVal Xx As Double, _  
    ByVal Yy As Double, _  
    ByVal Zz As Double _  
)
```

SOLIDWORKS Type Library

InsertGtol Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Function InsertGtol() As Object
```

SOLIDWORKS Type Library

InsertHatchedFace Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Sub InsertHatchedFace()
```

SOLIDWORKS Type Library

InsertHelix Method (ModelDoc2)



Visual Basic for Applications (VBA)

```
Public Sub InsertHelix( _  
    ByVal Reversed As Boolean, _  
    ByVal Clockwised As Boolean, _  
    ByVal Tapered As Boolean, _  
    ByVal Outward As Boolean, _  
    ByVal Helixdef As Long, _  
    ByVal Height As Double, _  
    ByVal Pitch As Double, _  
    ByVal Revolution As Double, _  
    ByVal TaperAngle As Double, _  
    ByVal Startangle As Double _  
)
```

SOLIDWORKS Type Library

InsertLibraryFeature Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertLibraryFeature( _  
    ByVal LibFeatPartNameIn As String _  
)
```

SOLIDWORKS Type Library

InsertLoftRefSurface Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertLoftRefSurface( _  
    ByVal Closed As Boolean, _  
    ByVal KeepTangency As Boolean, _  
    ByVal ForceNonRational As Boolean _  
)
```

SOLIDWORKS Type Library

InsertLoftRefSurface2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertLoftRefSurface2( _  
    ByVal Closed As Boolean, _  
    ByVal KeepTangency As Boolean, _  
    ByVal ForceNonRational As Boolean, _  
    ByVal TessToleranceFactor As Double, _  
    ByVal StartMatchingType As Integer, _  
    ByVal EndMatchingType As Integer _  
)
```

SOLIDWORKS Type Library

InsertMacroFeature Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertMacroFeature( _  
    ByVal CmdFile As String, _  
    ByVal CmdModule As String, _  
    ByVal CmdProcedure As String, _  
    ByVal ParamNames As Variant, _  
    ByVal ParamTypes As Variant, _  
    ByVal ParamValues As Variant, _  
    ByVal PmFile As String, _  
    ByVal PmModule As String, _  
    ByVal PmProcedure As String _  
) As Object
```

SOLIDWORKS Type Library

InsertMfDraft Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertMfDraft( _  
    ByVal Angle As Double, _  
    ByVal FlipDir As Boolean, _  
    ByVal IsEdgeDraft As Boolean, _  
    ByVal PropType As Long _  
)
```

SOLIDWORKS Type Library

InsertMfDraft2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertMfDraft2( _  
    ByVal Angle As Double, _  
    ByVal FlipDir As Boolean, _  
    ByVal IsEdgeDraft As Boolean, _  
    ByVal PropType As Long, _  
    ByVal StepDraft As Boolean _  
)
```

SOLIDWORKS Type Library

InsertMidSurfaceExt Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertMidSurfaceExt( _  
    ByVal Placement As Double, _  
    ByVal KnitFlag As Boolean _  
) As Object
```

SOLIDWORKS Type Library

InsertNewNote3 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertNewNote3( _  
    ByVal UpperText As String, _  
    ByVal NoLeader As Boolean, _  
    ByVal BentLeader As Boolean, _  
    ByVal ArrowStyle As Integer, _  
    ByVal LeaderSide As Integer, _  
    ByVal Angle As Double, _  
    ByVal BalloonStyle As Integer, _  
    ByVal BalloonFit As Integer, _  
    ByVal SmartArrow As Boolean _  
)
```

SOLIDWORKS Type Library

InsertNote Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertNote( _  
    ByVal Text As String _  
) As Object
```

SOLIDWORKS Type Library

InsertObject Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertObject()
```

SOLIDWORKS Type Library

InsertObjectFromFile Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertObjectFromFile( _  
    ByVal FilePath As String, _  
    ByVal CreateLink As Boolean, _
```

```
ByVal Xx As Double, _  
ByVal Yy As Double, _  
ByVal Zz As Double _  
) As Boolean
```

SOLIDWORKS Type Library

InsertOffsetSurface Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertOffsetSurface( _  
    ByVal Thickness As Double, _  
    ByVal Reverse As Boolean _  
)
```

SOLIDWORKS Type Library

InsertPlanarRefSurface Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertPlanarRefSurface() As Boolean
```

SOLIDWORKS Type Library

InsertPoint Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertPoint()
```

SOLIDWORKS Type Library

InsertProjectedSketch Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertProjectedSketch()
```

SOLIDWORKS Type Library

InsertProjectedSketch2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertProjectedSketch2( _  
    ByVal Reverse As Long _  
) As Object
```

SOLIDWORKS Type Library

InsertProtrusionBlend Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertProtrusionBlend( _  
    ByVal Closed As Boolean _  
)
```

SOLIDWORKS Type Library

InsertProtrusionBlend2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertProtrusionBlend2( _  
    ByVal Closed As Boolean, _  
    ByVal KeepTangency As Boolean, _  
    ByVal ForceNonRational As Boolean _  
)
```

SOLIDWORKS Type Library

InsertProtrusionBlend3 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertProtrusionBlend3( _  
    ByVal Closed As Boolean, _  
    ByVal KeepTangency As Boolean, _  
    ByVal ForceNonRational As Boolean, _  
    ByVal TessToleranceFactor As Double, _  
    ByVal StartMatchingType As Integer, _  
    ByVal EndMatchingType As Integer _  
)
```

SOLIDWORKS Type Library

InsertProtrusionBlend4 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertProtrusionBlend4( _  
    ByVal Closed As Boolean, _  
    ByVal KeepTangency As Boolean, _  
    ByVal ForceNonRational As Boolean, _  
    ByVal TessToleranceFactor As Double, _  
    ByVal StartMatchingType As Integer, _  
    ByVal EndMatchingType As Integer, _  
    ByVal IsThinBody As Boolean, _  
    ByVal Thickness1 As Double, _  
    ByVal Thickness2 As Double, _  
    ByVal ThinType As Integer _  
)
```

SOLIDWORKS Type Library

InsertProtrusionSwept Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertProtrusionSwept( _  
    ByVal Propagate As Boolean, _  
    ByVal Alignment As Boolean, _  
    ByVal KeepNormalConstant As Boolean _  
)
```

SOLIDWORKS Type Library

InsertProtrusionSwept2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertProtrusionSwept2( _  
    ByVal Propagate As Boolean, _  
    ByVal Alignment As Boolean, _  
    ByVal TwistCtrlOption As Integer, _  
    ByVal KeepTangency As Boolean, _  
    ByVal ForceNonRational As Boolean _  
)
```

InsertProtrusionSwept3 Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertProtrusionSwept3( _  
    ByVal Propagate As Boolean, _  
    ByVal Alignment As Boolean, _  
    ByVal TwistCtrlOption As Integer, _  
    ByVal KeepTangency As Boolean, _  
    ByVal ForceNonRational As Boolean, _  
    ByVal StartMatchingType As Integer, _  
    ByVal EndMatchingType As Integer _  
)
```

InsertProtrusionSwept4 Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertProtrusionSwept4( _  
    ByVal Propagate As Boolean, _  
    ByVal Alignment As Boolean, _  
    ByVal TwistCtrlOption As Integer, _  
    ByVal KeepTangency As Boolean, _  
    ByVal ForceNonRational As Boolean, _  
    ByVal StartMatchingType As Integer, _  
    ByVal EndMatchingType As Integer, _  
    ByVal IsThinBody As Boolean, _  
    ByVal Thickness1 As Double, _  
    ByVal Thickness2 As Double, _  
    ByVal ThinType As Integer _  
)
```

InsertRadiateSurface Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertRadiateSurface( _  
    ByVal Distance As Double, _  
    ByVal FlipDir As Boolean, _  
    ByVal TangentPropagate As Boolean _  
)
```

InsertRefPoint Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertRefPoint() As Boolean
```

InsertRevolvedRefSurface Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertRevolvedRefSurface( _  
    ByVal Angle As Double, _  
    ByVal ReverseDir As Boolean, _  
    ByVal Angle2 As Double, _
```

```
ByVal RevType As Integer _  
)
```

SOLIDWORKS Type Library

InsertRib Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertRib( _  
    ByVal Is2Sided As Boolean, _  
    ByVal ReverseThicknessDir As Boolean, _  
    ByVal Thickness As Double, _  
    ByVal ReferenceEdgeIndex As Long, _  
    ByVal ReverseMaterialDir As Boolean, _  
    ByVal IsDrafted As Boolean, _  
    ByVal DraftOutward As Boolean, _  
    ByVal DraftAngle As Double _  
)
```

SOLIDWORKS Type Library

InsertRib2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertRib2( _  
    ByVal Is2Sided As Boolean, _  
    ByVal ReverseThicknessDir As Boolean, _  
    ByVal Thickness As Double, _  
    ByVal ReferenceEdgeIndex As Long, _  
    ByVal ReverseMaterialDir As Boolean, _  
    ByVal IsDrafted As Boolean, _  
    ByVal DraftOutward As Boolean, _  
    ByVal DraftAngle As Double, _  
    ByVal IsNormToSketch As Boolean _  
)
```

SOLIDWORKS Type Library

InsertRip Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertRip( _  
    ByVal Gap As Double _  
)
```

SOLIDWORKS Type Library

InsertRoutePoint Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertRoutePoint()
```

SOLIDWORKS Type Library

InsertScale Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertScale( _  
    ByVal ScaleFactor_x As Double, _  
    ByVal ScaleFactor_y As Double, _  
    ByVal ScaleFactor_z As Double, _  
    ByVal IsUniform As Boolean, _
```

```
    ByVal ScaleType As Integer _  
)
```

SOLIDWORKS Type Library

InsertSewRefSurface Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertSewRefSurface()
```

SOLIDWORKS Type Library

InsertShape Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function InsertShape( _  
    ByVal PressureOn As Long, _  
    ByVal TangentsOn As Long, _  
    ByVal PressureGain As Double, _  
    ByVal TangentGain As Double, _  
    ByVal CurveSpringGain As Double, _  
    ByVal Alpha As Double, _  
    ByVal Beta As Double, _  
    ByVal Gamma As Double, _  
    ByVal Delta As Double, _  
    ByVal Degree As Long, _  
    ByVal Split As Long, _  
    ByVal Tuning As Long _  
) As Long
```

SOLIDWORKS Type Library

InsertSheetMetal3dBend Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub InsertSheetMetal3dBend( _  
    ByVal Angle As Double, _  
    ByVal Radius As Double, _  
    ByVal FlipDir As Boolean, _  
    ByVal BendPos As Integer _  
)
```