

SOLIDWORKS API (VB6 COM) — Reference (63/102): ModelDoc2 (part 5 of 5)

SOLIDWORKS API Documentation (converted from CHM)

ModelDoc2 (part 5 of 5) (Type)

SOLIDWORKS Type Library

SketchConstrainParallel Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchConstrainParallel()
```

SOLIDWORKS Type Library

SketchConstrainPerp Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchConstrainPerp()
```

SOLIDWORKS Type Library

SketchConstrainTangent Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchConstrainTangent()
```

SOLIDWORKS Type Library

SketchConstraintsDel Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchConstraintsDel( _  
    ByVal ConstrInd As Long, _  
    ByVal IdStr As String _  
)
```

SOLIDWORKS Type Library

SketchConstraintsDelAll Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchConstraintsDelAll()
```

SOLIDWORKS Type Library

SketchConvertIsoCurves Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchConvertIsoCurves( _  
    ByVal PercentRatio As Double, _  
    ByVal VORuDir As Boolean, _  
    ByVal DoConstrain As Boolean, _  
    ByVal SkipHoles As Boolean _  
)
```

SOLIDWORKS Type Library

SketchFillet Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchFillet( _  
    ByVal Rad As Double _  
)
```

SOLIDWORKS Type Library

SketchFillet1 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchFillet1( _  
    ByVal Rad As Double _  
)
```

SOLIDWORKS Type Library

SketchFillet2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SketchFillet2( _  
    ByVal Rad As Double, _  
    ByVal ConstrainedCorners As Integer _  
) As Boolean
```

SOLIDWORKS Type Library

SketchManager Property (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property SketchManager As SketchManager
```

SOLIDWORKS Type Library

SketchMirror Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchMirror()
```

SOLIDWORKS Type Library

SketchModifyFlip Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchModifyFlip( _  
    ByVal AxisFlag As Integer _  
)
```

SOLIDWORKS Type Library

SketchModifyRotate Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchModifyRotate( _  
    ByVal CenterX As Double, _  
    ByVal CenterY As Double, _  
    ByVal Angle As Double _  
)
```

SOLIDWORKS Type Library

SketchModifyScale Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SketchModifyScale( _  
    ByVal ScaleFactor As Double _  
) As Boolean
```

SOLIDWORKS Type Library

SketchModifyTranslate Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchModifyTranslate( _  
    ByVal StartX As Double, _  
    ByVal StartY As Double, _  
    ByVal EndX As Double, _  
    ByVal EndY As Double _  
)
```

SOLIDWORKS Type Library

SketchOffset Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchOffset( _  
    ByVal Offset As Double, _  
    ByVal ContourMode As Boolean _  
)
```

SOLIDWORKS Type Library

SketchOffset2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SketchOffset2( _  
    ByVal Offset As Double, _  
    ByVal BothDirections As Boolean, _  
    ByVal Chain As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

SketchOffsetEdges Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchOffsetEdges( _  
    ByVal Val As Double _  
)
```

SOLIDWORKS Type Library

SketchOffsetEntities Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchOffsetEntities( _  
    ByVal Offset As Double, _  
    ByVal Flip As Boolean _  
)
```

SketchOffsetEntities2 Method (ModelDoc2) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function SketchOffsetEntities2( _  
    ByVal Offset As Double, _  
    ByVal BothDirections As Boolean, _  
    ByVal Chain As Boolean _  
    ) As Boolean
```

SketchParabola Method (ModelDoc2) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub SketchParabola( _  
    ByVal Val1 As Double, _  
    ByVal Val2 As Double, _  
    ByVal Z1 As Double, _  
    ByVal Val3 As Double, _  
    ByVal Val4 As Double, _  
    ByVal Z2 As Double, _  
    ByVal Val5 As Double, _  
    ByVal Val6 As Double, _  
    ByVal Z3 As Double, _  
    ByVal Val7 As Double, _  
    ByVal Val8 As Double, _  
    ByVal Z4 As Double _  
    )
```

SketchPoint Method (ModelDoc2) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub SketchPoint( _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
    )
```

SketchPolygon Method (ModelDoc2) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function SketchPolygon( _  
    ByVal XCenter As Double, _  
    ByVal YCenter As Double, _  
    ByVal XEdge As Double, _  
    ByVal YEdge As Double, _  
    ByVal NSides As Integer, _  
    ByVal BIscribed As Boolean _  
    ) As Boolean
```

SketchRectangle Method (ModelDoc2) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub SketchRectangle( _  
    ByVal Val1 As Double, _  
    ByVal Val2 As Double, _  
    ByVal Z1 As Double, _  
    ByVal Val3 As Double, _  
    ByVal Val4 As Double, _  
    ByVal Z2 As Double, _  
    ByVal Val5 As Boolean _  
)
```

SOLIDWORKS Type Library

SketchRectangleAtAnyAngle Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchRectangleAtAnyAngle( _  
    ByVal Val1 As Double, _  
    ByVal Val2 As Double, _  
    ByVal Z1 As Double, _  
    ByVal Val3 As Double, _  
    ByVal Val4 As Double, _  
    ByVal Z2 As Double, _  
    ByVal Val3x As Double, _  
    ByVal Val3y As Double, _  
    ByVal Z3 As Double, _  
    ByVal Val5 As Boolean _  
)
```

SOLIDWORKS Type Library

SketchSpline Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchSpline( _  
    ByVal MorePts As Long, _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
)
```

SOLIDWORKS Type Library

SketchSplineByEqnParams Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SketchSplineByEqnParams( _  
    ByVal ParamsIn As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

SketchSplineByEqnParams2 Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SketchSplineByEqnParams2( _  
    ByVal ParamsIn As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

SketchTangentArc Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchTangentArc()
```

SOLIDWORKS Type Library

SketchTrim Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchTrim( _  
    ByVal Op As Long, _  
    ByVal SelEnd As Long, _  
    ByVal X As Double, _  
    ByVal Y As Double _  
)
```

SOLIDWORKS Type Library

SketchUndo Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchUndo()
```

SOLIDWORKS Type Library

SketchUseEdge Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchUseEdge()
```

SOLIDWORKS Type Library

SketchUseEdge2 Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function SketchUseEdge2( _  
    ByVal Chain As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

SketchUseEdgeCtrline Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub SketchUseEdgeCtrline()
```

SOLIDWORKS Type Library

SkToolsAutoConstr Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub SkToolsAutoConstr()
```

SOLIDWORKS Type Library

SplitClosedSegment Method (ModelDoc2)

 Syntax

Visual Basic for Applications (VBA)

```
Public Sub SplitClosedSegment( _  
    ByVal X0 As Double, _  
    ByVal Y0 As Double, _  
    ByVal Z0 As Double, _  
    ByVal X1 As Double, _  
    ByVal Y1 As Double, _  
    ByVal Z1 As Double _  
)
```

SOLIDWORKS Type Library

SplitOpenSegment Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SplitOpenSegment( _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double _  
)
```

SOLIDWORKS Type Library

SummaryInfo Property (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property SummaryInfo( _  
    ByVal FieldId As Long _  
) As String
```

SOLIDWORKS Type Library

Toolbars Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub Toolbars( _  
    ByVal M As Boolean, _  
    ByVal Vw As Boolean, _  
    ByVal SkMain As Boolean, _  
    ByVal Sk As Boolean, _  
    ByVal Feat As Boolean, _  
    ByVal Constr As Boolean, _  
    ByVal Macro As Boolean _  
)
```

SOLIDWORKS Type Library

ToolsConfiguration Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ToolsConfiguration()
```

SOLIDWORKS Type Library

ToolsDistance Method (ModelDoc2)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ToolsDistance()
```

SOLIDWORKS Type Library

ToolsGrid Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ToolsGrid()
```

SOLIDWORKS Type Library

ToolsMacro Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ToolsMacro()
```

SOLIDWORKS Type Library

ToolsMassProps Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ToolsMassProps()
```

SOLIDWORKS Type Library

ToolsSketchScale Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ToolsSketchScale()
```

SOLIDWORKS Type Library

ToolsSketchTranslate Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ToolsSketchTranslate()
```

SOLIDWORKS Type Library

UnBlankRefGeom Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub UnBlankRefGeom()
```

SOLIDWORKS Type Library

UnblankSketch Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub UnblankSketch()
```

SOLIDWORKS Type Library

UnderiveSketch Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub UnderiveSketch()
```

SOLIDWORKS Type Library

UnLock Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub UnLock()
```

SOLIDWORKS Type Library

UnlockAllExternalReferences Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub UnlockAllExternalReferences()
```

SOLIDWORKS Type Library

UnlockFramePoint Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub UnlockFramePoint()
```

SOLIDWORKS Type Library

UserFavors Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub UserFavors()
```

SOLIDWORKS Type Library

UserPreferences Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub UserPreferences()
```

SOLIDWORKS Type Library

VersionHistory Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Function VersionHistory() As Variant
```

SOLIDWORKS Type Library

ViewConstraint Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewConstraint()
```

SOLIDWORKS Type Library

ViewDispCoordinateSystems Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDispCoordinateSystems()
```

SOLIDWORKS Type Library

ViewDisplayCurvature Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDisplayCurvature()
```

SOLIDWORKS Type Library

ViewDisplayFaceted Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDisplayFaceted()
```

SOLIDWORKS Type Library

ViewDisplayHiddengreyed Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDisplayHiddengreyed()
```

SOLIDWORKS Type Library

ViewDisplayHiddenremoved Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDisplayHiddenremoved()
```

SOLIDWORKS Type Library

ViewDisplayShaded Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDisplayShaded()
```

SOLIDWORKS Type Library

ViewDisplayWireframe Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDisplayWireframe()
```

SOLIDWORKS Type Library

ViewDispOrigins Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDispOrigins()
```

SOLIDWORKS Type Library

ViewDispRefaxes Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDispRefaxes()
```

SOLIDWORKS Type Library

ViewDispRefplanes Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDispRefplanes()
```

SOLIDWORKS Type Library

ViewDispRefPoints Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDispRefPoints()
```

SOLIDWORKS Type Library

ViewDispTempRefaxes Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewDispTempRefaxes()
```

SOLIDWORKS Type Library

ViewOglShading Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewOglShading()
```

SOLIDWORKS Type Library

ViewOrientationUndo Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewOrientationUndo()
```

SOLIDWORKS Type Library

ViewRotate Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotate()
```

SOLIDWORKS Type Library

ViewRotateminusx Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotateminusx()
```

SOLIDWORKS Type Library

ViewRotateminusy Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotateminusy()
```

SOLIDWORKS Type Library

ViewRotateminusz Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotateminusz()
```

SOLIDWORKS Type Library

ViewRotateplusx Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotateplusx()
```

SOLIDWORKS Type Library

ViewRotateplusy Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotateplusy()
```

SOLIDWORKS Type Library

ViewRotateplusz Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotateplusz()
```

SOLIDWORKS Type Library

ViewRotXMinusNinety Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotXMinusNinety()
```

SOLIDWORKS Type Library

ViewRotXPlusNinety Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotXPlusNinety()
```

SOLIDWORKS Type Library

ViewRotYMinusNinety Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotYMinusNinety()
```

SOLIDWORKS Type Library

ViewRotYPlusNinety Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRotYPlusNinety()
```

SOLIDWORKS Type Library

ViewRwShading Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewRwShading()
```

SOLIDWORKS Type Library

ViewTranslate Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewTranslate()
```

SOLIDWORKS Type Library

ViewTranslateminusx Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewTranslateminusx()
```

SOLIDWORKS Type Library

ViewTranslateminusy Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewTranslateminusy()
```

SOLIDWORKS Type Library

ViewTranslateplusx Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewTranslateplusx()
```

SOLIDWORKS Type Library

ViewTranslateplusy Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewTranslateplusy()
```

SOLIDWORKS Type Library

ViewZoomin Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewZoomin()
```

SOLIDWORKS Type Library

ViewZoomout Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewZoomout()
```

SOLIDWORKS Type Library

ViewZoomto Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewZoomto()
```

SOLIDWORKS Type Library

ViewZoomTo2 Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewZoomTo2( _  
    ByVal X1 As Double, _  
    ByVal Y1 As Double, _  
    ByVal Z1 As Double, _  
    ByVal X2 As Double, _  
    ByVal Y2 As Double, _  
    ByVal Z2 As Double _  
)
```

SOLIDWORKS Type Library

ViewZoomtofit Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewZoomtofit()
```

SOLIDWORKS Type Library

ViewZoomtofit2 Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewZoomtofit2()
```

SOLIDWORKS Type Library

ViewZoomToSelection Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ViewZoomToSelection()
```

SOLIDWORKS Type Library

Visible Property (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Property Visible As Boolean
```

SOLIDWORKS Type Library

WindowRedraw Method (ModelDoc2)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub WindowRedraw()
```