

SOLIDWORKS API (VB6 COM) — Reference (67/102): Modeler

SOLIDWORKS API Documentation (converted from CHM)

Modeler (Type)

SOLIDWORKS Type Library

Modeler Object

 Object Model

Modeler

CreateBodyFromBox3 (Body2)

CreateCoonsBSurface (Surface)

CreateExtrudedBody (Body2)

CreateLoftBody (Body2)

CreateLoftBody2 (Body2)

CreateSheetFromFaces (Body2)

CreateSpring (Spring)

CreateSweptBody (Body2)

CreateWireBody (Body2)

ICreateArc (Curve)

ICreateBodyFromBox (Body)

ICreateBodyFromBox2 (Body2)

ICreateBodyFromCone (Body)

ICreateBodyFromCone2 (Body2)

ICreateBodyFromCyl (Body)

ICreateBodyFromCyl2 (Body2)

ICreateBodyFromFaces (Body)

ICreateBodyFromFaces2 (Body)

ICreateBodyFromFaces3 (Body2)

ICreateBrepBody (Body)

ICreateBrepBody2 (Body2)

ICreateBrepBody3 (Body2)

ICreateBsplineCurve (Curve)

ICreateBsplineSurface (Surface)

ICreateConicalSurface (Surface)

ICreateConicalSurface2 (Surface)

ICreateCylindricalSurface (Surface)

ICreateCylindricalSurface2 (Surface)

ICreateEllipse (Curve)

ICreateExtrusionSurface (Surface)

- ICreateLine (Curve)
- ICreateLoftSurface (Surface)
- ICreateOffsetSurface (Surface)
- ICreatePCurve (Curve)
- ICreatePlanarSurface (Surface)
- ICreatePlanarSurface2 (Surface)
- ICreateRevolutionSurface (Surface)
- ICreateRuledSurface (Surface)
- ICreateSheetFromFaces (Body2)
- ICreateSheetFromSurface (Body)
- ICreateSheetFromSurface2 (Body2)
- ICreateSphericalSurface (Surface)
- ICreateSphericalSurface2 (Surface)
- ICreateSweptSurface (Surface)
- ICreateToroidalSurface (Surface)
- ICreateWireBody (Body2)
- IMakeManifoldBodies (Body2)
- IMergeCurves (Curve)
- IRestore (Body)
- IRestore2 (Body2)
- ISplitFaceOnParam (Face)
- ISplitFaceOnParam2 (Face2)
- MergeCurves (Curve)
- ProjectCurveOnSurface (Curve)
- ThickenSheet (Body2)

SOLIDWORKS Type Library

Modeler Object Members

Public Methods

-  [CheckInterference](#)
-  [CheckInterference3](#)
-  [CheckInterferenceBetweenTwoBodies](#)
-  [CopyWizardHole](#)
- [CreateArc](#)

	
	CreateBodiesFromSheets
	CreateBodiesFromSheets2
	CreateBodyFromBox
	CreateBodyFromBox3
	CreateBodyFromCone
	CreateBodyFromCyl
	CreateBodyFromFaces2
	CreateBrepBody
	CreateBrepBody3
	CreateBspineCurve
	CreateBspineSurface
	CreateConicalSurface
	CreateConicalSurface2
	CreateCoonsBSurface
	CreateCylindricalSurface
	CreateCylindricalSurface2
	CreateEllipse
	CreateExtrudedBody
	CreateExtrusionSurface
	CreateLine
	CreateLoftBody
	CreateLoftBody2
	CreateLoftSurface
	CreateOffsetSurface
	CreatePCurve
	CreatePlanarSurface
	CreatePlanarSurface2
	CreateRevolutionSurface
	CreateRuledSurface
	CreateRuledSurfaceFromEdge
	CreateSheetFromFaces
	CreateSheetFromSurface
	CreateSphericalSurface
	CreateSphericalSurface2
	CreateSpring
	CreateSweptBody
	CreateSweptSurface
	CreateToroidalSurface
	CreateWireBody
	DeleteFacesFromSheetBody
	FindTwoEdgeMaxDeviation
	GetBodyOutline
	GetBodyOutline2

	
	<u>GetInitKnitGapWidth</u>
	<u>GetManifoldBodiesCount</u>
	<u>GetToleranceValue</u>
	<u>ICheckInterference</u>
	<u>ICheckInterference2</u>
	<u>ICheckInterference3</u>
	<u>ICheckInterferenceCount</u>
	<u>ICheckInterferenceCount2</u>
	<u>ICheckInterferenceCount3</u>
	<u>ICopyWizardHole</u>
	<u>ICreateArc</u>
	<u>ICreateBodiesFromSheets</u>
	<u>ICreateBodiesFromSheets2</u>
	<u>ICreateBodyFromBox</u>
	<u>ICreateBodyFromBox2</u>
	<u>ICreateBodyFromCone</u>
	<u>ICreateBodyFromCone2</u>
	<u>ICreateBodyFromCyl</u>
	<u>ICreateBodyFromCyl2</u>
	<u>ICreateBodyFromFaces</u>
	<u>ICreateBodyFromFaces2</u>
	<u>ICreateBodyFromFaces3</u>
	<u>ICreateBrepBody</u>
	<u>ICreateBrepBody2</u>
	<u>ICreateBrepBody3</u>
	<u>ICreateBsplineCurve</u>
	<u>ICreateBsplineSurface</u>
	<u>ICreateConicalSurface</u>
	<u>ICreateConicalSurface2</u>
	<u>ICreateCylindricalSurface</u>
	<u>ICreateCylindricalSurface2</u>
	<u>ICreateEllipse</u>
	<u>ICreateExtrusionSurface</u>
	<u>ICreateLine</u>
	<u>ICreateLoftSurface</u>
	<u>ICreateOffsetSurface</u>
	<u>ICreatePCurve</u>
	<u>ICreatePlanarSurface</u>
	<u>ICreatePlanarSurface2</u>
	<u>ICreateRevolutionSurface</u>
	<u>ICreateRuledSurface</u>
	<u>ICreateRuledSurfaceFromEdge</u>
	<u>ICreateSheetFromFaces</u>


 ICreateSheetFromSurface
 ICreateSheetFromSurface2
 ICreateSphericalSurface
 ICreateSphericalSurface2
 ICreateSweptSurface
 ICreateToroidalSurface
 ICreateWireBody
 IDeleteFacesFromSheetBody
 IFindTwoEdgeMaxDeviation
 IImprintingFaces
 IImprintingFacesCount
 IImprintingFacesCount2
 IMakeManifoldBodies
 IMergeCurves
 ImprintingFaces
 IReplaceSurfaces
 IReplaceSurfaces2
 IRestore
 IRestore2
 ISplitFaceOnParam
 ISplitFaceOnParam2
 ISplitFaceOnParamCount
 ISplitFaceOnParamCount2
 MakeManifoldBodies
 MergeCurves
 ProjectCurveOnSurface
 ReplaceSurfaces
 Restore
 SetInitKnitGapWidth
 SetTolerances
 SetToleranceValue
 SplitFaceOnParam
 ThickenSheet
 UnsetTolerances

Public Properties

 GeneralTopology

SOLIDWORKS Type Library

CheckInterference Method (Modeler)

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function CheckInterference(_ ByVal <i>Body1</i> As Object, _</pre>

```
ByVal Body2 As Object, _  
ByVal CoincidentInterference As Boolean, _  
ByRef Body1InterferedFaceArray As Variant, _  
ByRef Body2InterferedFaceArray As Variant, _  
ByRef IntersectedBodyArray As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

CheckInterference3 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CheckInterference3( _  
    ByVal TargetBodies As Variant, _  
    ByVal ToolBodies As Variant, _  
    ByVal Options As Long, _  
    ByRef Body1InterferedFaceArray As Variant, _  
    ByRef Body2InterferedFaceArray As Variant, _  
    ByRef IntersectedBodyArray As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

CheckInterferenceBetweenTwoBodies Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CheckInterferenceBetweenTwoBodies( _  
    ByVal Body1 As Object, _  
    ByVal Body2 As Object, _  
    ByVal CoincidentInterference As Boolean, _  
    ByRef Body1InterferedFaceArray As Variant, _  
    ByRef Body2InterferedFaceArray As Variant, _  
    ByRef IntersectedBodyArray As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

CopyWizardHole Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CopyWizardHole( _  
    ByVal SourceHole As Object, _  
    ByVal DestinationHole As Object, _  
    ByVal RebuildOwner As Boolean _  
) As Long
```

SOLIDWORKS Type Library

CreateArc Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateArc( _  
    ByVal Center As Variant, _  
    ByVal Axis As Variant, _  
    ByVal Radius As Double, _  
    ByVal StartPoint As Variant, _  
    ByVal EndPoint As Variant _  
) As Object
```

SOLIDWORKS Type Library

CreateBodiesFromSheets Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateBodiesFromSheets( _  
    ByVal Sheets As Variant, _  
    ByVal Options As Long, _  
    ByRef Error As Long _  
) As Variant
```

SOLIDWORKS Type Library

CreateBodiesFromSheets2 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateBodiesFromSheets2( _  
    ByVal Sheets As Variant, _  
    ByVal Options As Long, _  
    ByVal KnittingTolerance As Double, _  
    ByRef Error As Long _  
) As Variant
```

SOLIDWORKS Type Library

CreateBodyFromBox Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateBodyFromBox( _  
    ByVal BoxDimArray As Variant _  
) As Object
```

SOLIDWORKS Type Library

CreateBodyFromBox3 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateBodyFromBox3( _  
    ByVal BoxDimArray As Variant _  
) As Body2
```

SOLIDWORKS Type Library

CreateBodyFromCone Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateBodyFromCone( _  
    ByVal ConeDimArray As Variant _  
) As Object
```

SOLIDWORKS Type Library

CreateBodyFromCyl Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateBodyFromCyl( _  
    ByVal CylDimArray As Variant _  
) As Object
```

SOLIDWORKS Type Library

CreateBodyFromFaces2 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateBodyFromFaces2( _
    ByVal NumOfFaces As Long, _
    ByVal Faces As Variant, _
    ByVal ActionType As Long, _
    ByVal DoLocalCheck As Boolean, _
    ByRef LocalCheckResult As Boolean _
) As Object
```

SOLIDWORKS Type Library

CreateBrepBody Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateBrepBody( _
    ByVal Type As Integer, _
    ByVal NTopologies As Integer, _
    ByVal Topologies As Variant, _
    ByVal EdgeToleranceArray As Variant, _
    ByVal VertexToleranceArray As Variant, _
    ByVal PointArray As Variant, _
    ByVal CurveArray As Variant, _
    ByVal SurfaceArray As Variant, _
    ByVal NRelations As Integer, _
    ByVal Parents As Variant, _
    ByVal Children As Variant, _
    ByVal Senses As Variant _
) As Object
```

SOLIDWORKS Type Library

CreateBrepBody3 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateBrepBody3( _
    ByVal Type As Integer, _
    ByVal NTopologies As Integer, _
    ByVal Topologies As Variant, _
    ByVal EdgeToleranceArray As Variant, _
    ByVal VertexToleranceArray As Variant, _
    ByVal PointArray As Variant, _
    ByVal CurveArray1 As Variant, _
    ByVal CurveSurfaceArray1 As Variant, _
    ByVal CurveArray2 As Variant, _
    ByVal CurveSurfaceArray2 As Variant, _
    ByVal SurfaceArray As Variant, _
    ByVal NRelations As Integer, _
    ByVal Parents As Variant, _
    ByVal Children As Variant, _
    ByVal Senses As Variant, _
    ByVal Option As Long _
) As Object
```

SOLIDWORKS Type Library

CreateBsplineCurve Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateBsplineCurve( _
    ByVal Props As Variant, _
    ByVal Knots As Variant, _
    ByVal CtrlPtCoords As Variant _
) As Object
```

SOLIDWORKS Type Library

CreateBsplineSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateBsplineSurface( _  
    ByVal Props As Variant, _  
    ByVal UKnots As Variant, _  
    ByVal VKnots As Variant, _  
    ByVal CtrlPtCoords As Variant _  
) As Object
```

SOLIDWORKS Type Library

CreateConicalSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateConicalSurface( _  
    ByVal Center As Variant, _  
    ByVal Direction As Variant, _  
    ByVal Radius As Double, _  
    ByVal SemiAngle As Double _  
) As Object
```

SOLIDWORKS Type Library

CreateConicalSurface2 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateConicalSurface2( _  
    ByVal Center As Variant, _  
    ByVal Direction As Variant, _  
    ByVal RefDirection As Variant, _  
    ByVal Radius As Double, _  
    ByVal SemiAngle As Double _  
) As Object
```

SOLIDWORKS Type Library

CreateCoonsBSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateCoonsBSurface( _  
    ByVal UCurve0 As Curve, _  
    ByVal UCurve1 As Curve, _  
    ByVal VCurve0 As Curve, _  
    ByVal VCurve1 As Curve, _  
    ByVal IgnoreClosureReq As Boolean _  
) As Surface
```

SOLIDWORKS Type Library

CreateCylindricalSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateCylindricalSurface( _  
    ByVal Center As Variant, _  
    ByVal Direction As Variant, _  
    ByVal Radius As Double _  
) As Object
```

SOLIDWORKS Type Library

CreateCylindricalSurface2 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateCylindricalSurface2( _  
    ByVal Center As Variant, _  
    ByVal Direction As Variant, _  
    ByVal RefDirection As Variant, _  
    ByVal Radius As Double _  
    ) As Object
```

SOLIDWORKS Type Library

CreateEllipse Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateEllipse( _  
    ByVal Center As Variant, _  
    ByVal MajorRadius As Double, _  
    ByVal MinorRadius As Double, _  
    ByVal MajorAxis As Variant, _  
    ByVal MinorAxis As Variant _  
    ) As Object
```

SOLIDWORKS Type Library

CreateExtrudedBody Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateExtrudedBody( _  
    ByVal SheetBody As Body2, _  
    ByVal Direction As MathVector, _  
    ByVal Length As Double _  
    ) As Body2
```

SOLIDWORKS Type Library

CreateExtrusionSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateExtrusionSurface( _  
    ByVal ProfileCurve As Object, _  
    ByVal AxisDirection As Variant _  
    ) As Object
```

SOLIDWORKS Type Library

CreateLine Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateLine( _  
    ByVal RootPoint As Variant, _  
    ByVal Direction As Variant _  
    ) As Object
```

SOLIDWORKS Type Library

CreateLoftBody Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateLoftBody( _  
    ByVal PModDoc As ModelDoc2, _  
    ByVal IsBlendClosed As Boolean, _
```

```

    ByVal KeepTangency As Boolean, _
    ByVal ForceNonRational As Boolean, _
    ByVal IsSolidBody As Boolean, _
    ByVal TessTolFactor As Double, _
    ByVal StartMatchingType As Integer, _
    ByVal EndMatchingType As Integer _
) As Body2

```

SOLIDWORKS Type Library

CreateLoftBody2 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```

Public Function CreateLoftBody2( _
    ByVal PModDoc As ModelDoc2, _
    ByVal Profile As Variant, _
    ByVal GuideCurve As Variant, _
    ByVal CenterLine As Object, _
    ByVal IsThinBody As Boolean, _
    ByVal ThinType As Long, _
    ByVal Thickness1 As Double, _
    ByVal Thickness2 As Double, _
    ByVal FeatureScope As Boolean, _
    ByVal IsBlendClosed As Boolean, _
    ByVal KeepTangency As Boolean, _
    ByVal ForceNonRational As Boolean, _
    ByVal IsSolidBody As Boolean, _
    ByVal TessTolFactor As Double, _
    ByVal StartTangentLength As Double, _
    ByVal EndTangentLength As Double, _
    ByVal StartTangentDir As Boolean, _
    ByVal EndTangentDir As Boolean, _
    ByVal StartMatchingType As Long, _
    ByVal EndMatchingType As Long, _
    ByVal Merge As Boolean _
) As Body2

```

SOLIDWORKS Type Library

CreateLoftSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```

Public Function CreateLoftSurface( _
    ByVal CurveArray As Variant, _
    ByVal BBlendClosed As Boolean, _
    ByVal BForceCubic As Boolean, _
    ByVal GuideCrvArray As Variant, _
    ByVal StartMatchingType As Long, _
    ByVal EndMatchingType As Long, _
    ByVal NormalAtStartSection As Object, _
    ByVal NormalAtEndSection As Object, _
    ByVal StartMatchingFaceList As Variant, _
    ByVal EndMatchingFaceList As Variant, _
    ByVal DegeneratedStart As Boolean, _
    ByVal DegeneratedEnd As Boolean, _
    ByVal StartPointOfStartSection As Object, _
    ByVal StartPointOfEndSection As Object, _
    ByVal SectionIndexStart As Long, _
    ByVal SectionIndexEnd As Long, _
    ByVal GuideIndexStart As Long, _
    ByVal GuideIndexEnd As Long _
) As Object

```

SOLIDWORKS Type Library

CreateOffsetSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateOffsetSurface( _  
    ByVal SurfaceIn As Object, _  
    ByVal Distance As Double _  
    ) As Object
```

SOLIDWORKS Type Library

CreatePCurve Method (Modeler)



Visual Basic for Applications (VBA)

```
Public Function CreatePCurve( _  
    ByVal Surface As Object, _  
    ByVal Props As Variant, _  
    ByVal Knots As Variant, _  
    ByVal CtrlPtCoords As Variant _  
    ) As Object
```

SOLIDWORKS Type Library

CreatePlanarSurface Method (Modeler)



Visual Basic for Applications (VBA)

```
Public Function CreatePlanarSurface( _  
    ByVal VRootPoint As Variant, _  
    ByVal VNormal As Variant _  
    ) As Object
```

SOLIDWORKS Type Library

CreatePlanarSurface2 Method (Modeler)



Visual Basic for Applications (VBA)

```
Public Function CreatePlanarSurface2( _  
    ByVal VRootPoint As Variant, _  
    ByVal VNormal As Variant, _  
    ByVal VRef As Variant _  
    ) As Object
```

SOLIDWORKS Type Library

CreateRevolutionSurface Method (Modeler)



Visual Basic for Applications (VBA)

```
Public Function CreateRevolutionSurface( _  
    ByVal ProfileCurve As Object, _  
    ByVal AxisPoint As Variant, _  
    ByVal AxisDirection As Variant, _  
    ByVal ProfileEndPtParams As Variant _  
    ) As Object
```

SOLIDWORKS Type Library

CreateRuledSurface Method (Modeler)



Visual Basic for Applications (VBA)

```
Public Function CreateRuledSurface( _  
    ByVal Curve1In As Object, _  
    ByVal Curve2In As Object, _  
    ByVal Apex As Variant _  
) As Object
```

SOLIDWORKS Type Library

CreateRuledSurfaceFromEdge Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateRuledSurfaceFromEdge( _  
    ByVal ModDoc As ModelDoc2, _  
    ByVal Edges As Variant, _  
    ByVal Type As Long, _  
    ByVal Length As Double, _  
    ByVal FlipPullDir As Boolean, _  
    ByVal FlipDir As Boolean, _  
    ByVal TrimAndSew As Boolean, _  
    ByVal Angle As Double, _  
    ByVal CoordInput As Boolean, _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double, _  
    ByVal BConnectSurface As Boolean, _  
    ByRef RuledSurface As Object _  
) As Long
```

SOLIDWORKS Type Library

CreateSheetFromFaces Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateSheetFromFaces( _  
    ByVal FaceArr As Variant _  
) As Body2
```

SOLIDWORKS Type Library

CreateSheetFromSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateSheetFromSurface( _  
    ByVal SurfaceIn As Object, _  
    ByVal UvRange As Variant _  
) As Object
```

SOLIDWORKS Type Library

CreateSphericalSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateSphericalSurface( _  
    ByVal Center As Variant, _  
    ByVal Radius As Double _  
) As Object
```

SOLIDWORKS Type Library

CreateSphericalSurface2 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateSphericalSurface2( _
    ByVal Center As Variant, _
    ByVal Axis As Variant, _
    ByVal RefDir As Variant, _
    ByVal Radius As Double _
) As Object
```

SOLIDWORKS Type Library

CreateSpring Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateSpring() As Spring
```

SOLIDWORKS Type Library

CreateSweptBody Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateSweptBody( _
    ByVal PModDoc As ModelDoc2, _
    ByVal Propagate As Boolean, _
    ByVal Alignment As Boolean, _
    ByVal TwistCtrlOption As Integer, _
    ByVal KeepTangency As Boolean, _
    ByVal BAdvancedSmoothing As Boolean, _
    ByVal StartMatchingType As Integer, _
    ByVal EndMatchingType As Integer, _
    ByVal IsThinBody As Boolean, _
    ByVal Thickness1 As Double, _
    ByVal Thickness2 As Double, _
    ByVal ThinType As Integer, _
    ByVal PathAlign As Integer, _
    ByVal TwistAngle As Double, _
    ByVal BMergeSmoothFaces As Boolean _
) As Body2
```

SOLIDWORKS Type Library

CreateSweptSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateSweptSurface( _
    ByVal CurveIn As Object, _
    ByVal Dir As Variant _
) As Object
```

SOLIDWORKS Type Library

CreateToroidalSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateToroidalSurface( _
    ByVal Center As Variant, _
    ByVal Axis As Variant, _
    ByVal RefDirection As Variant, _
    ByVal MajorRadius As Double, _
    ByVal MinorRadius As Double _
) As Object
```

SOLIDWORKS Type Library

CreateWireBody Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function CreateWireBody( _  
    ByVal EntVar As Variant, _  
    ByVal Option As Long _  
    ) As Body2
```

SOLIDWORKS Type Library

DeleteFacesFromSheetBody Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function DeleteFacesFromSheetBody( _  
    ByVal FaceVar As Variant _  
    ) As Boolean
```

SOLIDWORKS Type Library

FindTwoEdgeMaxDeviation Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function FindTwoEdgeMaxDeviation( _  
    ByVal LpEdge1 As Object, _  
    ByVal LpEdge2 As Object _  
    ) As Double
```

SOLIDWORKS Type Library

GeneralTopology Property (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Property GeneralTopology As Boolean
```

SOLIDWORKS Type Library

GetBodyOutline Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetBodyOutline( _  
    ByVal BodyVar As Variant, _  
    ByVal Direction As MathVector, _  
    ByVal Tolerance As Double, _  
    ByRef CurvesOut As Variant, _  
    ByRef TopolEntities As Variant, _  
    ByRef Outline As Variant _  
    ) As Long
```

SOLIDWORKS Type Library

GetBodyOutline2 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetBodyOutline2( _
    ByVal BodyList As Variant, _
    ByVal Direction As MathVector, _
    ByVal Tolerance As Double, _
    ByVal ProjectOnPlane As Boolean, _
    ByRef Curves As Variant, _
    ByRef TopolEntities As Variant, _
    ByRef Outline As Variant _
) As Long
```

SOLIDWORKS Type Library

GetInitKnitGapWidth Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetInitKnitGapWidth() As Double
```

SOLIDWORKS Type Library

GetManifoldBodiesCount Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetManifoldBodiesCount( _
    ByVal NonManifoldIn As Body2 _
) As Long
```

SOLIDWORKS Type Library

GetToleranceValue Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetToleranceValue( _
    ByVal ToleranceID As Long _
) As Double
```

SOLIDWORKS Type Library

ICheckInterference Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ICheckInterference( _
    ByRef Body1InterferedFaceArray As Face, _
    ByRef Body2InterferedFaceArray As Face, _
    ByRef IntersectedBodyArray As Body _
)
```

SOLIDWORKS Type Library

ICheckInterference2 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ICheckInterference2( _
    ByRef Body1InterferedFaceArray As Face2, _
    ByRef Body2InterferedFaceArray As Face2, _
    ByRef IntersectedBodyArray As Body2 _
)
```

SOLIDWORKS Type Library

ICheckInterference3 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICheckInterference3( _  
    ByRef Body1InterferedFaceArray As Face2, _  
    ByRef Body2InterferedFaceArray As Face2, _  
    ByRef IntersectedBodyArray As Body2 _  
    ) As Boolean
```

SOLIDWORKS Type Library

ICheckInterferenceCount Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICheckInterferenceCount( _  
    ByVal Body1 As Body, _  
    ByVal Body2 As Body, _  
    ByVal CoincidentInterference As Boolean, _  
    ByRef Body1InterferedFaceCount As Long, _  
    ByRef Body2InterferedFaceCount As Long, _  
    ByRef IntersectedBodyCount As Long _  
    ) As Boolean
```

SOLIDWORKS Type Library

ICheckInterferenceCount2 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICheckInterferenceCount2( _  
    ByVal Body1 As Body2, _  
    ByVal Body2 As Body2, _  
    ByVal CoincidentInterference As Boolean, _  
    ByRef Body1InterferedFaceCount As Long, _  
    ByRef Body2InterferedFaceCount As Long, _  
    ByRef IntersectedBodyCount As Long _  
    ) As Boolean
```

SOLIDWORKS Type Library

ICheckInterferenceCount3 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICheckInterferenceCount3( _  
    ByVal NumOfTargetBodies As Long, _  
    ByVal TargetBodies As Body2, _  
    ByVal NumOfToolBodies As Long, _  
    ByVal ToolBodies As Body2, _  
    ByVal Options As Long, _  
    ByRef NumBody1InterferedFaceArray As Long, _  
    ByRef NumBody2InterferedFaceArray As Long, _  
    ByRef NumIntersectedBodyArray As Long _  
    ) As Boolean
```

SOLIDWORKS Type Library

ICopyWizardHole Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICopyWizardHole( _  
    ByVal SourceHole As Feature, _  
    ByVal DestinationHole As Feature, _  
    ByVal RebuildOwner As Boolean _  
    ) As Long
```

ICreateArc Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateArc( _
    ByRef Center As Double, _
    ByRef Axis As Double, _
    ByVal Radius As Double, _
    ByRef StartPoint As Double, _
    ByRef EndPoint As Double _
) As Curve
```

ICreateBodiesFromSheets Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateBodiesFromSheets( _
    ByVal NSheets As Long, _
    ByRef Sheets As Unknown, _
    ByVal Options As Long, _
    ByRef NResults As Long, _
    ByRef Results As Unknown _
) As Long
```

ICreateBodiesFromSheets2 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateBodiesFromSheets2( _
    ByVal NSheets As Long, _
    ByVal Sheets As Body2, _
    ByVal Options As Long, _
    ByVal KnittingTolerance As Double, _
    ByRef NResults As Long, _
    ByRef Results As Body2 _
) As Long
```

ICreateBodyFromBox Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateBodyFromBox( _
    ByRef BoxDimArray As Double _
) As Body
```

ICreateBodyFromBox2 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateBodyFromBox2( _
    ByRef BoxDimArray As Double _
) As Body2
```

ICreateBodyFromCone Method (Modeler)

Syntax

```
Public Function ICreateBodyFromCone( _  
    ByRef ConeDimArray As Double _  
) As Body
```

 Syntax

```
Public Function ICreateBodyFromCone2( _  
    ByRef ConeDimArray As Double _  
) As Body2
```

 Syntax

```
Public Function ICreateBodyFromCyl( _  
    ByRef CylDimArray As Double _  
) As Body
```

 Syntax

```
Public Function ICreateBodyFromCyl2( _  
    ByRef CylDimArray As Double _  
) As Body2
```

 Syntax

```
Public Function ICreateBodyFromFaces( _  
    ByVal NumOfFaces As Long, _  
    ByVal Faces As Face, _  
    ByVal DoLocalCheck As Boolean, _  
    ByRef LocalCheckResult As Boolean _  
) As Body
```

 Syntax

```
Public Function ICreateBodyFromFaces2( _  
    ByVal NumOfFaces As Long, _  
    ByVal Faces As Face, _  
    ByVal ActionType As Long, _  
    ByVal DoLocalCheck As Boolean, _  
    ByRef LocalCheckResult As Boolean _  
) As Body
```

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateBodyFromFaces3( _  
    ByVal NumOfFaces As Long, _  
    ByVal Faces As Face2, _  
    ByVal ActionType As Long, _  
    ByVal DoLocalCheck As Boolean, _  
    ByRef LocalCheckResult As Boolean _  
) As Body2
```

SOLIDWORKS Type Library

ICreateBrepBody Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateBrepBody( _  
    ByVal Type As Integer, _  
    ByVal NTopologies As Integer, _  
    ByRef Topologies As Integer, _  
    ByRef EdgeTolArray As Double, _  
    ByRef VertexTolArray As Double, _  
    ByRef PointArray As Double, _  
    ByVal CurveArray As Curve, _  
    ByVal SurfaceArray As Surface, _  
    ByVal NRelations As Integer, _  
    ByRef Parents As Integer, _  
    ByRef Children As Integer, _  
    ByRef Senses As Integer _  
) As Body
```

SOLIDWORKS Type Library

ICreateBrepBody2 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateBrepBody2( _  
    ByVal Type As Integer, _  
    ByVal NTopologies As Integer, _  
    ByRef Topologies As Integer, _  
    ByRef EdgeTolArray As Double, _  
    ByRef VertexTolArray As Double, _  
    ByRef PointArray As Double, _  
    ByVal CurveArray As Curve, _  
    ByVal SurfaceArray As Surface, _  
    ByVal NRelations As Integer, _  
    ByRef Parents As Integer, _  
    ByRef Children As Integer, _  
    ByRef Senses As Integer _  
) As Body2
```

SOLIDWORKS Type Library

ICreateBrepBody3 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateBrepBody3( _  
    ByVal Type As Integer, _  
    ByVal NTopologies As Integer, _  
    ByRef Topologies As Integer, _  
    ByRef EdgeTolArray As Double, _  
    ByRef VertexTolArray As Double, _  
    ByRef PointArray As Double, _  
    ByVal CurveArra1 As Curve, _  
    ByVal CurveSurfaceArray1 As Surface, _
```

```
ByVal CurveArray2 As Curve, _  
ByVal CurveSurfaceArray2 As Surface, _  
ByVal SurfaceArray As Surface, _  
ByVal NRelations As Integer, _  
ByRef Parents As Integer, _  
ByRef Children As Integer, _  
ByRef Senses As Integer, _  
ByVal Option As Long _  
) As Body2
```

SOLIDWORKS Type Library

ICreateBsplineCurve Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateBsplineCurve( _  
    ByRef Properties As Long, _  
    ByRef KnotArray As Double, _  
    ByRef ControlPointCoordArray As Double _  
) As Curve
```

SOLIDWORKS Type Library

ICreateBsplineSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateBsplineSurface( _  
    ByRef Properties As Long, _  
    ByRef UKnotArray As Double, _  
    ByRef VKnotArray As Double, _  
    ByRef ControlPointCoordArray As Double _  
) As Surface
```

SOLIDWORKS Type Library

ICreateConicalSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateConicalSurface( _  
    ByRef Center As Double, _  
    ByRef Direction As Double, _  
    ByVal Radius As Double, _  
    ByVal SemiAngle As Double _  
) As Surface
```

SOLIDWORKS Type Library

ICreateConicalSurface2 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateConicalSurface2( _  
    ByRef Center As Double, _  
    ByRef Direction As Double, _  
    ByRef RefDirection As Double, _  
    ByVal Radius As Double, _  
    ByVal SemiAngle As Double _  
) As Surface
```

SOLIDWORKS Type Library

ICreateCylindricalSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateCylindricalSurface( _  
    ByRef Center As Double, _  
    ByRef Direction As Double, _  
    ByVal Radius As Double _  
) As Surface
```

SOLIDWORKS Type Library

ICreateCylindricalSurface2 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateCylindricalSurface2( _  
    ByRef Center As Double, _  
    ByRef Direction As Double, _  
    ByRef RefDirection As Double, _  
    ByVal Radius As Double _  
) As Surface
```

SOLIDWORKS Type Library

ICreateEllipse Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateEllipse( _  
    ByRef Center As Double, _  
    ByVal MajorRadius As Double, _  
    ByVal MinorRadius As Double, _  
    ByRef MajorAxis As Double, _  
    ByRef MinorAxis As Double _  
) As Curve
```

SOLIDWORKS Type Library

ICreateExtrusionSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateExtrusionSurface( _  
    ByVal ProfileCurve As Curve, _  
    ByRef AxisDirection As Double _  
) As Surface
```

SOLIDWORKS Type Library

ICreateLine Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateLine( _  
    ByRef RootPoint As Double, _  
    ByRef Direction As Double _  
) As Curve
```

SOLIDWORKS Type Library

ICreateLoftSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateLoftSurface( _  
    ByVal NCurves As Long, _  
    ByVal CurveArray As Curve, _  
    ByVal BBlendClosed As Boolean, _  
    ByVal BForceCubic As Boolean, _
```



```

ByVal NGuides As Long, _
ByVal GuideCrvArray As Curve, _
ByVal StartMatchingType As Long, _
ByVal EndMatchingType As Long, _
ByVal NormalAtStartSection As MathVector, _
ByVal NormalAtEndSection As MathVector, _
ByVal NStartMatchingFaces As Long, _
ByVal StartMatchingFaceList As Face2, _
ByVal NEndMatchingFaces As Long, _
ByVal EndMatchingFaceList As Face2, _
ByVal DegeneratedStart As Boolean, _
ByVal DegeneratedEnd As Boolean, _
ByVal StartPointOfStartSection As MathPoint, _
ByVal StartPointOfEndSection As MathPoint, _
ByVal SectionIndexStart As Long, _
ByVal SectionIndexEnd As Long, _
ByVal GuideIndexStart As Long, _
ByVal GuideIndexEnd As Long _
) As Surface

```

SOLIDWORKS Type Library

ICreateOffsetSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```

Public Function ICreateOffsetSurface( _
    ByVal SurfaceIn As Surface, _
    ByVal Distance As Double _
) As Surface

```

SOLIDWORKS Type Library

ICreatePCurve Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```

Public Function ICreatePCurve( _
    ByVal Surface As Surface, _
    ByRef Props As Long, _
    ByRef Knots As Double, _
    ByRef CtrlPtCoords As Double _
) As Curve

```

SOLIDWORKS Type Library

ICreatePlanarSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```

Public Function ICreatePlanarSurface( _
    ByRef RootPoint As Double, _
    ByRef Normal As Double _
) As Surface

```

SOLIDWORKS Type Library

ICreatePlanarSurface2 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```

Public Function ICreatePlanarSurface2( _
    ByRef RootPoint As Double, _
    ByRef Normal As Double, _
    ByRef Ref As Double _
) As Surface

```

ICreateRevolutionSurface Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function ICreateRevolutionSurface( _
    ByVal ProfileCurve As Curve, _
    ByRef AxisPoint As Double, _
    ByRef AxisDirection As Double, _
    ByRef ProfileEndPtParams As Double _
) As Surface
```

ICreateRuledSurface Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function ICreateRuledSurface( _
    ByVal Curve1In As Curve, _
    ByVal Curve2In As Curve, _
    ByRef Apex As Double _
) As Surface
```

ICreateRuledSurfaceFromEdge Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function ICreateRuledSurfaceFromEdge( _
    ByVal ModDoc As ModelDoc2, _
    ByVal NumOfEdges As Long, _
    ByVal Edges As Edge, _
    ByVal Type As Long, _
    ByVal Length As Double, _
    ByVal FlipPullDir As Boolean, _
    ByVal FlipDir As Boolean, _
    ByVal TrimAndSew As Boolean, _
    ByVal Angle As Double, _
    ByVal CoordInput As Boolean, _
    ByVal X As Double, _
    ByVal Y As Double, _
    ByVal Z As Double, _
    ByVal BConnectSurface As Boolean, _
    ByRef RuledSurface As Body2 _
) As Long
```

ICreateSheetFromFaces Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function ICreateSheetFromFaces( _
    ByVal FaceCount As Long, _
    ByVal FaceArr As Face2 _
) As Body2
```

ICreateSheetFromSurface Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function ICreateSheetFromSurface( _  
    ByVal SurfaceIn As Surface, _  
    ByRef UvRange As Double _  
    ) As Body
```

SOLIDWORKS Type Library

ICreateSheetFromSurface2 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateSheetFromSurface2( _  
    ByVal SurfaceIn As Surface, _  
    ByRef UvRange As Double _  
    ) As Body2
```

SOLIDWORKS Type Library

ICreateSphericalSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateSphericalSurface( _  
    ByRef Center As Double, _  
    ByVal Radius As Double _  
    ) As Surface
```

SOLIDWORKS Type Library

ICreateSphericalSurface2 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateSphericalSurface2( _  
    ByRef Center As Double, _  
    ByRef Axis As Double, _  
    ByRef RefDir As Double, _  
    ByVal Radius As Double _  
    ) As Surface
```

SOLIDWORKS Type Library

ICreateSweptSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateSweptSurface( _  
    ByVal CurveIn As Curve, _  
    ByRef Dir As Double _  
    ) As Surface
```

SOLIDWORKS Type Library

ICreateToroidalSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ICreateToroidalSurface( _  
    ByRef Center As Double, _  
    ByRef Axis As Double, _  
    ByRef RefDirection As Double, _  
    ByVal MajorRadius As Double, _  
    ByVal MinorRadius As Double _  
    ) As Surface
```

ICreateWireBody Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function ICreateWireBody( _
    ByVal Count As Long, _
    ByRef EntArr As Object, _
    ByVal Option As Long _
) As Body2
```

IDeleteFacesFromSheetBody Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function IDeleteFacesFromSheetBody( _
    ByVal Count As Long, _
    ByVal FaceVar As Face2 _
) As Boolean
```

IFindTwoEdgeMaxDeviation Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function IFindTwoEdgeMaxDeviation( _
    ByVal PEdge1 As Edge, _
    ByVal PEdge2 As Edge _
) As Double
```

IImprintingFaces Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub IImprintingFaces( _
    ByRef TargetEdges As Edge, _
    ByRef ToolEdges As Edge, _
    ByRef TargetVertices As Vertex, _
    ByRef ToolVertices As Vertex _
)
```

IImprintingFacesCount Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function IImprintingFacesCount( _
    ByVal NTargetFaces As Long, _
    ByVal TargetFaceArray As Face, _
    ByVal NToolFaces As Long, _
    ByVal ToolFaceArray As Face, _
    ByVal Options As Long, _
    ByRef NTargetEdges As Long, _
    ByRef NtoolEdges As Long, _
    ByRef NtargetVertices As Long, _
    ByRef ToolVertices As Long _
) As Boolean
```

IImprintingFacesCount2 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IImprintingFacesCount2( _  
    ByVal NTargetFaces As Long, _  
    ByVal TargetFaceArray As Face2, _  
    ByVal NToolFaces As Long, _  
    ByVal ToolFaceArray As Face2, _  
    ByVal Options As Long, _  
    ByRef NTargetEdges As Long, _  
    ByRef NtoolEdges As Long, _  
    ByRef NtargetVertices As Long, _  
    ByRef ToolVertices As Long _  
) As Boolean
```

SOLIDWORKS Type Library

IMakeManifoldBodies Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IMakeManifoldBodies( _  
    ByVal NonManifoldIn As Body2, _  
    ByVal Count As Long _  
) As Body2
```

SOLIDWORKS Type Library

IMergeCurves Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IMergeCurves( _  
    ByVal CurveCount As Long, _  
    ByVal CurveArr As Curve _  
) As Curve
```

SOLIDWORKS Type Library

ImprintingFaces Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ImprintingFaces( _  
    ByVal TargetFaceArray As Variant, _  
    ByVal ToolFaceArray As Variant, _  
    ByVal Options As Long, _  
    ByRef TargetEdges As Variant, _  
    ByRef ToolEdges As Variant, _  
    ByRef TargetVertices As Variant, _  
    ByRef ToolVertices As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

IRemoveSurfaces Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IRemoveSurfaces( _  
    ByVal NFaces As Long, _  
    ByVal FaceArray As Face, _  
    ByVal NewSurfArray As Surface, _  
    ByRef SenseArray As Integer, _  
    ByVal Tolerance As Double _  
) As Boolean
```

IReplaceSurfaces2 Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function IReplaceSurfaces2( _  
    ByVal NFaces As Long, _  
    ByVal FaceArray As Face2, _  
    ByVal NewSurfArray As Surface, _  
    ByRef SenseArray As Integer, _  
    ByVal Tolerance As Double _  
) As Boolean
```

IRestore Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function IRestore( _  
    ByVal StreamIn As Unknown _  
) As Body
```

IRestore2 Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function IRestore2( _  
    ByVal StreamIn As Unknown _  
) As Body2
```

ISplitFaceOnParam Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function ISplitFaceOnParam() As Face
```

ISplitFaceOnParam2 Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function ISplitFaceOnParam2() As Face2
```

ISplitFaceOnParamCount Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function ISplitFaceOnParamCount( _  
    ByVal Facedisp As Face, _  
    ByVal UVFlag As Long, _  
    ByVal Parameter As Double, _  
    ByRef Status As Boolean _  
) As Long
```

ISplitFaceOnParamCount2 Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ISplitFaceOnParamCount2( _  
    ByVal Facedisp As Face2, _  
    ByVal UVFlag As Long, _  
    ByVal Parameter As Double, _  
    ByRef Status As Boolean _  
    ) As Long
```

SOLIDWORKS Type Library

MakeManifoldBodies Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function MakeManifoldBodies( _  
    ByVal NonManifoldIn As Body2 _  
    ) As Variant
```

SOLIDWORKS Type Library

MergeCurves Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function MergeCurves( _  
    ByVal CurveVar As Variant _  
    ) As Curve
```

SOLIDWORKS Type Library

ProjectCurveOnSurface Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ProjectCurveOnSurface( _  
    ByVal CurveIn As Curve, _  
    ByVal SurfaceIn As Surface, _  
    ByVal ProjDir As MathVector _  
    ) As Curve
```

SOLIDWORKS Type Library

ReplaceSurfaces Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ReplaceSurfaces( _  
    ByVal NFaces As Long, _  
    ByVal FaceArray As Variant, _  
    ByVal NewSurfArray As Variant, _  
    ByVal SenseArray As Variant, _  
    ByVal Tolerance As Double _  
    ) As Boolean
```

SOLIDWORKS Type Library

Restore Method (Modeler)

Syntax

Visual Basic for Applications (VBA)

```
Public Function Restore( _  
    ByVal StreamIn As Unknown _  
    ) As Object
```

SetInitKnitGapWidth Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function SetInitKnitGapWidth( _  
    ByVal InitGapWidth As Double _  
) As Boolean
```

SetTolerances Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function SetTolerances( _  
    ByRef ToleranceIDArray As Long, _  
    ByRef ToleranceValueArray As Double, _  
    ByVal NumTol As Long _  
) As Boolean
```

SetToleranceValue Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function SetToleranceValue( _  
    ByVal ToleranceID As Long, _  
    ByVal NewToleranceValue As Double _  
) As Double
```

SplitFaceOnParam Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function SplitFaceOnParam( _  
    ByVal Facedisp As Object, _  
    ByVal UVFlag As Long, _  
    ByVal Parameter As Double, _  
    ByRef Status As Boolean _  
) As Variant
```

ThickenSheet Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function ThickenSheet( _  
    ByVal Sheet As Body2, _  
    ByVal Thickness As Double, _  
    ByVal Direction As Long _  
) As Body2
```

UnsetTolerances Method (Modeler) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function UnsetTolerances( _  
    ByRef ToleranceIDArray As Long, _
```



```
ByVal NumTol As Long _  
) As Boolean
```