

SOLIDWORKS API (VB6 COM) — Reference (85/102): SketchBlockInstance-SketchLine


SOLIDWORKS API Documentation (converted from CHM)

SketchBlockInstance (Type)

SOLIDWORKS Type Library

SketchBlockInstance Object

Object Model



SOLIDWORKS Type Library

SketchBlockInstance Object Members

Public Methods

	GetArrowHeadStyle
	GetAttachedEntities
	GetAttributeCount
	GetAttributes
	GetAttributeValue
	GetLeaderPoints
	GetLeaderStyle
	GetScale3
	GetSketch
	IGetAttributes
	IGetLeaderPoints
	IsNested
	Select
	SetAttributeValue
	SetLeader

Public Properties

	Angle
	BlockToSketchTransform
	Definition
	DimensionDisplay
	InstancePosition
	Layer
	LockAngle
	Name
	Scale



[Scale2](#)



[TextDisplay](#)



[Visible](#)

SOLIDWORKS Type Library

Angle Property (SketchBlockInstance)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Angle As Double
```

SOLIDWORKS Type Library

BlockToSketchTransform Property (SketchBlockInstance)

Syntax

Visual Basic for Applications (VBA)

```
Public Property BlockToSketchTransform As MathTransform
```

SOLIDWORKS Type Library

Definition Property (SketchBlockInstance)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Definition As SketchBlockDefinition
```

SOLIDWORKS Type Library

DimensionDisplay Property (SketchBlockInstance)

Syntax

Visual Basic for Applications (VBA)

```
Public Property DimensionDisplay As Boolean
```

SOLIDWORKS Type Library

GetArrowHeadStyle Method (SketchBlockInstance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetArrowHeadStyle() As Long
```

SOLIDWORKS Type Library

GetAttachedEntities Method (SketchBlockInstance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetAttachedEntities( _  
    ByRef Entities As Variant, _  
    ByRef EntityTypes As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

GetAttributeCount Method (SketchBlockInstance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetAttributeCount() As Long
```

SOLIDWORKS Type Library

GetAttributes Method (SketchBlockInstance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetAttributes() As Variant
```

SOLIDWORKS Type Library

GetAttributeValue Method (SketchBlockInstance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetAttributeValue( _  
    ByVal TagName As String _  
) As String
```

SOLIDWORKS Type Library

GetLeaderPoints Method (SketchBlockInstance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetLeaderPoints() As Variant
```

SOLIDWORKS Type Library

GetLeaderStyle Method (SketchBlockInstance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetLeaderStyle() As Long
```

SOLIDWORKS Type Library

GetScale3 Method (SketchBlockInstance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetScale3( _  
    ByVal Ignoreparentscale As Boolean _  
) As Double
```

SOLIDWORKS Type Library

GetSketch Method (SketchBlockInstance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSketch() As Sketch
```

SOLIDWORKS Type Library

IGetAttributes Method (SketchBlockInstance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetAttributes( _  
    ByVal Count As Long _  
) As Note
```

SOLIDWORKS Type Library

IGetLeaderPoints Method (SketchBlockInstance)



Visual Basic for Applications (VBA)

```
Public Function IGetLeaderPoints() As Double
```

SOLIDWORKS Type Library

InstancePosition Property (SketchBlockInstance)



Visual Basic for Applications (VBA)

```
Public Property InstancePosition As MathPoint
```

SOLIDWORKS Type Library

IsNested Method (SketchBlockInstance)



Visual Basic for Applications (VBA)

```
Public Function IsNested() As Boolean
```

SOLIDWORKS Type Library

Layer Property (SketchBlockInstance)



Visual Basic for Applications (VBA)

```
Public Property Layer As String
```

SOLIDWORKS Type Library

LockAngle Property (SketchBlockInstance)



Visual Basic for Applications (VBA)

```
Public Property LockAngle As Boolean
```

SOLIDWORKS Type Library

Name Property (SketchBlockInstance)



Visual Basic for Applications (VBA)

```
Public Property Name As String
```

SOLIDWORKS Type Library

Scale Property (SketchBlockInstance)



Visual Basic for Applications (VBA)

```
Public Property Scale As Double
```

SOLIDWORKS Type Library

Scale2 Property (SketchBlockInstance)



Visual Basic for Applications (VBA)

```
Public Property Scale2 As Double
```

SOLIDWORKS Type Library

Select Method (SketchBlockInstance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function Select( _  
    ByVal Append As Boolean, _  
    ByVal Data As SelectData _  
) As Boolean
```

SOLIDWORKS Type Library

SetAttributeValue Method (SketchBlockInstance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetAttributeValue( _  
    ByVal TagName As String, _  
    ByVal Value As String _  
) As Boolean
```

SOLIDWORKS Type Library

SetLeader Method (SketchBlockInstance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetLeader( _  
    ByVal LeaderStyle As Long, _  
    ByVal ArrowHeadStyle As Long _  
) As Boolean
```

SOLIDWORKS Type Library

TextDisplay Property (SketchBlockInstance)

Syntax

Visual Basic for Applications (VBA)

```
Public Property TextDisplay As Long
```

SOLIDWORKS Type Library

Visible Property (SketchBlockInstance)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Visible As Long
```

SketchContour (Type)

SOLIDWORKS Type Library
SketchContour Object

Object Model



SOLIDWORKS Type Library
SketchContour Object Members

Public Methods

	DeSelect
	GetEdges
	GetEdgesCount
	GetSketchSegments
	GetSketchSegmentsCount
	IGetEdges
	IGetSketchSegments
	IsClosed
	Select
	Select2

Public Properties

	Sketch
---	------------------------

SOLIDWORKS Type Library
DeSelect Method (SketchContour)

Syntax

```
Visual Basic for Applications (VBA)

Public Function DeSelect() As Boolean
```

SOLIDWORKS Type Library
GetEdges Method (SketchContour)

Syntax

```
Visual Basic for Applications (VBA)

Public Function GetEdges() As Variant
```

SOLIDWORKS Type Library
GetEdgesCount Method (SketchContour)

Syntax

```
Visual Basic for Applications (VBA)
```

```
Public Function GetEdgesCount() As Long
```

SOLIDWORKS Type Library

GetSketchSegments Method (SketchContour)



Visual Basic for Applications (VBA)

```
Public Function GetSketchSegments() As Variant
```

SOLIDWORKS Type Library

GetSketchSegmentsCount Method (SketchContour)



Visual Basic for Applications (VBA)

```
Public Function GetSketchSegmentsCount() As Long
```

SOLIDWORKS Type Library

IGetEdges Method (SketchContour)



Visual Basic for Applications (VBA)

```
Public Function IGetEdges( _  
    ByVal Count As Long _  
) As Edge
```

SOLIDWORKS Type Library

IGetSketchSegments Method (SketchContour)



Visual Basic for Applications (VBA)

```
Public Function IGetSketchSegments( _  
    ByVal Count As Long _  
) As SketchSegment
```

SOLIDWORKS Type Library

IsClosed Method (SketchContour)



Visual Basic for Applications (VBA)

```
Public Function IsClosed() As Boolean
```

SOLIDWORKS Type Library

Select Method (SketchContour)



Visual Basic for Applications (VBA)

```
Public Function Select( _  
    ByVal Append As Boolean, _  
    ByVal Mark As Long _  
) As Boolean
```

SOLIDWORKS Type Library

Select2 Method (SketchContour)



Visual Basic for Applications (VBA)

```
Public Function Select2( _  
    ByVal Append As Boolean, _  
    ByVal Data As SelectData _  
    ) As Boolean
```

SOLIDWORKS Type Library

Sketch Property (SketchContour)

 Syntax


Visual Basic for Applications (VBA)

```
Public Property Sketch As Sketch
```

SketchedBendFeatureData (Type)

SOLIDWORKS Type Library
SketchedBendFeatureData Object

Object Model



SOLIDWORKS Type Library
SketchedBendFeatureData Object Members

Public Methods

	AccessSelections
	GetCustomBendAllowance
	GetFixedFace
	IAccessSelections
	IAccessSelections2
	ReleaseSelectionAccess
	SetCustomBendAllowance
	SetFixedFace

Public Properties

	BendAngle
	BendRadius
	OverrideValue
	PositionType
	ReverseDirection
	UseDefaultBendAllowance
	UseDefaultBendRadius
	UseGaugeTable

SOLIDWORKS Type Library
AccessSelections Method (SketchedBendFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Function AccessSelections( _
    ByVal TopDoc As Object, _
    ByVal Component As Object _
) As Boolean
```

SOLIDWORKS Type Library
BendAngle Property (SketchedBendFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property BendAngle As Double
```

SOLIDWORKS Type Library

BendRadius Property (SketchedBendFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property BendRadius As Double
```

SOLIDWORKS Type Library

GetCustomBendAllowance Method (SketchedBendFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCustomBendAllowance() As CustomBendAllowance
```

SOLIDWORKS Type Library

GetFixedFace Method (SketchedBendFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFixedFace( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double _  
) As Object
```

SOLIDWORKS Type Library

IAccessSelections Method (SketchedBendFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IAccessSelections( _  
    ByVal TopDoc As ModelDoc, _  
    ByVal Component As Component _  
) As Boolean
```

SOLIDWORKS Type Library

IAccessSelections2 Method (SketchedBendFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IAccessSelections2( _  
    ByVal TopDoc As ModelDoc2, _  
    ByVal Component As Component2 _  
) As Boolean
```

SOLIDWORKS Type Library

OverrideValue Property (SketchedBendFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property OverrideValue As Boolean
```

SOLIDWORKS Type Library

PositionType Property (SketchedBendFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property PositionType As Long
```

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (SketchedBendFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ReleaseSelectionAccess()
```

SOLIDWORKS Type Library

ReverseDirection Property (SketchedBendFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property ReverseDirection As Boolean
```

SOLIDWORKS Type Library

SetCustomBendAllowance Method (SketchedBendFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetCustomBendAllowance( _  
    ByVal PBendData As CustomBendAllowance _  
)
```

SOLIDWORKS Type Library

SetFixedFace Method (SketchedBendFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetFixedFace( _  
    ByVal X As Double, _  
    ByVal Y As Double, _  
    ByVal Z As Double, _  
    ByVal EdgeArray As Object _  
)
```

SOLIDWORKS Type Library

UseDefaultBendAllowance Property (SketchedBendFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property UseDefaultBendAllowance As Boolean
```

SOLIDWORKS Type Library

UseDefaultBendRadius Property (SketchedBendFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property UseDefaultBendRadius As Boolean
```

SOLIDWORKS Type Library

UseGaugeTable Property (SketchedBendFeatureData)

Syntax


Visual Basic for Applications (VBA)

```
Public Property UseGaugeTable As Boolean
```

SketchEllipse (Type)

SOLIDWORKS Type Library
SketchEllipse Object

Object Model



SOLIDWORKS Type Library
SketchEllipse Object Members

Public Methods

	GetCenterPoint
	GetCenterPoint2
	GetEndPoint
	GetEndPoint2
	GetMajorPoint
	GetMajorPoint2
	GetMinorPoint
	GetMinorPoint2
	GetRotationDir
	GetStartPoint
	GetStartPoint2
	IGetCenterPoint
	IGetCenterPoint2
	IGetEndPoint
	IGetEndPoint2
	IGetMajorPoint
	IGetMajorPoint2
	IGetMinorPoint
	IGetMinorPoint2
	IGetStartPoint
	IGetStartPoint2

SOLIDWORKS Type Library
GetCenterPoint Method (SketchEllipse)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCenterPoint() As Variant
```

SOLIDWORKS Type Library

GetCenterPoint2 Method (SketchEllipse)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetCenterPoint2() As Object
```

SOLIDWORKS Type Library

GetEndPoint Method (SketchEllipse)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetEndPoint() As Variant
```

SOLIDWORKS Type Library

GetEndPoint2 Method (SketchEllipse)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetEndPoint2() As Object
```

SOLIDWORKS Type Library

GetMajorPoint Method (SketchEllipse)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetMajorPoint() As Variant
```

SOLIDWORKS Type Library

GetMajorPoint2 Method (SketchEllipse)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetMajorPoint2() As Object
```

SOLIDWORKS Type Library

GetMinorPoint Method (SketchEllipse)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetMinorPoint() As Variant
```

SOLIDWORKS Type Library

GetMinorPoint2 Method (SketchEllipse)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetMinorPoint2() As Object
```

SOLIDWORKS Type Library

GetRotationDir Method (SketchEllipse)

 **Syntax**

Visual Basic for Applications (VBA)

Public Function GetRotationDir() As Long

SOLIDWORKS Type Library

GetStartPoint Method (SketchEllipse)



Visual Basic for Applications (VBA)

Public Function GetStartPoint() As Variant

SOLIDWORKS Type Library

GetStartPoint2 Method (SketchEllipse)



Visual Basic for Applications (VBA)

Public Function GetStartPoint2() As Object

SOLIDWORKS Type Library

IGetCenterPoint Method (SketchEllipse)



Visual Basic for Applications (VBA)

Public Function IGetCenterPoint() As Double

SOLIDWORKS Type Library

IGetCenterPoint2 Method (SketchEllipse)



Visual Basic for Applications (VBA)

Public Function IGetCenterPoint2() As [SketchPoint](#)

SOLIDWORKS Type Library

IGetEndPoint Method (SketchEllipse)



Visual Basic for Applications (VBA)

Public Function IGetEndPoint() As Double

SOLIDWORKS Type Library

IGetEndPoint2 Method (SketchEllipse)



Visual Basic for Applications (VBA)

Public Function IGetEndPoint2() As [SketchPoint](#)

SOLIDWORKS Type Library

IGetMajorPoint Method (SketchEllipse)



Visual Basic for Applications (VBA)

Public Function IGetMajorPoint() As Double

SOLIDWORKS Type Library

IGetMajorPoint2 Method (SketchEllipse)



Visual Basic for Applications (VBA)

```
Public Function IGetMajorPoint2() As SketchPoint
```

SOLIDWORKS Type Library

IGetMinorPoint Method (SketchEllipse)



Visual Basic for Applications (VBA)

```
Public Function IGetMinorPoint() As Double
```

SOLIDWORKS Type Library

IGetMinorPoint2 Method (SketchEllipse)



Visual Basic for Applications (VBA)

```
Public Function IGetMinorPoint2() As SketchPoint
```

SOLIDWORKS Type Library

IGetStartPoint Method (SketchEllipse)



Visual Basic for Applications (VBA)

```
Public Function IGetStartPoint() As Double
```

SOLIDWORKS Type Library

IGetStartPoint2 Method (SketchEllipse)



Visual Basic for Applications (VBA)

```
Public Function IGetStartPoint2() As SketchPoint
```

SketchHatch (Type)

SOLIDWORKS Type Library

SketchHatch Object

Object Model

SketchHatch

GetSketch (Sketch)

IGetFace (Face)

IGetFace2 (Face2)

SOLIDWORKS Type Library

SketchHatch Object Members

Public Methods

-  [DeSelect](#)
-  [GetFace](#)
-  [GetID](#)
-  [GetSketch](#)
-  [IGetFace](#)
-  [IGetFace2](#)
-  [IGetID](#)
-  [Select](#)
-  [Select2](#)
-  [Select3](#)
-  [Select4](#)
-  [SelectByMark](#)

Public Properties

-  [Angle](#)
-  [Color](#)
-  [Layer](#)
-  [LayerOverride](#)
-  [Pattern](#)
-  [PatternId](#)
-  [Scale](#)
-  [Scale2](#)
-  [SolidFill](#)

SOLIDWORKS Type Library

Angle Property (SketchHatch)

Syntax

Visual Basic for Applications (VBA)

Public Property Angle As Double

SOLIDWORKS Type Library

Color Property (SketchHatch)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Color As Long
```

SOLIDWORKS Type Library

DeSelect Method (SketchHatch)

Syntax

Visual Basic for Applications (VBA)

```
Public Function DeSelect() As Boolean
```

SOLIDWORKS Type Library

GetFace Method (SketchHatch)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFace() As Object
```

SOLIDWORKS Type Library

GetID Method (SketchHatch)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetID() As Variant
```

SOLIDWORKS Type Library

GetSketch Method (SketchHatch)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSketch() As Sketch
```

SOLIDWORKS Type Library

IGetFace Method (SketchHatch)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetFace() As Face
```

SOLIDWORKS Type Library

IGetFace2 Method (SketchHatch)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetFace2() As Face2
```

SOLIDWORKS Type Library

IGetID Method (SketchHatch)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetID() As Long
```

SOLIDWORKS Type Library

Layer Property (SketchHatch)



Syntax

Visual Basic for Applications (VBA)

```
Public Property Layer As String
```

SOLIDWORKS Type Library

LayerOverride Property (SketchHatch)



Syntax

Visual Basic for Applications (VBA)

```
Public Property LayerOverride As Integer
```

SOLIDWORKS Type Library

Pattern Property (SketchHatch)



Syntax

Visual Basic for Applications (VBA)

```
Public Property Pattern As String
```

SOLIDWORKS Type Library

PatternId Property (SketchHatch)



Syntax

Visual Basic for Applications (VBA)

```
Public Property PatternId As Long
```

SOLIDWORKS Type Library

Scale Property (SketchHatch)



Syntax

Visual Basic for Applications (VBA)

```
Public Property Scale As Double
```

SOLIDWORKS Type Library

Scale2 Property (SketchHatch)



Syntax

Visual Basic for Applications (VBA)

```
Public Property Scale2 As Double
```

SOLIDWORKS Type Library

Select Method (SketchHatch)



Syntax

Visual Basic for Applications (VBA)

```
Public Function Select( _  
    ByVal AppendFlag As Boolean _  
    ) As Boolean
```

SOLIDWORKS Type Library

Select2 Method (SketchHatch)



Syntax

Visual Basic for Applications (VBA)

```
Public Function Select2( _  
    ByVal Append As Boolean, _  
    ByVal Mark As Long _  
) As Boolean
```

SOLIDWORKS Type Library

Select3 Method (SketchHatch)



Syntax

Visual Basic for Applications (VBA)

```
Public Function Select3( _  
    ByVal Append As Boolean, _  
    ByVal Mark As Long, _  
    ByVal Callout As Callout _  
) As Boolean
```

SOLIDWORKS Type Library

Select4 Method (SketchHatch)



Syntax

Visual Basic for Applications (VBA)

```
Public Function Select4( _  
    ByVal Append As Boolean, _  
    ByVal Data As SelectData _  
) As Boolean
```

SOLIDWORKS Type Library

SelectByMark Method (SketchHatch)



Syntax

Visual Basic for Applications (VBA)

```
Public Function SelectByMark( _  
    ByVal AppendFlag As Boolean, _  
    ByVal Mark As Long _  
) As Boolean
```

SOLIDWORKS Type Library

SolidFill Property (SketchHatch)



Syntax

Visual Basic for Applications (VBA)


```
Public Property SolidFill As Boolean
```

SketchLine (Type)

SOLIDWORKS Type Library

SketchLine Object

Object Model



SOLIDWORKS Type Library

SketchLine Object Members

Public Methods

	GetBendLineDirection
	GetEndPoint
	GetEndPoint2
	GetStartPoint
	GetStartPoint2
	IGetEndPoint
	IGetEndPoint2
	IGetStartPoint
	IGetStartPoint2
	MakeInfinite

Public Properties

	Angle
	Infinite

SOLIDWORKS Type Library

Angle Property (SketchLine)

Syntax

Visual Basic for Applications (VBA)
Public Property Angle As Double

SOLIDWORKS Type Library

GetBendLineDirection Method (SketchLine)

Syntax

Visual Basic for Applications (VBA)
Public Function GetBendLineDirection() As Long

SOLIDWORKS Type Library

GetEndPoint Method (SketchLine)

Syntax

Visual Basic for Applications (VBA)
Public Function GetEndPoint() As Variant

SOLIDWORKS Type Library

GetEndPoint2 Method (SketchLine)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetEndPoint2() As Object
```

SOLIDWORKS Type Library

GetStartPoint Method (SketchLine)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetStartPoint() As Variant
```

SOLIDWORKS Type Library

GetStartPoint2 Method (SketchLine)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetStartPoint2() As Object
```

SOLIDWORKS Type Library

IGetEndPoint Method (SketchLine)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetEndPoint() As Double
```

SOLIDWORKS Type Library

IGetEndPoint2 Method (SketchLine)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetEndPoint2() As SketchPoint
```

SOLIDWORKS Type Library

IGetStartPoint Method (SketchLine)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetStartPoint() As Double
```

SOLIDWORKS Type Library

IGetStartPoint2 Method (SketchLine)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetStartPoint2() As SketchPoint
```

SOLIDWORKS Type Library

Infinite Property (SketchLine)



Syntax

Visual Basic for Applications (VBA)

```
Public Property Infinite As Boolean
```



Syntax

Visual Basic for Applications (VBA)

```
Public Function MakeInfinite() As Boolean
```