

SOLIDWORKS API (VB6 COM) — Reference (95/102): TablePatternFeatureData- ThickenFeatureData


SOLIDWORKS API Documentation (converted from CHM)

TablePatternFeatureData (Type)

SOLIDWORKS Type Library

TablePatternFeatureData Object

Object Model



SOLIDWORKS Type Library

TablePatternFeatureData Object Members

Public Methods

	AccessSelections
	GetBasePoint
	GetPatternBodyCount
	GetPatternFaceCount
	GetPatternFeatureCount
	GetPointCount
	GetReferencePointType
	GetSkippedItemCount
	GetTransform
	IAccessSelections
	IAccessSelections2
	IGetBasePoint
	IGetPatternBodyArray
	IGetPatternFaceArray
	IGetPatternFeatureArray
	IGetPointArray
	IGetSkippedItemArray
	ISetPatternBodyArray
	ISetPatternFaceArray
	ISetPatternFeatureArray
	ISetPointArray
	ISetSkippedItemArray
	LoadPointsFromFile
	ReleaseSelectionAccess
	SavePointsToFile

Public Properties

	CoordinateSystem
	GeometryPattern
	PatternBodyArray

 PatternFaceArray
 PatternFeatureArray
 PointArray
 PropagateVisualProperty
 ReferencePoint
 SkippedItemArray
 UseCentroid

SOLIDWORKS Type Library

AccessSelections Method (TablePatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AccessSelections( _  
    ByVal TopDoc As Object, _  
    ByVal Component As Object _  
) As Boolean
```

SOLIDWORKS Type Library

CoordinateSystem Property (TablePatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property CoordinateSystem As Object
```

SOLIDWORKS Type Library

GeometryPattern Property (TablePatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property GeometryPattern As Boolean
```

SOLIDWORKS Type Library

GetBasePoint Method (TablePatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetBasePoint() As Variant
```

SOLIDWORKS Type Library

GetPatternBodyCount Method (TablePatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPatternBodyCount() As Long
```

SOLIDWORKS Type Library

GetPatternFaceCount Method (TablePatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPatternFaceCount() As Long
```

SOLIDWORKS Type Library

GetPatternFeatureCount Method (TablePatternFeatureData)



Visual Basic for Applications (VBA)

```
Public Function GetPatternFeatureCount() As Long
```

SOLIDWORKS Type Library

GetPointCount Method (TablePatternFeatureData)



Visual Basic for Applications (VBA)

```
Public Function GetPointCount() As Long
```

SOLIDWORKS Type Library

GetReferencePointType Method (TablePatternFeatureData)



Visual Basic for Applications (VBA)

```
Public Function GetReferencePointType() As Long
```

SOLIDWORKS Type Library

GetSkippedItemCount Method (TablePatternFeatureData)



Visual Basic for Applications (VBA)

```
Public Function GetSkippedItemCount() As Long
```

SOLIDWORKS Type Library

GetTransform Method (TablePatternFeatureData)



Visual Basic for Applications (VBA)

```
Public Function GetTransform( _  
    ByVal Instance As Long _  
) As MathTransform
```

SOLIDWORKS Type Library

IAccessSelections Method (TablePatternFeatureData)



Visual Basic for Applications (VBA)

```
Public Function IAccessSelections( _  
    ByVal TopDoc As ModelDoc, _  
    ByVal Component As Component _  
) As Boolean
```

SOLIDWORKS Type Library

IAccessSelections2 Method (TablePatternFeatureData)



Visual Basic for Applications (VBA)

```
Public Function IAccessSelections2( _  
    ByVal TopDoc As ModelDoc2, _  
    ByVal Component As Component2 _  
) As Boolean
```

SOLIDWORKS Type Library

IGetBasePoint Method (TablePatternFeatureData)



Visual Basic for Applications (VBA)

```
Public Function IGetBasePoint() As Double
```

SOLIDWORKS Type Library

IGetPatternBodyArray Method (TablePatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetPatternBodyArray() As Body2
```

SOLIDWORKS Type Library

IGetPatternFaceArray Method (TablePatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetPatternFaceArray() As Object
```

SOLIDWORKS Type Library

IGetPatternFeatureArray Method (TablePatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetPatternFeatureArray() As Object
```

SOLIDWORKS Type Library

IGetPointArray Method (TablePatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetPointArray() As Double
```

SOLIDWORKS Type Library

IGetSkippedItemArray Method (TablePatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetSkippedItemArray( _  
    ByVal Count As Long _  
) As Long
```

SOLIDWORKS Type Library

ISetPatternBodyArray Method (TablePatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ISetPatternBodyArray( _  
    ByVal BodyCount As Long, _  
    ByVal ArrayDataIn As Body2 _  
)
```

SOLIDWORKS Type Library

ISetPatternFaceArray Method (TablePatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ISetPatternFaceArray( _  
    ByVal FaceCount As Long, _
```

```
ByRef ArrayDataIn As Object _  
)
```

SOLIDWORKS Type Library

ISetPatternFeatureArray Method (TablePatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ISetPatternFeatureArray( _  
    ByVal FeatCount As Long, _  
    ByRef ArrayDataIn As Object _  
)
```

SOLIDWORKS Type Library

ISetPointArray Method (TablePatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ISetPointArray( _  
    ByVal FeatCount As Long, _  
    ByRef ArrayDataIn As Double _  
)
```

SOLIDWORKS Type Library

ISetSkippedItemArray Method (TablePatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ISetSkippedItemArray( _  
    ByVal Count As Long, _  
    ByRef ArrayDataIn As Long _  
)
```

SOLIDWORKS Type Library

LoadPointsFromFile Method (TablePatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function LoadPointsFromFile( _  
    ByVal FileName As String _  
) As Boolean
```

SOLIDWORKS Type Library

PatternBodyArray Property (TablePatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property PatternBodyArray As Variant
```

SOLIDWORKS Type Library

PatternFaceArray Property (TablePatternFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property PatternFaceArray As Variant
```

SOLIDWORKS Type Library

PatternFeatureArray Property (TablePatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Property PatternFeatureArray As Variant
```

SOLIDWORKS Type Library

PointArray Property (TablePatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Property PointArray As Variant
```

SOLIDWORKS Type Library

PropagateVisualProperty Property (TablePatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Property PropagateVisualProperty As Boolean
```

SOLIDWORKS Type Library

ReferencePoint Property (TablePatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Property ReferencePoint As Object
```

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (TablePatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ReleaseSelectionAccess()
```

SOLIDWORKS Type Library

SavePointsToFile Method (TablePatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function SavePointsToFile( _  
    ByVal FileName As String _  
    ) As Boolean
```

SOLIDWORKS Type Library

SkippedItemArray Property (TablePatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Property SkippedItemArray As Variant
```

SOLIDWORKS Type Library

UseCentroid Property (TablePatternFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Property UseCentroid As Boolean
```

TangentMateFeatureData (Type)

SOLIDWORKS Type Library

TangentMateFeatureData Object

Object Model

TangentMateFeatureData

SOLIDWORKS Type Library

TangentMateFeatureData Object Members

Public Properties

- EntitiesToMate
- MateAlignment
- PickPoints

SOLIDWORKS Type Library

EntitiesToMate Property (TangentMateFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property EntitiesToMate As Variant
```

SOLIDWORKS Type Library

MateAlignment Property (TangentMateFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property MateAlignment As Long
```

SOLIDWORKS Type Library

PickPoints Property (TangentMateFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property PickPoints As Variant
```

TaperedTapElementData (Type)

SOLIDWORKS Type Library

TaperedTapElementData Object

Object Model

TaperedTapElementData

SOLIDWORKS Type Library

TaperedTapElementData Object Members

Public Properties

- CustomSizing
- EndConditionOverride
- ThreadClass
- ThreadClassOverride
- UseStandardDepth

SOLIDWORKS Type Library

CustomSizing Property (TaperedTapElementData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property CustomSizing As Long
```

SOLIDWORKS Type Library

EndConditionOverride Property (TaperedTapElementData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property EndCondition0verride As Boolean
```

SOLIDWORKS Type Library

ThreadClass Property (TaperedTapElementData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property ThreadClass As Long
```

SOLIDWORKS Type Library

ThreadClassOverride Property (TaperedTapElementData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property ThreadClass0verride As Boolean
```

SOLIDWORKS Type Library

UseStandardDepth Property (TaperedTapElementData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property UseStandardDepth As Boolean
```

TaskpaneView (Type)

SOLIDWORKS Type Library
TaskpaneView Object

Object Model

TaskpaneView

SOLIDWORKS Type Library
TaskpaneView Object Members

Public Methods

	AddControl
	AddCustomButton
	AddCustomButton2
	AddStandardButton
	DeleteView
	DisplayWindowFromHandle
	DisplayWindowFromHandle64
	GetButtonState
	GetControl
	GetTaskpaneViewWnd
	GetTaskpaneViewWnd64
	HideView
	IGetControl
	IsActiveTab
	SetButtonState
	ShowView

Events

	TaskPaneActivateNotify
	TaskPaneDeactivateNotify
	TaskPaneDestroyNotify
	TaskPaneToolBarButtonClicked

SOLIDWORKS Type Library
AddControl Method (TaskpaneView)

Syntax

```
Visual Basic for Applications (VBA)

Public Function AddControl( _
    ByVal ClassName As String, _
    ByVal LicKey As String _
) As Unknown
```

SOLIDWORKS Type Library
AddCustomButton Method (TaskpaneView)

Syntax

```
Visual Basic for Applications (VBA)
```

```
Public Function AddCustomButton( _  
    ByVal BitmapPath As String, _  
    ByVal ToolTip As String _  
    ) As Boolean
```

SOLIDWORKS Type Library

AddCustomButton2 Method (TaskpaneView)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddCustomButton2( _  
    ByVal ImageList As Variant, _  
    ByVal ToolTip As String _  
    ) As Boolean
```

SOLIDWORKS Type Library

AddStandardButton Method (TaskpaneView)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddStandardButton( _  
    ByVal BitmapOption As Long, _  
    ByVal ToolTip As String _  
    ) As Boolean
```

SOLIDWORKS Type Library

DeleteView Method (TaskpaneView)

Syntax

Visual Basic for Applications (VBA)

```
Public Function DeleteView() As Boolean
```

SOLIDWORKS Type Library

DisplayWindowFromHandle Method (TaskpaneView)

Syntax

Visual Basic for Applications (VBA)

```
Public Function DisplayWindowFromHandle( _  
    ByVal WindowHandle As Long _  
    ) As Boolean
```

SOLIDWORKS Type Library

DisplayWindowFromHandlex64 Method (TaskpaneView)

Syntax

Visual Basic for Applications (VBA)

```
Public Function DisplayWindowFromHandlex64( _  
    ByVal WindowHandle As Unknown _  
    ) As Boolean
```

SOLIDWORKS Type Library

GetButtonState Method (TaskpaneView)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetButtonState( _  
    ByVal ButtonIndex As Long _  
    ) As Boolean
```

SOLIDWORKS Type Library

GetControl Method (TaskpaneView)



Visual Basic for Applications (VBA)

```
Public Function GetControl() As Object
```

SOLIDWORKS Type Library

GetTaskpaneViewWnd Method (TaskpaneView)



Visual Basic for Applications (VBA)

```
Public Function GetTaskpaneViewWnd() As Long
```

SOLIDWORKS Type Library

GetTaskpaneViewWndx64 Method (TaskpaneView)



Visual Basic for Applications (VBA)

```
Public Function GetTaskpaneViewWndx64() As Unknown
```

SOLIDWORKS Type Library

HideView Method (TaskpaneView)



Visual Basic for Applications (VBA)

```
Public Function HideView() As Boolean
```

SOLIDWORKS Type Library

IGetControl Method (TaskpaneView)



Visual Basic for Applications (VBA)

```
Public Function IGetControl() As Unknown
```

SOLIDWORKS Type Library

IsActiveTab Method (TaskpaneView)



Visual Basic for Applications (VBA)

```
Public Function IsActiveTab() As Boolean
```

SOLIDWORKS Type Library

SetButtonState Method (TaskpaneView)



Visual Basic for Applications (VBA)

```
Public Sub SetButtonState( _  
    ByVal ButtonIndex As Long, _  
    ByVal Enable As Boolean _  
)
```

SOLIDWORKS Type Library

ShowView Method (TaskpaneView)



Visual Basic for Applications (VBA)

```
Public Function ShowView() As Boolean
```

SOLIDWORKS Type Library

TaskPaneActivateNotify Event (TaskpaneView)



Syntax

Visual Basic for Applications (VBA)

```
Public Event TaskPaneActivateNotify()
```

SOLIDWORKS Type Library

TaskPaneDeactivateNotify Event (TaskpaneView)



Syntax

Visual Basic for Applications (VBA)

```
Public Event TaskPaneDeactivateNotify()
```

SOLIDWORKS Type Library

TaskPaneDestroyNotify Event (TaskpaneView)



Syntax

Visual Basic for Applications (VBA)

```
Public Event TaskPaneDestroyNotify()
```

SOLIDWORKS Type Library

TaskPaneToolBarButtonClicked Event (TaskpaneView)



Syntax

Visual Basic for Applications (VBA)

```
Public Event TaskPaneToolBarButtonClicked( _  
    ByVal ButtonIndex As Long _  
)
```

Tessellation (Type)

SOLIDWORKS Type Library

Tessellation Object

Object Model

Tessellation

IGetFacetFace (Face)

IGetFacetFace2 (Face2)

IGetFinEdge (Edge)

SOLIDWORKS Type Library

Tessellation Object Members

Public Methods

	GetEdgeFins
	GetErrorList
	GetFaceFacets
	GetFacetCount
	GetFacetFace
	GetFacetFins
	GetFinCgFin
	GetFinCount
	GetFinEdge
	GetFinVertices
	GetVertexCount
	GetVertexNormal
	GetVertexParams
	GetVertexPoint
	IGetEdgeFins
	IGetEdgeFinsCount
	IGetErrorList
	IGetErrorList2
	IGetErrorListCount
	IGetFaceFacets
	IGetFaceFacets2
	IGetFaceFacetsCount
	IGetFaceFacetsCount2
	IGetFacetFace
	IGetFacetFace2
	IGetFacetFins
	IGetFacetFinsCount
	IGetFinEdge

 IGetFinVertices
 IGetVertexNormal
 IGetVertexParams
 IGetVertexPoint
 Tessellate

Public Properties

 CurveChordAngleTolerance
 CurveChordTolerance
 ImprovedQuality
 MatchType
 MaxFacetWidth
 MinFacetWidth
 NeedEdgeFinMap
 NeedErrorList
 NeedFaceFacetMap
 NeedVertexNormal
 NeedVertexParams
 SurfacePlaneAngleTolerance
 SurfacePlaneTolerance

SOLIDWORKS Type Library

CurveChordAngleTolerance Property (Tessellation)

Syntax

Visual Basic for Applications (VBA)
Public Property CurveChordAngleTolerance As Double

SOLIDWORKS Type Library

CurveChordTolerance Property (Tessellation)

Syntax

Visual Basic for Applications (VBA)
Public Property CurveChordTolerance As Double

SOLIDWORKS Type Library

GetEdgeFins Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)
Public Function GetEdgeFins(_ ByVal <i>EdgeDisp</i> As Object _) As Variant

SOLIDWORKS Type Library

GetErrorList Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)
Public Sub GetErrorList(_ ByRef <i>FaceErrArray</i> As Variant, _ ByRef <i>FacetErrArray</i> As Variant, _

```
ByRef VertexPointErrArray As Variant, _  
ByRef VertexNormalErrArray As Variant, _  
ByRef VertexParamsErrArray As Variant _  
)
```

SOLIDWORKS Type Library

GetFaceFacets Method (Tessellation)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFaceFacets( _  
    ByVal Facedisp As Object _  
) As Variant
```

SOLIDWORKS Type Library

GetFacetCount Method (Tessellation)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFacetCount() As Long
```

SOLIDWORKS Type Library

GetFacetFace Method (Tessellation)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFacetFace( _  
    ByVal FacetId As Long _  
) As Object
```

SOLIDWORKS Type Library

GetFacetFins Method (Tessellation)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFacetFins( _  
    ByVal FacetId As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetFinCoFin Method (Tessellation)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFinCoFin( _  
    ByVal FinId As Long _  
) As Long
```

SOLIDWORKS Type Library

GetFinCount Method (Tessellation)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFinCount() As Long
```

SOLIDWORKS Type Library

GetFinEdge Method (Tessellation)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFinEdge( _  
    ByVal FinId As Long _  
) As Object
```

SOLIDWORKS Type Library

GetFinVertices Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFinVertices( _  
    ByVal FinId As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetVertexCount Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetVertexCount() As Long
```

SOLIDWORKS Type Library

GetVertexNormal Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetVertexNormal( _  
    ByVal VertexId As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetVertexParams Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetVertexParams( _  
    ByVal VertexId As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetVertexPoint Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetVertexPoint( _  
    ByVal VertexId As Long _  
) As Variant
```

SOLIDWORKS Type Library

IGetEdgeFins Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetEdgeFins( _  
    ByVal EdgeObj As Edge _  
) As Long
```

SOLIDWORKS Type Library

IGetEdgeFinsCount Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetEdgeFinsCount( _  
    ByVal EdgeObj As Edge _  
) As Long
```

SOLIDWORKS Type Library

IGetErrorList Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub IGetErrorList( _  
    ByRef FaceErrArray As Face, _  
    ByRef FacetErrArray As Long, _  
    ByRef VertexPointErrArray As Long, _  
    ByRef VertexNormalErrArray As Long, _  
    ByRef VertexParamsErrArray As Long _  
)
```

SOLIDWORKS Type Library

IGetErrorList2 Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub IGetErrorList2( _  
    ByRef FaceErrArray As Face2, _  
    ByRef FacetErrArray As Long, _  
    ByRef VertexPointErrArray As Long, _  
    ByRef VertexNormalErrArray As Long, _  
    ByRef VertexParamsErrArray As Long _  
)
```

SOLIDWORKS Type Library

IGetErrorListCount Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub IGetErrorListCount( _  
    ByRef FaceErrArrayCount As Long, _  
    ByRef FacetErrArrayCount As Long, _  
    ByRef VertexPointErrArrayCount As Long, _  
    ByRef VertexNormalErrArrayCount As Long, _  
    ByRef VertexParamsErrArrayCount As Long _  
)
```

SOLIDWORKS Type Library

IGetFaceFacets Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetFaceFacets( _  
    ByVal FaceObj As Face _  
) As Long
```

SOLIDWORKS Type Library

IGetFaceFacets2 Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetFaceFacets2( _  
    ByVal FaceObj As Face2 _
```

) As Long

SOLIDWORKS Type Library

IGetFaceFacetsCount Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetFaceFacetsCount( _  
    ByVal FaceObj As Face _  
    ) As Long
```

SOLIDWORKS Type Library

IGetFaceFacetsCount2 Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetFaceFacetsCount2( _  
    ByVal FaceObj As Face2 _  
    ) As Long
```

SOLIDWORKS Type Library

IGetFacetFace Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetFacetFace( _  
    ByVal FacetId As Long _  
    ) As Face
```

SOLIDWORKS Type Library

IGetFacetFace2 Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetFacetFace2( _  
    ByVal FacetId As Long _  
    ) As Face2
```

SOLIDWORKS Type Library

IGetFacetFins Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetFacetFins( _  
    ByVal FacetId As Long _  
    ) As Long
```

SOLIDWORKS Type Library

IGetFacetFinsCount Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetFacetFinsCount( _  
    ByVal FacetId As Long _  
    ) As Long
```

SOLIDWORKS Type Library

IGetFinEdge Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetFinEdge( _  
    ByVal FinId As Long _  
) As Edge
```

SOLIDWORKS Type Library

IGetFinVertices Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetFinVertices( _  
    ByVal FinId As Long _  
) As Long
```

SOLIDWORKS Type Library

IGetVertexNormal Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetVertexNormal( _  
    ByVal VertexId As Long _  
) As Double
```

SOLIDWORKS Type Library

IGetVertexParams Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetVertexParams( _  
    ByVal VertexId As Long _  
) As Double
```

SOLIDWORKS Type Library

IGetVertexPoint Method (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetVertexPoint( _  
    ByVal VertexId As Long _  
) As Double
```

SOLIDWORKS Type Library

ImprovedQuality Property (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Property ImprovedQuality As Boolean
```

SOLIDWORKS Type Library

MatchType Property (Tessellation)

Syntax

Visual Basic for Applications (VBA)

```
Public Property MatchType As Long
```

SOLIDWORKS Type Library

MaxFacetWidth Property (Tessellation)



Visual Basic for Applications (VBA)

Public Property MaxFacetWidth As Double

SOLIDWORKS Type Library

MinFacetWidth Property (Tessellation)



Visual Basic for Applications (VBA)

Public Property MinFacetWidth As Double

SOLIDWORKS Type Library

NeedEdgeFinMap Property (Tessellation)



Visual Basic for Applications (VBA)

Public Property NeedEdgeFinMap As Boolean

SOLIDWORKS Type Library

NeedErrorList Property (Tessellation)



Visual Basic for Applications (VBA)

Public Property NeedErrorList As Boolean

SOLIDWORKS Type Library

NeedFaceFacetMap Property (Tessellation)



Visual Basic for Applications (VBA)

Public Property NeedFaceFacetMap As Boolean

SOLIDWORKS Type Library

NeedVertexNormal Property (Tessellation)



Visual Basic for Applications (VBA)

Public Property NeedVertexNormal As Boolean

SOLIDWORKS Type Library

NeedVertexParams Property (Tessellation)



Visual Basic for Applications (VBA)

Public Property NeedVertexParams As Boolean

SOLIDWORKS Type Library

SurfacePlaneAngleTolerance Property (Tessellation)



Visual Basic for Applications (VBA)

Public Property SurfacePlaneAngleTolerance As Double

SOLIDWORKS Type Library

SurfacePlaneTolerance Property (Tessellation)



Syntax

Visual Basic for Applications (VBA)

Public Property SurfacePlaneTolerance As Double

SOLIDWORKS Type Library

Tessellate Method (Tessellation)



Syntax

Visual Basic for Applications (VBA)

Public Function Tessellate() As Boolean

TextAndCustomProperty (Type)

SOLIDWORKS Type Library
TextAndCustomProperty Object

Object Model

TextAndCustomProperty

SOLIDWORKS Type Library
TextAndCustomProperty Object Members

Public Properties

 CustomPropertyName
 Description
 IsCustomProperty
 Name
 Value

SOLIDWORKS Type Library
CustomPropertyName Property (TextAndCustomProperty)

Syntax

```
Visual Basic for Applications (VBA)  
  
Public Property CustomPropertyName As String
```

SOLIDWORKS Type Library
Description Property (TextAndCustomProperty)

Syntax

```
Visual Basic for Applications (VBA)  
  
Public Property Description As String
```

SOLIDWORKS Type Library
IsCustomProperty Property (TextAndCustomProperty)

Syntax

```
Visual Basic for Applications (VBA)  
  
Public Property IsCustomProperty As Boolean
```

SOLIDWORKS Type Library
Name Property (TextAndCustomProperty)

Syntax

```
Visual Basic for Applications (VBA)  
  
Public Property Name As String
```

SOLIDWORKS Type Library
Value Property (TextAndCustomProperty)

Syntax

```
Visual Basic for Applications (VBA)  
  
Public Property Value As String
```

TextFormat (Type)

SOLIDWORKS Type Library

TextFormat Object

Object Model

TextFormat

SOLIDWORKS Type Library

TextFormat Object Members

Public Methods

	GetAllValues
	IGetAllValues
	IsHeightSpecifiedInPts

Public Properties

	BackWards
	Bold
	CharHeight
	CharHeightInPts
	CharSpacingFactor
	Escapement
	Italic
	LineLength
	LineSpacing
	ObliqueAngle
	Strikeout
	TypeFaceName
	Underline
	UpsideDown
	Vertical
	WidthFactor

SOLIDWORKS Type Library

BackWards Property (TextFormat)

Syntax

Visual Basic for Applications (VBA)
Public Property BackWards As Boolean

SOLIDWORKS Type Library

Bold Property (TextFormat)

Syntax

Visual Basic for Applications (VBA)
Public Property Bold As Boolean

SOLIDWORKS Type Library

CharHeight Property (TextFormat)



Visual Basic for Applications (VBA)

```
Public Property CharHeight As Double
```

SOLIDWORKS Type Library

CharHeightInPts Property (TextFormat)



Visual Basic for Applications (VBA)

```
Public Property CharHeightInPts As Integer
```

SOLIDWORKS Type Library

CharSpacingFactor Property (TextFormat)



Visual Basic for Applications (VBA)

```
Public Property CharSpacingFactor As Double
```

SOLIDWORKS Type Library

Escapement Property (TextFormat)



Visual Basic for Applications (VBA)

```
Public Property Escapement As Double
```

SOLIDWORKS Type Library

GetAllValues Method (TextFormat)



Visual Basic for Applications (VBA)

```
Public Function GetAllValues() As Variant
```

SOLIDWORKS Type Library

IGetAllValues Method (TextFormat)



Visual Basic for Applications (VBA)

```
Public Function IGetAllValues( _  
    ByVal Count As Long _  
    ) As Double
```

SOLIDWORKS Type Library

IsHeightSpecifiedInPts Method (TextFormat)



Visual Basic for Applications (VBA)

```
Public Function IsHeightSpecifiedInPts() As Boolean
```

SOLIDWORKS Type Library

Italic Property (TextFormat)



Visual Basic for Applications (VBA)

```
Public Property Italic As Boolean
```

SOLIDWORKS Type Library

LineLength Property (TextFormat)



Visual Basic for Applications (VBA)

```
Public Property LineLength As Double
```

SOLIDWORKS Type Library

LineSpacing Property (TextFormat)



Visual Basic for Applications (VBA)

```
Public Property LineSpacing As Double
```

SOLIDWORKS Type Library

ObliqueAngle Property (TextFormat)



Visual Basic for Applications (VBA)

```
Public Property ObliqueAngle As Double
```

SOLIDWORKS Type Library

Strikeout Property (TextFormat)



Visual Basic for Applications (VBA)

```
Public Property Strikeout As Boolean
```

SOLIDWORKS Type Library

TypeFaceName Property (TextFormat)



Visual Basic for Applications (VBA)

```
Public Property TypeFaceName As String
```

SOLIDWORKS Type Library

Underline Property (TextFormat)



Visual Basic for Applications (VBA)

```
Public Property Underline As Boolean
```

SOLIDWORKS Type Library

UpsideDown Property (TextFormat)



Visual Basic for Applications (VBA)

```
Public Property UpsideDown As Boolean
```

SOLIDWORKS Type Library

Vertical Property (TextFormat)



Visual Basic for Applications (VBA)

```
Public Property Vertical As Boolean
```



Syntax

Visual Basic for Applications (VBA)

Public Property WidthFactor As Double

Texture (Type)

SOLIDWORKS Type Library

Texture Object

Object Model

Texture

SOLIDWORKS Type Library

Texture Object Members

Public Methods

GetSystemTextureName

Public Properties

Angle

BlendColor

DecalType

IgnoreColorMaterial

MaterialName

ScaleFactor

TransX

TransY

UDir

VDir

VScale

SOLIDWORKS Type Library

Angle Property (Texture)

Syntax

Visual Basic for Applications (VBA)

Public Property Angle As Double

SOLIDWORKS Type Library

BlendColor Property (Texture)

Syntax

Visual Basic for Applications (VBA)

Public Property BlendColor As Boolean

SOLIDWORKS Type Library

DecalType Property (Texture)

Syntax

Visual Basic for Applications (VBA)

Public Property DecalType As Boolean

SOLIDWORKS Type Library

GetSystemTextureName Method (Texture)



Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSystemTextureName( _  
    ByVal FileNameIn As String, _  
    ByRef Res As Boolean _  
    ) As String
```

SOLIDWORKS Type Library

IgnoreColorMaterial Property (Texture)



Syntax

Visual Basic for Applications (VBA)

```
Public Property IgnoreColorMaterial As Boolean
```

SOLIDWORKS Type Library

MaterialName Property (Texture)



Syntax

Visual Basic for Applications (VBA)

```
Public Property MaterialName As String
```

SOLIDWORKS Type Library

ScaleFactor Property (Texture)



Syntax

Visual Basic for Applications (VBA)

```
Public Property ScaleFactor As Double
```

SOLIDWORKS Type Library

TransX Property (Texture)



Syntax

Visual Basic for Applications (VBA)

```
Public Property TransX As Double
```

SOLIDWORKS Type Library

TransY Property (Texture)



Syntax

Visual Basic for Applications (VBA)

```
Public Property TransY As Double
```

SOLIDWORKS Type Library

UDir Property (Texture)



Syntax

Visual Basic for Applications (VBA)

```
Public Property UDir As Double
```

SOLIDWORKS Type Library

VDir Property (Texture)



Syntax

Visual Basic for Applications (VBA)

```
Public Property VDir As Double
```

SOLIDWORKS Type Library



Syntax


Visual Basic for Applications (VBA)

```
Public Property VScale As Double
```

ThickenFeatureData (Type)

SOLIDWORKS Type Library
ThickenFeatureData Object

Object Model



SOLIDWORKS Type Library
ThickenFeatureData Object Members

Public Methods

	AccessSelections
	GetFeatureScopeBodiesCount
	IAccessSelections
	IGetFeatureScopeBodies
	IsBossFeature
	ISetFeatureScopeBodies
	ReleaseSelectionAccess

Public Properties

	AutoSelect
	FeatureScope
	FeatureScopeBodies
	FillVolume
	Merge
	Surface
	Thickness
	ThicknessSide

SOLIDWORKS Type Library
AccessSelections Method (ThickenFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Function AccessSelections( _
    ByVal TopDoc As Object, _
    ByVal Component As Object _
) As Boolean
```

SOLIDWORKS Type Library
AutoSelect Property (ThickenFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property AutoSelect As Boolean
```

SOLIDWORKS Type Library
FeatureScope Property (ThickenFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property FeatureScope As Boolean

SOLIDWORKS Type Library

FeatureScopeBodies Property (ThickenFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property FeatureScopeBodies As Variant

SOLIDWORKS Type Library

FillVolume Property (ThickenFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property FillVolume As Boolean

SOLIDWORKS Type Library

GetFeatureScopeBodiesCount Method (ThickenFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Function GetFeatureScopeBodiesCount() As Long

SOLIDWORKS Type Library

IAccessSelections Method (ThickenFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IAccessSelections( _  
    ByVal TopDoc As ModelDoc2, _  
    ByVal Component As Component2 _  
    ) As Boolean
```

SOLIDWORKS Type Library

IGetFeatureScopeBodies Method (ThickenFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetFeatureScopeBodies( _  
    ByVal Count As Long _  
    ) As Body2
```

SOLIDWORKS Type Library

IsBossFeature Method (ThickenFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Function IsBossFeature() As Boolean

SOLIDWORKS Type Library

ISetFeatureScopeBodies Method (ThickenFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ISetFeatureScopeBodies( _  
    ByVal Count As Long, _  
    ByVal BodyArr As Body2 _  
)
```

SOLIDWORKS Type Library

Merge Property (ThickenFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Property Merge As Boolean
```

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (ThickenFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ReleaseSelectionAccess()
```

SOLIDWORKS Type Library

Surface Property (ThickenFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Property Surface As Object
```

SOLIDWORKS Type Library

Thickness Property (ThickenFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Property Thickness As Double
```

SOLIDWORKS Type Library

ThicknessSide Property (ThickenFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Property ThicknessSide As Integer
```