

SOLIDWORKS API (VB6 COM) — Reference (96/102): ThreadFeatureData- VariableFilletFeatureData

SOLIDWORKS API Documentation (converted from CHM)

ThreadFeatureData (Type)

SOLIDWORKS Type Library

ThreadFeatureData Object

 Object Model

ThreadFeatureData

Edge

SOLIDWORKS Type Library

ThreadFeatureData Object Members

 Public Methods

	AccessSelections
	GetEndConditionReference
	InitializeThreadData
	ReleaseSelectionAccess
	SetEndConditionReference

 Public Properties

	BlindDepth
	Diameter
	DiameterOverride
	Edge
	EndCondition
	EndConditionOffset
	EndConditionOffsetDistance
	EndConditionOffsetReverse
	MaintainThreadLength
	MirrorProfile
	MirrorType
	MultipleStart
	NumberOfStarts
	Offset
	OffsetDistance
	Pitch
	PitchOverride
	ProfileLocation
	ReverseDirection
	ReverseOffset
	Revolutions
	RightHanded
	RotationAngle
	Size
	StartEntity



[ThreadMethod](#)



[ThreadStartAngle](#)



[TrimEndFace](#)



[TrimStartFace](#)



[Type](#)

SOLIDWORKS Type Library

AccessSelections Method (ThreadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AccessSelections( _  
    ByVal TopDoc As ModelDoc, _  
    ByVal Component As Component _  
    ) As Boolean
```

SOLIDWORKS Type Library

BlindDepth Property (ThreadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property BlindDepth As Double
```

SOLIDWORKS Type Library

Diameter Property (ThreadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Diameter As Double
```

SOLIDWORKS Type Library

DiameterOverride Property (ThreadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property DiameterOverride As Boolean
```

SOLIDWORKS Type Library

Edge Property (ThreadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Edge As Edge
```

SOLIDWORKS Type Library

EndCondition Property (ThreadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property EndCondition As Long
```

SOLIDWORKS Type Library

EndConditionOffset Property (ThreadFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property EndConditionOffset As Boolean

SOLIDWORKS Type Library

EndConditionOffsetDistance Property (ThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property EndConditionOffsetDistance As Double

SOLIDWORKS Type Library

EndConditionOffsetReverse Property (ThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property EndConditionOffsetReverse As Boolean

SOLIDWORKS Type Library

GetEndConditionReference Method (ThreadFeatureData)



Visual Basic for Applications (VBA)

Public Function GetEndConditionReference() As Object

SOLIDWORKS Type Library

InitializeThreadData Method (ThreadFeatureData)



Visual Basic for Applications (VBA)

Public Sub InitializeThreadData()

SOLIDWORKS Type Library

MaintainThreadLength Property (ThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property MaintainThreadLength As Boolean

SOLIDWORKS Type Library

MirrorProfile Property (ThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property MirrorProfile As Boolean

SOLIDWORKS Type Library

MirrorType Property (ThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property MirrorType As Long

SOLIDWORKS Type Library

MultipleStart Property (ThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property MultipleStart As Boolean

SOLIDWORKS Type Library

NumberOfStarts Property (ThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property NumberOfStarts As Long

SOLIDWORKS Type Library

Offset Property (ThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property Offset As Boolean

SOLIDWORKS Type Library

OffsetDistance Property (ThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property OffsetDistance As Double

SOLIDWORKS Type Library

Pitch Property (ThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property Pitch As Double

SOLIDWORKS Type Library

PitchOverride Property (ThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property PitchOverride As Boolean

SOLIDWORKS Type Library

ProfileLocation Property (ThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property ProfileLocation As Object

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (ThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Sub ReleaseSelectionAccess()

SOLIDWORKS Type Library

ReverseDirection Property (ThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property ReverseDirection As Boolean

SOLIDWORKS Type Library

ReverseOffset Property (ThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property ReverseOffset As Boolean

SOLIDWORKS Type Library

Revolutions Property (ThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property Revolutions As Double

SOLIDWORKS Type Library

RightHanded Property (ThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property RightHanded As Boolean

SOLIDWORKS Type Library

RotationAngle Property (ThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property RotationAngle As Double

SOLIDWORKS Type Library

SetEndConditionReference Method (ThreadFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub SetEndConditionReference( _  
    ByVal Value As Object _  
)
```

SOLIDWORKS Type Library

Size Property (ThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property Size As String

SOLIDWORKS Type Library

StartEntity Property (ThreadFeatureData)



Visual Basic for Applications (VBA)

Public Property StartEntity As Object

SOLIDWORKS Type Library

ThreadMethod Property (ThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property ThreadMethod As Long

SOLIDWORKS Type Library

ThreadStartAngle Property (ThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property ThreadStartAngle As Double

SOLIDWORKS Type Library

TrimEndFace Property (ThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property TrimEndFace As Boolean

SOLIDWORKS Type Library

TrimStartFace Property (ThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)

Public Property TrimStartFace As Boolean

SOLIDWORKS Type Library

Type Property (ThreadFeatureData)



Syntax

Visual Basic for Applications (VBA)


Public Property Type As String

TitleBlock (Type)

SOLIDWORKS Type Library

TitleBlock Object

Object Model



SOLIDWORKS Type Library

TitleBlock Object Members

Public Methods

	GetExtents
	GetFeature
	GetNoteCount
	GetNotes
	IGetNotes
	SetExtents

SOLIDWORKS Type Library

GetExtents Method (TitleBlock)

Syntax

```
Visual Basic for Applications (VBA)

Public Sub GetExtents( _
    ByRef XUpperLeft As Double, _
    ByRef YUpperLeft As Double, _
    ByRef XLowerRight As Double, _
    ByRef YLowerRight As Double _
)
```

SOLIDWORKS Type Library

GetFeature Method (TitleBlock)

Syntax

```
Visual Basic for Applications (VBA)

Public Function GetFeature() As Feature
```

SOLIDWORKS Type Library

GetNoteCount Method (TitleBlock)

Syntax

```
Visual Basic for Applications (VBA)

Public Function GetNoteCount() As Long
```

SOLIDWORKS Type Library

GetNotes Method (TitleBlock)

Syntax

```
Visual Basic for Applications (VBA)
```

```
Public Function GetNotes() As Variant
```

SOLIDWORKS Type Library

IGetNotes Method (TitleBlock)



Visual Basic for Applications (VBA)

```
Public Function IGetNotes( _  
    ByVal Count As Long _  
) As Note
```

SOLIDWORKS Type Library

SetExtents Method (TitleBlock)



Visual Basic for Applications (VBA)

```
Public Sub SetExtents( _  
    ByVal XUpperLeft As Double, _  
    ByVal YUpperLeft As Double, _  
    ByVal XLowerRight As Double, _  
    ByVal YLowerRight As Double _  
)
```

TitleBlockTableAnnotation (Type)

SOLIDWORKS Type Library

TitleBlockTableAnnotation Object

Object Model

TitleBlockTableAnnotation

TitleBlockTableFeature

SOLIDWORKS Type Library

TitleBlockTableAnnotation Object Members

Public Properties

TitleBlockTableFeature

SOLIDWORKS Type Library

TitleBlockTableFeature Property (TitleBlockTableAnnotation)

Syntax

Visual Basic for Applications (VBA)

Public Property TitleBlockTableFeature As [TitleBlockTableFeature](#)

TitleBlockTableFeature (Type)

SOLIDWORKS Type Library
TitleBlockTableFeature Object

Object Model



SOLIDWORKS Type Library
TitleBlockTableFeature Object Members

Public Methods

	GetFeature
	GetTableAnnotationCount
	GetTableAnnotations
	IGetTableAnnotations

SOLIDWORKS Type Library
GetFeature Method (TitleBlockTableFeature)

Syntax

```
Visual Basic for Applications (VBA)

Public Function GetFeature() As Feature
```

SOLIDWORKS Type Library
GetTableAnnotationCount Method (TitleBlockTableFeature)

Syntax

```
Visual Basic for Applications (VBA)

Public Function GetTableAnnotationCount() As Long
```

SOLIDWORKS Type Library
GetTableAnnotations Method (TitleBlockTableFeature)

Syntax

```
Visual Basic for Applications (VBA)

Public Function GetTableAnnotations() As Variant
```

SOLIDWORKS Type Library
IGetTableAnnotations Method (TitleBlockTableFeature)

Syntax

```
Visual Basic for Applications (VBA)


Public Function IGetTableAnnotations( _
    ByVal Count As Long _
) As TitleBlockTableAnnotation
```

ToolingSplitFeatureData (Type)

SOLIDWORKS Type Library

ToolingSplitFeatureData Object

Object Model



SOLIDWORKS Type Library

ToolingSplitFeatureData Object Members

Public Methods

	AccessSelections
	GetCavitySurfacesCount
	GetCoreSurfacesCount
	GetPartingSurfacesCount
	IGetCavitySurfaces
	IGetCoreSurfaces
	IGetPartingSurfaces
	ISetCavitySurfaces
	ISetCoreSurfaces
	ISetPartingSurfaces
	ReleaseSelectionAccess

Public Properties

	Angle
	CavitySurfaces
	CoreSurfaces
	Depth
	InterlockSurface
	PartingSurfaces

SOLIDWORKS Type Library

AccessSelections Method (ToolingSplitFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Function AccessSelections( _
    ByVal TopDoc As ModelDoc2, _
    ByVal Component As Component2 _
) As Boolean
```

SOLIDWORKS Type Library

Angle Property (ToolingSplitFeatureData)



Visual Basic for Applications (VBA)

```
Public Property Angle As Double
```

SOLIDWORKS Type Library

CavitySurfaces Property (ToolingSplitFeatureData)



Visual Basic for Applications (VBA)

```
Public Property CavitySurfaces As Variant
```

SOLIDWORKS Type Library

CoreSurfaces Property (ToolingSplitFeatureData)



Visual Basic for Applications (VBA)

```
Public Property CoreSurfaces As Variant
```

SOLIDWORKS Type Library

Depth Property (ToolingSplitFeatureData)



Visual Basic for Applications (VBA)

```
Public Property Depth( _  
    ByVal Dir As Long _  
) As Double
```

SOLIDWORKS Type Library

GetCavitySurfacesCount Method (ToolingSplitFeatureData)



Visual Basic for Applications (VBA)

```
Public Function GetCavitySurfacesCount() As Long
```

SOLIDWORKS Type Library

GetCoreSurfacesCount Method (ToolingSplitFeatureData)



Visual Basic for Applications (VBA)

```
Public Function GetCoreSurfacesCount() As Long
```

SOLIDWORKS Type Library

GetPartingSurfacesCount Method (ToolingSplitFeatureData)



Visual Basic for Applications (VBA)

```
Public Function GetPartingSurfacesCount() As Long
```

SOLIDWORKS Type Library

IGetCavitySurfaces Method (ToolingSplitFeatureData)



Visual Basic for Applications (VBA)

```
Public Function IGetCavitySurfaces( _  
    ByVal Count As Long _  
) As Body2
```

IGetCoreSurfaces Method (ToolingSplitFeatureData) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function IGetCoreSurfaces( _  
    ByVal Count As Long _  
) As Body2
```

IGetPartingSurfaces Method (ToolingSplitFeatureData) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function IGetPartingSurfaces( _  
    ByVal Count As Long _  
) As Body2
```

InterlockSurface Property (ToolingSplitFeatureData) **Syntax**

Visual Basic for Applications (VBA)

```
Public Property InterlockSurface As Boolean
```

ISetCavitySurfaces Method (ToolingSplitFeatureData) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub ISetCavitySurfaces( _  
    ByVal Count As Long, _  
    ByVal BodyArr As Body2 _  
)
```

ISetCoreSurfaces Method (ToolingSplitFeatureData) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub ISetCoreSurfaces( _  
    ByVal Count As Long, _  
    ByVal BodyArr As Body2 _  
)
```

ISetPartingSurfaces Method (ToolingSplitFeatureData) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub ISetPartingSurfaces( _  
    ByVal Count As Long, _  
    ByVal BodyArr As Body2 _  
)
```

PartingSurfaces Property (ToolingSplitFeatureData) **Syntax**

Visual Basic for Applications (VBA)

Public Property PartingSurfaces As Variant

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (ToolingSplitFeatureData)




Visual Basic for Applications (VBA)

Public Sub ReleaseSelectionAccess()

TreeControlItem (Type)

SOLIDWORKS Type Library
TreeControlItem Object

Object Model



SOLIDWORKS Type Library
TreeControlItem Object Members

Public Methods

	GetFirstChild
	GetNext
	GetParent
	GetPrevious
	GetRoot

Public Properties

	Expanded
	IsRoot
	Object
	ObjectType
	Text

SOLIDWORKS Type Library
Expanded Property (TreeControlItem)

Syntax

Visual Basic for Applications (VBA)
Public Property Expanded As Boolean

SOLIDWORKS Type Library
GetFirstChild Method (TreeControlItem)

Syntax

Visual Basic for Applications (VBA)
Public Function GetFirstChild() As TreeControlItem

SOLIDWORKS Type Library
GetNext Method (TreeControlItem)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNext() As TreeControlItem
```

SOLIDWORKS Type Library

GetParent Method (TreeControlItem)



Visual Basic for Applications (VBA)

```
Public Function GetParent() As TreeControlItem
```

SOLIDWORKS Type Library

GetPrevious Method (TreeControlItem)



Visual Basic for Applications (VBA)

```
Public Function GetPrevious() As TreeControlItem
```

SOLIDWORKS Type Library

GetRoot Method (TreeControlItem)



Visual Basic for Applications (VBA)

```
Public Function GetRoot() As TreeControlItem
```

SOLIDWORKS Type Library

IsRoot Property (TreeControlItem)



Visual Basic for Applications (VBA)

```
Public Property IsRoot As Boolean
```

SOLIDWORKS Type Library

Object Property (TreeControlItem)



Visual Basic for Applications (VBA)

```
Public Property Object As Object
```

SOLIDWORKS Type Library

ObjectType Property (TreeControlItem)



Visual Basic for Applications (VBA)

```
Public Property ObjectType As Long
```

SOLIDWORKS Type Library

Text Property (TreeControlItem)




Visual Basic for Applications (VBA)

```
Public Property Text As String
```

TriadManipulator (Type)

SOLIDWORKS Type Library
TriadManipulator Object

Object Model



SOLIDWORKS Type Library
TriadManipulator Object Members

Public Methods

	SetColorRefAtIndex
	UpdatePosition
	UpdateScale

Public Properties

	Cursor
	DoNotShow
	Origin
	PreviousDragPoint
	XAxis
	YAxis
	ZAxis

SOLIDWORKS Type Library
Cursor Property (TriadManipulator)

Syntax

Visual Basic for Applications (VBA)
Public Property Cursor

SOLIDWORKS Type Library
DoNotShow Property (TriadManipulator)

Syntax

Visual Basic for Applications (VBA)
Public Property DoNotShow As Long

SOLIDWORKS Type Library
Origin Property (TriadManipulator)

Syntax

Public Property Origin As [MathPoint](#)

SOLIDWORKS Type Library

PreviousDragPoint Property (TriadManipulator)



Syntax

Visual Basic for Applications (VBA)

Public Property PreviousDragPoint As [MathPoint](#)

SOLIDWORKS Type Library

SetColorRefAtIndex Method (TriadManipulator)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetColorRefAtIndex( _  
    ByVal Index As Long, _  
    ByVal ColorRef As Long _  
)
```

SOLIDWORKS Type Library

UpdatePosition Method (TriadManipulator)



Syntax

Visual Basic for Applications (VBA)

Public Function UpdatePosition() As Boolean

SOLIDWORKS Type Library

UpdateScale Method (TriadManipulator)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub UpdateScale( _  
    ByVal Scale As Double _  
)
```

SOLIDWORKS Type Library

XAxis Property (TriadManipulator)



Syntax

Visual Basic for Applications (VBA)

Public Property XAxis As [MathVector](#)

SOLIDWORKS Type Library

YAxis Property (TriadManipulator)



Syntax

Visual Basic for Applications (VBA)

Public Property YAxis As [MathVector](#)

SOLIDWORKS Type Library

ZAxis Property (TriadManipulator)



Syntax

Visual Basic for Applications (VBA)

Public Property ZAxis As [MathVector](#)

TwoMemberCornerTreatmentFeatureData (Type)

SOLIDWORKS Type Library

TwoMemberCornerTreatmentFeatureData Object

 Object Model

TwoMemberCornerTreatmentFeatureData

SOLIDWORKS Type Library

TwoMemberCornerTreatmentFeatureData Object Members

 Public Methods

 [GetCornerGroupMembers](#)

 [SwapMembers](#)

 Public Properties

 [CornerTreatmentTrimType](#)

 [MiterTrimPlanePoint](#)

 [PlanarTrimOption](#)

 [WeldTrimGap](#)

SOLIDWORKS Type Library

CornerTreatmentTrimType Property (TwoMemberCornerTreatmentFeatureData)

 Syntax

Visual Basic for Applications (VBA)

Public Property CornerTreatmentTrimType As Long

SOLIDWORKS Type Library

GetCornerGroupMembers Method (TwoMemberCornerTreatmentFeatureData)

 Syntax

Visual Basic for Applications (VBA)

Public Function GetCornerGroupMembers() As Variant

SOLIDWORKS Type Library

MiterTrimPlanePoint Property (TwoMemberCornerTreatmentFeatureData)

 Syntax

Visual Basic for Applications (VBA)

Public Property MiterTrimPlanePoint As Object

SOLIDWORKS Type Library

PlanarTrimOption Property (TwoMemberCornerTreatmentFeatureData)

 Syntax

Visual Basic for Applications (VBA)

Public Property PlanarTrimOption As Long

SOLIDWORKS Type Library

SwapMembers Method (TwoMemberCornerTreatmentFeatureData)

 Syntax

```
Public Sub SwapMembers()
```

WeldTrimGap Property (TwoMemberCornerTreatmentFeatureData)



Syntax

```
Public Property WeldTrimGap As Double
```

UniversalJointMateFeatureData (Type)

SOLIDWORKS Type Library
UniversalJointMateFeatureData Object

 Object Model

UniversalJointMateFeatureData

SOLIDWORKS Type Library
UniversalJointMateFeatureData Object Members



 Public Properties

-  [DefineJointPoint](#)
-  [EntitiesToMate](#)
-  [JointPoint](#)

SOLIDWORKS Type Library
DefineJointPoint Property (UniversalJointMateFeatureData)

 Syntax

Visual Basic for Applications (VBA)

Public Property DefineJointPoint As Boolean

SOLIDWORKS Type Library
EntitiesToMate Property (UniversalJointMateFeatureData)

 Syntax

Visual Basic for Applications (VBA)

Public Property EntitiesToMate As Variant

SOLIDWORKS Type Library
JointPoint Property (UniversalJointMateFeatureData)

 Syntax

Visual Basic for Applications (VBA)

Public Property JointPoint As Object

UserNotificationDefinition (Type)

SOLIDWORKS Type Library

UserNotificationDefinition Object

Object Model

UserNotificationDefinition

SOLIDWORKS Type Library

UserNotificationDefinition Object Members

Public Properties

- IncludeDoNotShowAgain
- Message
- Position
- ResponseAText
- ResponseAType
- ResponseBText
- ResponseBType
- Severity
- Title
- UniqueName

SOLIDWORKS Type Library

IncludeDoNotShowAgain Property (UserNotificationDefinition)

Syntax

Visual Basic for Applications (VBA)

Public Property IncludeDoNotShowAgain As Boolean

SOLIDWORKS Type Library

Message Property (UserNotificationDefinition)

Syntax

Visual Basic for Applications (VBA)

Public Property Message As String

SOLIDWORKS Type Library

Position Property (UserNotificationDefinition)

Syntax

Visual Basic for Applications (VBA)

Public Property Position As Long

SOLIDWORKS Type Library

ResponseAText Property (UserNotificationDefinition)

Syntax

Visual Basic for Applications (VBA)

Public Property ResponseAText As String

SOLIDWORKS Type Library

ResponseAType Property (UserNotificationDefinition)



Visual Basic for Applications (VBA)

```
Public Property ResponseAType As Long
```

SOLIDWORKS Type Library

ResponseBText Property (UserNotificationDefinition)



Visual Basic for Applications (VBA)

```
Public Property ResponseBText As String
```

SOLIDWORKS Type Library

ResponseBType Property (UserNotificationDefinition)



Visual Basic for Applications (VBA)

```
Public Property ResponseBType As Long
```

SOLIDWORKS Type Library

Severity Property (UserNotificationDefinition)



Visual Basic for Applications (VBA)

```
Public Property Severity As Long
```

SOLIDWORKS Type Library

Title Property (UserNotificationDefinition)



Visual Basic for Applications (VBA)

```
Public Property Title As String
```

SOLIDWORKS Type Library

UniqueName Property (UserNotificationDefinition)



Visual Basic for Applications (VBA)

```
Public Property UniqueName As String
```

UserProgressBar (Type)

SOLIDWORKS Type Library
UserProgressBar Object

 Object Model

UserProgressBar

SOLIDWORKS Type Library
UserProgressBar Object Members

 Public Methods

 End
 Start
 UpdateProgress
 UpdateTitle

SOLIDWORKS Type Library
End Method (UserProgressBar)

 Syntax

```
Visual Basic for Applications (VBA)

Public Function End() As Boolean
```

SOLIDWORKS Type Library
Start Method (UserProgressBar)

 Syntax

```
Visual Basic for Applications (VBA)

Public Function Start( _
    ByVal LowerBound As Long, _
    ByVal UpperBound As Long, _
    ByVal ProgressBarTitle As String _
) As Boolean
```

SOLIDWORKS Type Library
UpdateProgress Method (UserProgressBar)

 Syntax

```
Visual Basic for Applications (VBA)

Public Function UpdateProgress( _
    ByVal Position As Long _
) As Long
```

SOLIDWORKS Type Library
UpdateTitle Method (UserProgressBar)

 Syntax

```
Visual Basic for Applications (VBA)

Public Function UpdateTitle( _
    ByVal ProgressBarTitle As String _
) As Boolean
```

UserUnit (Type)

SOLIDWORKS Type Library

UserUnit Object

Object Model

UserUnit

SOLIDWORKS Type Library

UserUnit Object Members

Public Methods

	ConvertDoubleToSystemValue
	ConvertToSystemValue
	ConvertToUserUnit
	GetConversionFactor
	GetFullUnitName
	GetUnitsString
	GetUserAngleTolerance
	IsMetric

Public Properties

	DisplayLeadingZero
	FractionBase
	FractionValue
	PadZero
	RoundToFraction
	SeparatorCharacter
	SignificantDigits
	SpecificUnitType
	UnitType

SOLIDWORKS Type Library

ConvertDoubleToSystemValue Method (UserUnit)

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function ConvertDoubleToSystemValue(_ ByVal <i>UserValue</i> As Double _) As Double</pre>

SOLIDWORKS Type Library

ConvertToSystemValue Method (UserUnit)

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function ConvertToSystemValue(_ ByVal <i>UnitText</i> As String, _ ByRef <i>ComputedValue</i> As Double _) As Boolean</pre>

SOLIDWORKS Type Library

ConvertToUserUnit Method (UserUnit)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ConvertToUserUnit( _  
    ByVal ValueIn As Double, _  
    ByVal ShowUsernames As Boolean, _  
    ByVal NameInEnglish As Boolean _  
) As String
```

SOLIDWORKS Type Library

DisplayLeadingZero Property (UserUnit)

Syntax

Visual Basic for Applications (VBA)

```
Public Property DisplayLeadingZero As Boolean
```

SOLIDWORKS Type Library

FractionBase Property (UserUnit)

Syntax

Visual Basic for Applications (VBA)

```
Public Property FractionBase As Long
```

SOLIDWORKS Type Library

FractionValue Property (UserUnit)

Syntax

Visual Basic for Applications (VBA)

```
Public Property FractionValue As Long
```

SOLIDWORKS Type Library

GetConversionFactor Method (UserUnit)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetConversionFactor() As Double
```

SOLIDWORKS Type Library

GetFullUnitName Method (UserUnit)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFullUnitName( _  
    ByVal Plural As Boolean _  
) As String
```

SOLIDWORKS Type Library

GetUnitsString Method (UserUnit)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetUnitsString( _  
    ByVal InEnglish As Boolean _  
) As String
```

SOLIDWORKS Type Library

GetUserAngleTolerance Method (UserUnit)



Visual Basic for Applications (VBA)

```
Public Function GetUserAngleTolerance() As Double
```

SOLIDWORKS Type Library

IsMetric Method (UserUnit)



Visual Basic for Applications (VBA)

```
Public Function IsMetric() As Boolean
```

SOLIDWORKS Type Library

PadZero Property (UserUnit)



Visual Basic for Applications (VBA)

```
Public Property PadZero As Boolean
```

SOLIDWORKS Type Library

RoundToFraction Property (UserUnit)



Visual Basic for Applications (VBA)

```
Public Property RoundToFraction As Boolean
```

SOLIDWORKS Type Library

SeparatorCharacter Property (UserUnit)



Visual Basic for Applications (VBA)

```
Public Property SeparatorCharacter As String
```

SOLIDWORKS Type Library

SignificantDigits Property (UserUnit)



Visual Basic for Applications (VBA)

```
Public Property SignificantDigits As Long
```

SOLIDWORKS Type Library

SpecificUnitType Property (UserUnit)



Visual Basic for Applications (VBA)

```
Public Property SpecificUnitType As Long
```

SOLIDWORKS Type Library

UnitType Property (UserUnit)



Visual Basic for Applications (VBA)

```
Public Property UnitType As Long
```

VariableFilletFeatureData (Type)

SOLIDWORKS Type Library

VariableFilletFeatureData Object

Object Model

VariableFilletFeatureData

IGetFilletEdgeAtIndex (Edge)

SOLIDWORKS Type Library

VariableFilletFeatureData Object Members

Public Methods

	AccessSelections
	GetFilletEdgeAtIndex
	GetRadius
	IAccessSelections
	IGetFilletEdgeAtIndex
	IGetRadius
	ISetRadius
	ReleaseSelectionAccess
	SetRadius

Public Properties

	DefaultRadius
	FilletEdgeCount
	OverflowType
	PropagateToTangentFaces
	TransitionType

SOLIDWORKS Type Library

AccessSelections Method (VariableFilletFeatureData)

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function AccessSelections(_ ByVal TopDoc As Object, _ ByVal Component As Object _) As Boolean</pre>

SOLIDWORKS Type Library

DefaultRadius Property (VariableFilletFeatureData)

Syntax

Visual Basic for Applications (VBA)
<pre>Public Property DefaultRadius As Double</pre>

SOLIDWORKS Type Library

FilletEdgeCount Property (VariableFilletFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property FilletEdgeCount As Integer
```

SOLIDWORKS Type Library

GetFilletEdgeAtIndex Method (VariableFilletFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFilletEdgeAtIndex( _  
    ByVal Index As Integer _  
) As Object
```

SOLIDWORKS Type Library

GetRadius Method (VariableFilletFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetRadius( _  
    ByVal PFilletItem As Object _  
) As Double
```

SOLIDWORKS Type Library

IAccessSelections Method (VariableFilletFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IAccessSelections( _  
    ByVal TopDoc As ModelDoc, _  
    ByVal Component As Component _  
) As Boolean
```

SOLIDWORKS Type Library

IGetFilletEdgeAtIndex Method (VariableFilletFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetFilletEdgeAtIndex( _  
    ByVal Index As Integer _  
) As Edge
```

SOLIDWORKS Type Library

IGetRadius Method (VariableFilletFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetRadius( _  
    ByVal PFilletItem As Vertex _  
) As Double
```

SOLIDWORKS Type Library

ISetRadius Method (VariableFilletFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ISetRadius( _  
    ByVal PFilletItem As Vertex, _  
    ByVal Radius As Double _  
)
```

SOLIDWORKS Type Library

OverflowType Property (VariableFilletFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Property OverflowType As Integer
```

SOLIDWORKS Type Library

PropagateToTangentFaces Property (VariableFilletFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Property PropagateToTangentFaces As Boolean
```

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (VariableFilletFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub ReleaseSelectionAccess()
```

SOLIDWORKS Type Library

SetRadius Method (VariableFilletFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetRadius( _  
    ByVal PFilletItem As Object, _  
    ByVal Radius As Double _  
)
```

SOLIDWORKS Type Library

TransitionType Property (VariableFilletFeatureData)



Syntax

Visual Basic for Applications (VBA)

```
Public Property TransitionType As Integer
```