

SOLIDWORKS API (VB6 COM) — Reference (101/102): View3D-WizardHoleFeatureData

SOLIDWORKS API Documentation (converted from CHM)

View3D (Type)

SOLIDWORKS Type Library

View3D Object

Object Model

View3D

Rotation (MathTransform)

Translation (MathVector)

SOLIDWORKS Type Library

View3D Object Members

Public Methods

 [Activate](#)

 [Deactivate](#)

 [Get3DViewAnnotationTextScale](#)

Public Properties

 [AnnotationViews](#)

 [AnnotationViews2](#)

 [ConfigurationName](#)

 [DisplayMode](#)

 [DisplayState](#)

 [ModelBreakViewName](#)

 [Name](#)

 [Rotation](#)

 [Scale](#)

 [Translation](#)

SOLIDWORKS Type Library

Activate Method (View3D)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub Activate( _  
    ByVal SaveLastState As Boolean _  
)
```

SOLIDWORKS Type Library

AnnotationViews Property (View3D)

Syntax

Visual Basic for Applications (VBA)

```
Public Property AnnotationViews As Variant
```

SOLIDWORKS Type Library

AnnotationViews2 Property (View3D)

Syntax

Visual Basic for Applications (VBA)

Public Property AnnotationViews2 As Variant

SOLIDWORKS Type Library

ConfigurationName Property (View3D)



Visual Basic for Applications (VBA)

Public Property ConfigurationName As String

SOLIDWORKS Type Library

Deactivate Method (View3D)



Visual Basic for Applications (VBA)

Public Sub Deactivate()

SOLIDWORKS Type Library

DisplayMode Property (View3D)



Visual Basic for Applications (VBA)

Public Property DisplayMode As Long

SOLIDWORKS Type Library

DisplayState Property (View3D)



Visual Basic for Applications (VBA)

Public Property DisplayState As String

SOLIDWORKS Type Library

Get3DViewAnnotationTextScale Method (View3D)



Visual Basic for Applications (VBA)

```
Public Sub Get3DViewAnnotationTextScale( _  
    ByRef Scale1 As Double, _  
    ByRef Scale2 As Double _  
)
```

SOLIDWORKS Type Library

ModelBreakViewName Property (View3D)



Visual Basic for Applications (VBA)

Public Property ModelBreakViewName As String

SOLIDWORKS Type Library

Name Property (View3D)



Visual Basic for Applications (VBA)

Public Property Name As String

SOLIDWORKS Type Library

Rotation Property (View3D)



Visual Basic for Applications (VBA)

Public Property Rotation As [MathTransform](#)

SOLIDWORKS Type Library

Scale Property (View3D)



Visual Basic for Applications (VBA)

Public Property Scale As Double

SOLIDWORKS Type Library

Translation Property (View3D)



Visual Basic for Applications (VBA)


Public Property Translation As [MathVector](#)

WeldBead (Type)

SOLIDWORKS Type Library

WeldBead Object

Object Model



SOLIDWORKS Type Library

WeldBead Object Members

Public Methods

 [GetAnnotation](#)

 [GetNext](#)

Public Properties

 [SolidFill](#)

SOLIDWORKS Type Library

GetAnnotation Method (WeldBead)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetAnnotation() As Annotation
```

SOLIDWORKS Type Library

GetNext Method (WeldBead)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNext() As WeldBead
```

SOLIDWORKS Type Library

SolidFill Property (WeldBead)

Syntax


Visual Basic for Applications (VBA)

```
Public Property SolidFill As Boolean
```

WeldmentBeadFeatureData (Type)

SOLIDWORKS Type Library
WeldmentBeadFeatureData Object

Object Model



SOLIDWORKS Type Library
WeldmentBeadFeatureData Object Members

Public Methods

 AccessSelections
 GetFaces
 GetFacesCount
 GetVirtualEdges
 GetVirtualEdgesCount
 IGetFaces
 IGetVirtualEdges
 ISetFaces
 ISetVirtualEdges
 ReleaseSelectionAccess
 SetFaces
 SetVirtualEdges

Public Properties

 BeadLength
 BeadPitch
 BeadSize
 BeadType
 TangentPropagation
 UseOtherSide

SOLIDWORKS Type Library
AccessSelections Method (WeldmentBeadFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Function AccessSelections( _
    ByVal PTopDoc As ModelDoc2, _
    ByVal PComponent As Component2 _
) As Boolean
```

SOLIDWORKS Type Library
BeadLength Property (WeldmentBeadFeatureData)

Syntax

```
Visual Basic for Applications (VBA)
```

```
Public Property BeadLength( _  
    ByVal Side As Long _  
) As Double
```

SOLIDWORKS Type Library

BeadPitch Property (WeldmentBeadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property BeadPitch( _  
    ByVal Side As Long _  
) As Double
```

SOLIDWORKS Type Library

BeadSize Property (WeldmentBeadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property BeadSize( _  
    ByVal Side As Long _  
) As Double
```

SOLIDWORKS Type Library

BeadType Property (WeldmentBeadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property BeadType( _  
    ByVal Side As Long _  
) As Long
```

SOLIDWORKS Type Library

GetFaces Method (WeldmentBeadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub GetFaces( _  
    ByVal Side As Long, _  
    ByRef FaceSet1 As Variant, _  
    ByRef FaceSet2 As Variant _  
)
```

SOLIDWORKS Type Library

GetFacesCount Method (WeldmentBeadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub GetFacesCount( _  
    ByVal Side As Long, _  
    ByRef FaceSet1Count As Long, _  
    ByRef FaceSet2Count As Long _  
)
```

SOLIDWORKS Type Library

GetVirtualEdges Method (WeldmentBeadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetVirtualEdges( _  
    ByVal FromFeature As Boolean, _  
    ByVal Side As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetVirtualEdgesCount Method (WeldmentBeadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetVirtualEdgesCount( _  
    ByVal FromFeature As Boolean, _  
    ByVal Side As Long _  
) As Long
```

SOLIDWORKS Type Library

IGetFaces Method (WeldmentBeadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub IGetFaces( _  
    ByVal Side As Long, _  
    ByVal Count1 As Long, _  
    ByRef FaceSet1 As Face2, _  
    ByVal Count2 As Long, _  
    ByRef FaceSet2 As Face2 _  
)
```

SOLIDWORKS Type Library

IGetVirtualEdges Method (WeldmentBeadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetVirtualEdges( _  
    ByVal FromFeature As Boolean, _  
    ByVal Side As Long, _  
    ByVal Count As Long _  
) As Edge
```

SOLIDWORKS Type Library

ISetFaces Method (WeldmentBeadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function ISetFaces( _  
    ByVal Side As Long, _  
    ByVal Count1 As Long, _  
    ByVal FaceSet1 As Face2, _  
    ByVal Count2 As Long, _  
    ByVal FaceSet2 As Face2 _  
) As Boolean
```

SOLIDWORKS Type Library

ISetVirtualEdges Method (WeldmentBeadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ISetVirtualEdges( _  
    ByVal Side As Long, _  
    ByVal Count As Long, _
```

```
ByVal EdgesIn As Edge _  
)
```

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (WeldmentBeadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ReleaseSelectionAccess()
```

SOLIDWORKS Type Library

SetFaces Method (WeldmentBeadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetFaces( _  
    ByVal Side As Long, _  
    ByVal FaceSet1 As Variant, _  
    ByVal FaceSet2 As Variant _  
) As Boolean
```

SOLIDWORKS Type Library

SetVirtualEdges Method (WeldmentBeadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub SetVirtualEdges( _  
    ByVal Side As Long, _  
    ByVal EdgesIn As Variant _  
)
```

SOLIDWORKS Type Library

TangentPropagation Property (WeldmentBeadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property TangentPropagation As Boolean
```

SOLIDWORKS Type Library

UseOtherSide Property (WeldmentBeadFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property UseOtherSide As Boolean
```

WeldmentCutListAnnotation (Type)

SOLIDWORKS Type Library

WeldmentCutListAnnotation Object

Object Model

WeldmentCutListAnnotation

WeldmentCutListFeature

SOLIDWORKS Type Library

WeldmentCutListAnnotation Object Members

Public Methods

 [GetAllCustomProperties](#)

 [GetAllCustomPropertiesCount](#)

 [GetColumnCustomProperty](#)

 [IGetAllCustomProperties](#)

 [SetColumnCustomProperty](#)

 [Sort](#)

Public Properties

 [WeldmentCutListFeature](#)

SOLIDWORKS Type Library

GetAllCustomProperties Method (WeldmentCutListAnnotation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetAllCustomProperties() As Variant
```

SOLIDWORKS Type Library

GetAllCustomPropertiesCount Method (WeldmentCutListAnnotation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetAllCustomPropertiesCount() As Long
```

SOLIDWORKS Type Library

GetColumnCustomProperty Method (WeldmentCutListAnnotation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetColumnCustomProperty( _  
    ByVal Index As Long _  
) As String
```

SOLIDWORKS Type Library

IGetAllCustomProperties Method (WeldmentCutListAnnotation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetAllCustomProperties( _  
    ByVal Count As Long _  
    ) As String
```

SOLIDWORKS Type Library

SetColumnCustomProperty Method (WeldmentCutListAnnotation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetColumnCustomProperty( _  
    ByVal Index As Long, _  
    ByVal CustomProp As String _  
    ) As Boolean
```

SOLIDWORKS Type Library

Sort Method (WeldmentCutListAnnotation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function Sort( _  
    ByVal ColumnIndex As Long, _  
    ByVal SortAscending As Boolean _  
    ) As Boolean
```

SOLIDWORKS Type Library

WeldmentCutListFeature Property (WeldmentCutListAnnotation)

Syntax


Visual Basic for Applications (VBA)

```
Public Property WeldmentCutListFeature As WeldmentCutListFeature
```

WeldmentCutListFeature (Type)

SOLIDWORKS Type Library
WeldmentCutListFeature Object

Object Model



SOLIDWORKS Type Library
WeldmentCutListFeature Object Members

Public Methods

	GetFeature
	GetReferencedModelName
	GetTableAnnotationCount
	GetTableAnnotations
	IGetTableAnnotations

Public Properties

	Configuration
	KeepCurrentItemNumbers
	KeepMissingItems
	SequenceStartNumber
	StrikeoutMissingItems

SOLIDWORKS Type Library
Configuration Property (WeldmentCutListFeature)

Syntax

```
Visual Basic for Applications (VBA)

Public Property Configuration As String
```

SOLIDWORKS Type Library
GetFeature Method (WeldmentCutListFeature)

Syntax

```
Visual Basic for Applications (VBA)

Public Function GetFeature() As Feature
```

SOLIDWORKS Type Library
GetReferencedModelName Method (WeldmentCutListFeature)

Syntax

```
Visual Basic for Applications (VBA)

Public Function GetReferencedModelName() As String
```

SOLIDWORKS Type Library
GetTableAnnotationCount Method (WeldmentCutListFeature)



Visual Basic for Applications (VBA)

```
Public Function GetTableAnnotationCount() As Long
```

SOLIDWORKS Type Library

GetTableAnnotations Method (WeldmentCutListFeature)



Visual Basic for Applications (VBA)

```
Public Function GetTableAnnotations() As Variant
```

SOLIDWORKS Type Library

IGetTableAnnotations Method (WeldmentCutListFeature)



Visual Basic for Applications (VBA)

```
Public Function IGetTableAnnotations( _  
    ByVal Count As Long _  
) As WeldmentCutListAnnotation
```

SOLIDWORKS Type Library

KeepCurrentItemNumbers Property (WeldmentCutListFeature)



Visual Basic for Applications (VBA)

```
Public Property KeepCurrentItemNumbers As Boolean
```

SOLIDWORKS Type Library

KeepMissingItems Property (WeldmentCutListFeature)



Visual Basic for Applications (VBA)

```
Public Property KeepMissingItems As Boolean
```

SOLIDWORKS Type Library

SequenceStartNumber Property (WeldmentCutListFeature)



Visual Basic for Applications (VBA)

```
Public Property SequenceStartNumber As Long
```

SOLIDWORKS Type Library

StrikeoutMissingItems Property (WeldmentCutListFeature)




Visual Basic for Applications (VBA)

```
Public Property StrikeoutMissingItems As Boolean
```

WeldmentTrimExtendFeatureData (Type)

SOLIDWORKS Type Library
WeldmentTrimExtendFeatureData Object



SOLIDWORKS Type Library
WeldmentTrimExtendFeatureData Object Members

Public Methods

	AccessSelections
	GetBodiesToBeTrimmedCount
	GetTrimmingBoundary
	GetTrimmingBoundaryCount
	IGetBodiesToBeTrimmed
	IGetTrimmingBoundary
	ISetBodiesToBeTrimmed
	ISetTrimmingBoundary
	ReleaseSelectionAccess
	SetTrimmingBoundary

Public Properties

	BodiesToBeTrimmed
	CornerType

SOLIDWORKS Type Library
AccessSelections Method (WeldmentTrimExtendFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Function AccessSelections( _
    ByVal PTopDoc As ModelDoc2, _
    ByVal PComponent As Component2 _
) As Boolean
```

SOLIDWORKS Type Library
BodiesToBeTrimmed Property (WeldmentTrimExtendFeatureData)

Syntax

```
Visual Basic for Applications (VBA)

Public Property BodiesToBeTrimmed As Variant
```

SOLIDWORKS Type Library
CornerType Property (WeldmentTrimExtendFeatureData)

Syntax

```
Visual Basic for Applications (VBA)
```

Public Property CornerType As Long

SOLIDWORKS Type Library

GetBodiesToBeTrimmedCount Method (WeldmentTrimExtendFeatureData)



Visual Basic for Applications (VBA)

```
Public Function GetBodiesToBeTrimmedCount() As Long
```

SOLIDWORKS Type Library

GetTrimmingBoundary Method (WeldmentTrimExtendFeatureData)



Visual Basic for Applications (VBA)

```
Public Function GetTrimmingBoundary( _  
    ByRef Type As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetTrimmingBoundaryCount Method (WeldmentTrimExtendFeatureData)



Visual Basic for Applications (VBA)

```
Public Function GetTrimmingBoundaryCount() As Long
```

SOLIDWORKS Type Library

IGetBodiesToBeTrimmed Method (WeldmentTrimExtendFeatureData)



Visual Basic for Applications (VBA)

```
Public Function IGetBodiesToBeTrimmed( _  
    ByVal Count As Long _  
) As Body2
```

SOLIDWORKS Type Library

IGetTrimmingBoundary Method (WeldmentTrimExtendFeatureData)



Visual Basic for Applications (VBA)

```
Public Function IGetTrimmingBoundary( _  
    ByVal Count As Long, _  
    ByRef Type As Long _  
) As Object
```

SOLIDWORKS Type Library

ISetBodiesToBeTrimmed Method (WeldmentTrimExtendFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub ISetBodiesToBeTrimmed( _  
    ByVal Count As Long, _  
    ByVal BodiesIn As Body2 _  
)
```

SOLIDWORKS Type Library

ISetTrimmingBoundary Method (WeldmentTrimExtendFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub ISetTrimmingBoundary( _  
    ByVal Count As Long, _  
    ByRef TrimBoundArr As Object _  
)
```

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (WeldmentTrimExtendFeatureData)



Visual Basic for Applications (VBA)

```
Public Sub ReleaseSelectionAccess()
```

SOLIDWORKS Type Library

SetTrimmingBoundary Method (WeldmentTrimExtendFeatureData)



Visual Basic for Applications (VBA)


```
Public Sub SetTrimmingBoundary( _  
    ByVal TrimBoundVar As Variant _  
)
```

WeldSymbol (Type)

SOLIDWORKS Type Library

WeldSymbol Object

Object Model



SOLIDWORKS Type Library

WeldSymbol Object Members

Public Methods

	GetAnnotation
	GetArcAtIndex
	GetArcCount
	GetArrowHeadAtIndex
	GetArrowHeadCount
	GetArrowHeadInfo
	GetContour
	GetFieldWeld
	GetLeaderAtIndex
	GetLeaderCount
	GetLineAtIndex
	GetLineCount
	GetNext
	GetPeripheral
	GetProcess
	GetProcessReference
	GetStagger
	GetSymmetric
	GetText
	GetTextAngleAtIndex
	GetTextAtIndex
	GetTextCount
	GetTextHeightAtIndex
	GetTextInvertAtIndex
	GetTextPositionAtIndex
	GetTextRefPositionAtIndex
	GetTriangleAtIndex
	GetTriangleCount
	HasExtralLeader
	IGetAnnotation


 IGetArcAtIndex
 IGetArrowHeadAtIndex
 IGetArrowHeadInfo
 IGetLeaderAtIndex
 IGetLineAtIndex
 IGetNext
 IGetTextPositionAtIndex
 IGetTriangleAtIndex
 IsAttached
 SetFieldWeld
 SetPeripheral
 SetProcess
 SetStagger
 SetSymmetric
 SetText

SOLIDWORKS Type Library

GetAnnotation Method (WeldSymbol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetAnnotation() As Object
```

SOLIDWORKS Type Library

GetArcAtIndex Method (WeldSymbol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetArcAtIndex( _  
    ByVal Index As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetArcCount Method (WeldSymbol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetArcCount() As Long
```

SOLIDWORKS Type Library

GetArrowHeadAtIndex Method (WeldSymbol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetArrowHeadAtIndex( _  
    ByVal Index As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetArrowHeadCount Method (WeldSymbol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetArrowHeadCount() As Long
```

SOLIDWORKS Type Library

GetArrowHeadInfo Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function GetArrowHeadInfo() As Variant
```

SOLIDWORKS Type Library

GetContour Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function GetContour( _  
    ByVal Top As Boolean _  
    ) As Long
```

SOLIDWORKS Type Library

GetFieldWeld Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function GetFieldWeld() As Long
```

SOLIDWORKS Type Library

GetLeaderAtIndex Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function GetLeaderAtIndex( _  
    ByVal Index As Long _  
    ) As Variant
```

SOLIDWORKS Type Library

GetLeaderCount Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function GetLeaderCount() As Long
```

SOLIDWORKS Type Library

GetLineAtIndex Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function GetLineAtIndex( _  
    ByVal Index As Long _  
    ) As Variant
```

SOLIDWORKS Type Library

GetLineCount Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function GetLineCount() As Long
```

SOLIDWORKS Type Library

GetNext Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function GetNext() As Object
```

SOLIDWORKS Type Library

GetPeripheral Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function GetPeripheral() As Boolean
```

SOLIDWORKS Type Library

GetProcess Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function GetProcess() As Boolean
```

SOLIDWORKS Type Library

GetProcessReference Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function GetProcessReference() As Boolean
```

SOLIDWORKS Type Library

GetStagger Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function GetStagger() As Boolean
```

SOLIDWORKS Type Library

GetSymmetric Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function GetSymmetric() As Long
```

SOLIDWORKS Type Library

GetText Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function GetText( _  
    ByVal WhichText As Long _  
) As String
```

SOLIDWORKS Type Library

GetTextAngleAtIndex Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function GetTextAngleAtIndex( _  
    ByVal Index As Long _  
    ) As Double
```

SOLIDWORKS Type Library

GetTextAtIndex Method (WeldSymbol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTextAtIndex( _  
    ByVal Index As Long _  
    ) As String
```

SOLIDWORKS Type Library

GetTextCount Method (WeldSymbol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTextCount() As Long
```

SOLIDWORKS Type Library

GetTextHeightAtIndex Method (WeldSymbol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTextHeightAtIndex( _  
    ByVal Index As Long _  
    ) As Double
```

SOLIDWORKS Type Library

GetTextInvertAtIndex Method (WeldSymbol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTextInvertAtIndex( _  
    ByVal Index As Long _  
    ) As Long
```

SOLIDWORKS Type Library

GetTextPositionAtIndex Method (WeldSymbol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTextPositionAtIndex( _  
    ByVal Index As Long _  
    ) As Variant
```

SOLIDWORKS Type Library

GetTextRefPositionAtIndex Method (WeldSymbol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTextRefPositionAtIndex( _  
    ByVal Index As Long _  
    ) As Long
```

SOLIDWORKS Type Library

GetTriangleAtIndex Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function GetTriangleAtIndex( _  
    ByVal Index As Long _  
) As Variant
```

SOLIDWORKS Type Library

GetTriangleCount Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function GetTriangleCount() As Long
```

SOLIDWORKS Type Library

HasExtraLeader Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function HasExtraLeader() As Boolean
```

SOLIDWORKS Type Library

IGetAnnotation Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function IGetAnnotation() As Annotation
```

SOLIDWORKS Type Library

IGetArcAtIndex Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function IGetArcAtIndex( _  
    ByVal Index As Long _  
) As Double
```

SOLIDWORKS Type Library

IGetArrowHeadAtIndex Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function IGetArrowHeadAtIndex( _  
    ByVal Index As Long _  
) As Double
```

SOLIDWORKS Type Library

IGetArrowHeadInfo Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function IGetArrowHeadInfo() As Double
```

SOLIDWORKS Type Library

IGetLeaderAtIndex Method (WeldSymbol)



Visual Basic for Applications (VBA)

```
Public Function IGetLeaderAtIndex( _  
    ByVal Index As Long, _  
    ByRef PointCount As Long _  
) As Double
```

SOLIDWORKS Type Library

IGetLineAtIndex Method (WeldSymbol)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetLineAtIndex( _  
    ByVal Index As Long _  
) As Double
```

SOLIDWORKS Type Library

IGetNext Method (WeldSymbol)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetNext() As WeldSymbol
```

SOLIDWORKS Type Library

IGetTextPositionAtIndex Method (WeldSymbol)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetTextPositionAtIndex( _  
    ByVal Index As Long _  
) As Double
```

SOLIDWORKS Type Library

IGetTriangleAtIndex Method (WeldSymbol)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetTriangleAtIndex( _  
    ByVal Index As Long _  
) As Double
```

SOLIDWORKS Type Library

IsAttached Method (WeldSymbol)



Syntax

Visual Basic for Applications (VBA)

```
Public Function IsAttached() As Boolean
```

SOLIDWORKS Type Library

SetFieldWeld Method (WeldSymbol)



Syntax

Visual Basic for Applications (VBA)

```
Public Function SetFieldWeld( _  
    ByVal FieldWeld As Long _  
) As Boolean
```

SOLIDWORKS Type Library

SetPeripheral Method (WeldSymbol)



Syntax

Visual Basic for Applications (VBA)

```
Public Function SetPeripheral( _  
    ByVal Peripheral As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

SetProcess Method (WeldSymbol)



Syntax

Visual Basic for Applications (VBA)

```
Public Function SetProcess( _  
    ByVal Process As Boolean, _  
    ByVal Text As String, _  
    ByVal Reference As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

SetStagger Method (WeldSymbol)



Syntax

Visual Basic for Applications (VBA)

```
Public Function SetStagger( _  
    ByVal Stagger As Boolean _  
) As Boolean
```

SOLIDWORKS Type Library

SetSymmetric Method (WeldSymbol)



Syntax

Visual Basic for Applications (VBA)

```
Public Function SetSymmetric( _  
    ByVal Symmetric As Long _  
) As Boolean
```

SOLIDWORKS Type Library

SetText Method (WeldSymbol)



Syntax

Visual Basic for Applications (VBA)

```
Public Function SetText( _  
    ByVal Top As Boolean, _  
    ByVal Left As String, _  
    ByVal Symbol As String, _  
    ByVal Right As String, _  
    ByVal Stagger As String, _  
    ByVal Contour As Long _  
) As Boolean
```

WidthMateFeatureData (Type)

SOLIDWORKS Type Library

WidthMateFeatureData Object

Object Model

WidthMateFeatureData

SOLIDWORKS Type Library

WidthMateFeatureData Object Members

Public Properties

 ConstraintType
 DistanceFromEnd
 FlipDimension
 PercentDistanceFromEnd
 TabSelection
 WidthSelection

SOLIDWORKS Type Library

ConstraintType Property (WidthMateFeatureData)

Syntax

Visual Basic for Applications (VBA)
Public Property ConstraintType As Long

SOLIDWORKS Type Library

DistanceFromEnd Property (WidthMateFeatureData)

Syntax

Visual Basic for Applications (VBA)
Public Property DistanceFromEnd As Double

SOLIDWORKS Type Library

FlipDimension Property (WidthMateFeatureData)

Syntax

Visual Basic for Applications (VBA)
Public Property FlipDimension As Boolean

SOLIDWORKS Type Library

PercentDistanceFromEnd Property (WidthMateFeatureData)

Syntax

Visual Basic for Applications (VBA)
Public Property PercentDistanceFromEnd As Double

SOLIDWORKS Type Library

TabSelection Property (WidthMateFeatureData)

Syntax

Visual Basic for Applications (VBA)

Public Property TabSelection As Variant

SOLIDWORKS Type Library

WidthSelection Property (WidthMateFeatureData)



Visual Basic for Applications (VBA)

Public Property WidthSelection As Variant

WizardHoleFeatureData (Type)

SOLIDWORKS Type Library

WizardHoleFeatureData Object

Object Model

WizardHoleFeatureData

IFace (Face)

IVertex (Vertex)

SOLIDWORKS Type Library

WizardHoleFeatureData Object Members

Public Methods

-  [AccessSelections](#)
-  [IAccessSelections](#)
-  [ReleaseSelectionAccess](#)

Public Properties

-  [CounterBoreDepth](#)
-  [CounterBoreDiameter](#)
-  [CounterDrillAngle](#)
-  [CounterDrillDepth](#)
-  [CounterDrillDiameter](#)
-  [CounterSinkAngle](#)
-  [CounterSinkDiameter](#)
-  [Depth](#)
-  [Diameter](#)
-  [DrillAngle](#)
-  [EndCondition](#)
-  [Face](#)
-  [FarCounterSinkAngle](#)
-  [FarCounterSinkDiameter](#)
-  [FastenerSize](#)
-  [FastenerType](#)
-  [HeadClearance](#)
-  [HoleDepth](#)
-  [HoleDiameter](#)
-  [IFace](#)
-  [IVertex](#)
-  [MajorDiameter](#)
-  [MidCounterSinkAngle](#)
-  [MidCounterSinkDiameter](#)
-  [MinorDiameter](#)

 NearCounterSinkAngle
 NearCounterSinkDiameter
 Standard
 TapDrillDepth
 TapDrillDiameter
 ThreadAngle
 ThreadDepth
 ThreadDiameter
 ThruHoleDepth
 ThruHoleDiameter
 ThruTapDrillDepth
 ThruTapDrillDiameter
 Type
 Vertex

SOLIDWORKS Type Library

AccessSelections Method (WizardHoleFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AccessSelections( _
    ByVal TopDoc As Object, _
    ByVal Component As Object _
) As Boolean
```

SOLIDWORKS Type Library

CounterBoreDepth Property (WizardHoleFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property CounterBoreDepth As Double
```

SOLIDWORKS Type Library

CounterBoreDiameter Property (WizardHoleFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property CounterBoreDiameter As Double
```

SOLIDWORKS Type Library

CounterDrillAngle Property (WizardHoleFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property CounterDrillAngle As Double
```

SOLIDWORKS Type Library

CounterDrillDepth Property (WizardHoleFeatureData)

Syntax

Visual Basic for Applications (VBA)

```
Public Property CounterDrillDepth As Double
```

SOLIDWORKS Type Library

CounterDrillDiameter Property (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

```
Public Property CounterDrillDiameter As Double
```

SOLIDWORKS Type Library

CounterSinkAngle Property (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

```
Public Property CounterSinkAngle As Double
```

SOLIDWORKS Type Library

CounterSinkDiameter Property (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

```
Public Property CounterSinkDiameter As Double
```

SOLIDWORKS Type Library

Depth Property (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

```
Public Property Depth As Double
```

SOLIDWORKS Type Library

Diameter Property (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

```
Public Property Diameter As Double
```

SOLIDWORKS Type Library

DrillAngle Property (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

```
Public Property DrillAngle As Double
```

SOLIDWORKS Type Library

EndCondition Property (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

```
Public Property EndCondition As Integer
```

SOLIDWORKS Type Library

Face Property (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

```
Public Property Face As Object
```

SOLIDWORKS Type Library

FarCounterSinkAngle Property (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

```
Public Property FarCounterSinkAngle As Double
```

SOLIDWORKS Type Library

FarCounterSinkDiameter Property (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

```
Public Property FarCounterSinkDiameter As Double
```

SOLIDWORKS Type Library

FastenerSize Property (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

```
Public Property FastenerSize As String
```

SOLIDWORKS Type Library

FastenerType Property (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

```
Public Property FastenerType As String
```

SOLIDWORKS Type Library

HeadClearance Property (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

```
Public Property HeadClearance As Double
```

SOLIDWORKS Type Library

HoleDepth Property (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

```
Public Property HoleDepth As Double
```

SOLIDWORKS Type Library

HoleDiameter Property (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

```
Public Property HoleDiameter As Double
```

SOLIDWORKS Type Library

IAccessSelections Method (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

```
Public Function IAccessSelections( _  
    ByVal TopDoc As ModelDoc, _
```

```
ByVal Component As Component _  
) As Boolean
```

SOLIDWORKS Type Library

IFace Property (WizardHoleFeatureData)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Property IFace As Face
```

SOLIDWORKS Type Library

IVertex Property (WizardHoleFeatureData)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Property IVertex As Vertex
```

SOLIDWORKS Type Library

MajorDiameter Property (WizardHoleFeatureData)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Property MajorDiameter As Double
```

SOLIDWORKS Type Library

MidCounterSinkAngle Property (WizardHoleFeatureData)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Property MidCounterSinkAngle As Double
```

SOLIDWORKS Type Library

MidCounterSinkDiameter Property (WizardHoleFeatureData)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Property MidCounterSinkDiameter As Double
```

SOLIDWORKS Type Library

MinorDiameter Property (WizardHoleFeatureData)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Property MinorDiameter As Double
```

SOLIDWORKS Type Library

NearCounterSinkAngle Property (WizardHoleFeatureData)

 **Syntax**

Visual Basic for Applications (VBA)

```
Public Property NearCounterSinkAngle As Double
```

SOLIDWORKS Type Library

NearCounterSinkDiameter Property (WizardHoleFeatureData)

 **Syntax**

Visual Basic for Applications (VBA)

Public Property NearCounterSinkDiameter As Double

SOLIDWORKS Type Library

ReleaseSelectionAccess Method (WizardHoleFeatureData)

 Syntax

Visual Basic for Applications (VBA)

Public Sub ReleaseSelectionAccess()

SOLIDWORKS Type Library

Standard Property (WizardHoleFeatureData)

 Syntax

Visual Basic for Applications (VBA)

Public Property Standard As String

SOLIDWORKS Type Library

TapDrillDepth Property (WizardHoleFeatureData)

 Syntax

Visual Basic for Applications (VBA)

Public Property TapDrillDepth As Double

SOLIDWORKS Type Library

TapDrillDiameter Property (WizardHoleFeatureData)

 Syntax

Visual Basic for Applications (VBA)

Public Property TapDrillDiameter As Double

SOLIDWORKS Type Library

ThreadAngle Property (WizardHoleFeatureData)

 Syntax

Visual Basic for Applications (VBA)

Public Property ThreadAngle As Double

SOLIDWORKS Type Library

ThreadDepth Property (WizardHoleFeatureData)

 Syntax

Visual Basic for Applications (VBA)

Public Property ThreadDepth As Double

SOLIDWORKS Type Library

ThreadDiameter Property (WizardHoleFeatureData)

 Syntax

Visual Basic for Applications (VBA)

Public Property ThreadDiameter As Double

SOLIDWORKS Type Library

ThruHoleDepth Property (WizardHoleFeatureData)

 Syntax

Visual Basic for Applications (VBA)

Public Property ThruHoleDepth As Double

SOLIDWORKS Type Library

ThruHoleDiameter Property (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

Public Property ThruHoleDiameter As Double

SOLIDWORKS Type Library

ThruTapDrillDepth Property (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

Public Property ThruTapDrillDepth As Double

SOLIDWORKS Type Library

ThruTapDrillDiameter Property (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

Public Property ThruTapDrillDiameter As Double

SOLIDWORKS Type Library

Type Property (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

Public Property Type As Integer

SOLIDWORKS Type Library

Vertex Property (WizardHoleFeatureData)



Visual Basic for Applications (VBA)

Public Property Vertex As Object