


SOLIDWORKS Document Manager API (VB6 COM)
— Reference (2/8):
ISwDMDimXpertCompoundNotchFeature-
ISwDMDimXpertPlaneFeature

SOLIDWORKS API Documentation (converted from CHM)

ISwDMDimXpertCompoundNotchFeature (Type)

Object Model



Public Methods

	GetBottomFeature
	GetEndFeature
	GetNominalBottomPlane
	GetNominalNotch
	GetOpenSideReferenceFeature
	GetPlaneFeatures
	GetTopReferenceFeature

Public Properties

	Blind
---	-----------------------

Syntax

Visual Basic for Applications (VBA)
Public Property Blind As Boolean

Syntax

Visual Basic for Applications (VBA)
Public Function GetBottomFeature() As SwDMDimXpertFeature

Syntax

Visual Basic for Applications (VBA)
Public Function GetEndFeature() As SwDMDimXpertFeature

GetNominalBottomPlane Method (ISwDMDimXpertCompoundNotchFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalBottomPlane( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

GetNominalNotch Method (ISwDMDimXpertCompoundNotchFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalNotch( _  
    ByRef width As Double, _  
    ByRef Length As Double, _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double, _  
    ByRef LongitudeI As Double, _  
    ByRef LongitudeJ As Double, _  
    ByRef LongitudeK As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

GetOpenSideReferenceFeature Method (ISwDMDimXpertCompoundNotchFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetOpenSideReferenceFeature() As SwDMDimXpertFeature
```

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

GetPlaneFeatures Method (ISwDMDimXpertCompoundNotchFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPlaneFeatures( _  
    ByRef Plane1 As SwDMDimXpertPlaneFeature, _  
    ByRef Plane2 As SwDMDimXpertPlaneFeature _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

GetTopReferenceFeature Method (ISwDMDimXpertCompoundNotchFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTopReferenceFeature() As SwDMDimXpertFeature
```

ISwDMDimXpertCompoundWidthFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ISwDMDimXpertCompoundWidthFeature Object

Object Model

ISwDMDimXpertCompoundWidthFeature

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ISwDMDimXpertCompoundWidthFeature Object Members

Public Methods

-  [GetNominalCompoundWidth](#)
-  [GetNominalLongitude](#)
-  [GetPlaneFeatures](#)

Public Properties

-  [Inner](#)

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

GetNominalCompoundWidth Method (ISwDMDimXpertCompoundWidthFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalCompoundWidth( _  
    ByRef width As Double, _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

GetNominalLongitude Method (ISwDMDimXpertCompoundWidthFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalLongitude( _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

GetPlaneFeatures Method (ISwDMDimXpertCompoundWidthFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPlaneFeatures( _  
    ByRef Plane1 As SwDMDimXpertPlaneFeature, _  
    ByRef Plane2 As SwDMDimXpertPlaneFeature _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)



Syntax

Visual Basic for Applications (VBA)

```
Public Property Inner As Boolean
```

ISwDMDimXpertConcentricityGeoTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertConcentricityGeoTol Object

Object Model

ISwDMDimXpertConcentricityGeoTol

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertConcentricityGeoTol Object Members

Public Methods

 [GetMaxTolerance](#)

Public Properties

 [Modifier](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetMaxTolerance Method (ISwDMDimXpertConcentricityGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetMaxTolerance( _  
    ByRef IsMax As Boolean, _  
    ByRef Tolerance As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

Modifier Property (ISwDMDimXpertConcentricityGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Modifier As swDmDimXpertMaterialConditionModifier\_e
```

ISwDMDimXpertConeAngleDimTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ISwDMDimXpertConeAngleDimTol Object

 Object Model

ISwDMDimXpertConeAngleDimTol

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ISwDMDimXpertConeAngleDimTol Object Members



ISwDMDimXpertConeFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertConeFeature Object

Object Model

ISwDMDimXpertConeFeature

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertConeFeature Object Members

Public Methods

 [GetNominalBottomPlane](#)

 [GetNominalCone](#)

 [GetNominalTopPlane](#)

Public Properties

 [Inner](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalBottomPlane Method (ISwDMDimXpertConeFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalBottomPlane( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalCone Method (ISwDMDimXpertConeFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalCone( _  
    ByRef Angle As Double, _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalTopPlane Method (ISwDMDimXpertConeFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalTopPlane( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _
```

```
ByRef I As Double, _  
ByRef J As Double, _  
ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

Inner Property (ISwMDimXpertConeFeature)



Syntax

Visual Basic for Applications (VBA)

```
Public Property Inner As Boolean
```


ISwDMDimXpertCounterBoreDimTol (Type)

SOLIDWORKS Document Manager Type Library

ISwDMDimXpertCounterBoreDimTol Object

[Send comments on this topic.](#)

Object Model




SOLIDWORKS Document Manager Type Library

ISwDMDimXpertCounterBoreDimTol Object Members

[Send comments on this topic.](#)

Public Properties



SOLIDWORKS Document Manager Type Library

ReferenceFeature Property (ISwDMDimXpertCounterBoreDimTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Property ReferenceFeature As SwDMDimXpertFeature
```


ISwDMDimXpertCounterSinkAngleDimTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ISwDMDimXpertCounterSinkAngleDimTol Object

 Object Model



SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ISwDMDimXpertCounterSinkAngleDimTol Object Members



 Public Properties

 [ReferenceFeature](#)

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ReferenceFeature Property (ISwDMDimXpertCounterSinkAngleDimTol)

 Syntax

Visual Basic for Applications (VBA)

Public Property ReferenceFeature As [SwDMDimXpertFeature](#)


ISwDMDimXpertCounterSinkDiameterDimTol (Type)

SOLIDWORKS Document Manager Type Library

ISwDMDimXpertCounterSinkDiameterDimTol Object

[Send comments on this topic.](#)

Object Model




SOLIDWORKS Document Manager Type Library

ISwDMDimXpertCounterSinkDiameterDimTol Object Members

[Send comments on this topic.](#)

Public Properties



SOLIDWORKS Document Manager Type Library

ReferenceFeature Property (ISwDMDimXpertCounterSinkDiameterDimTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Property ReferenceFeature As SwDMDimXpertFeature
```

ISwDMDimXpertCylinderFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertCylinderFeature Object

Object Model

ISwDMDimXpertCylinderFeature

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertCylinderFeature Object Members

Public Methods

 [GetNominalBottomPlane](#)

 [GetNominalCylinder](#)

 [GetNominalTopPlane](#)

 [GetThread](#)

Public Properties

 [Inner](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalBottomPlane Method (ISwDMDimXpertCylinderFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalBottomPlane( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalCylinder Method (ISwDMDimXpertCylinderFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalCylinder( _  
    ByRef R As Double, _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalTopPlane Method (ISwDMDimXpertCylinderFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalTopPlane( _  
    ByRef X As Double, _
```

```
ByRef Y As Double, _  
ByRef Z As Double, _  
ByRef I As Double, _  
ByRef J As Double, _  
ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetThread Method (ISwMDimXpertCylinderFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetThread( _  
    ByRef IsThreaded As Boolean, _  
    ByRef ThreadDesignation As String, _  
    ByRef ThreadDepth As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

Inner Property (ISwMDimXpertCylinderFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Inner As Boolean
```

ISwDMDimXpertCylindricityGeoTol (Type)

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
ISwDMDimXpertCylindricityGeoTol Object	

 Object Model

ISwDMDimXpertCylindricityGeoTol

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
ISwDMDimXpertCylindricityGeoTol Object Members	
	

ISwDMDimXpertDatum (Type)

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ISwDMDimXpertDatum Object

 Object Model

ISwDMDimXpertDatum

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ISwDMDimXpertDatum Object Members



 Public Properties

 [Identifier](#)

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

Identifier Property (ISwDMDimXpertDatum)

 Syntax

Visual Basic for Applications (VBA)

Public Property Identifier As String


ISwDMDimXpertDepthDimTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertDepthDimTol Object

Object Model



SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertDepthDimTol Object Members



Public Methods

 [IsThreadDepth](#)

Public Properties

 [ReferenceFeature](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IsThreadDepth Method (ISwDMDimXpertDepthDimTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsThreadDepth() As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ReferenceFeature Property (ISwDMDimXpertDepthDimTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Property ReferenceFeature As SwDMDimXpertFeature
```

ISwDMDimXpertDiameterDimTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ISwDMDimXpertDiameterDimTol Object

 Object Model

ISwDMDimXpertDiameterDimTol

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ISwDMDimXpertDiameterDimTol Object Members



 Public Properties

 [PatternTreatment](#)

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

PatternTreatment Property (ISwDMDimXpertDiameterDimTol)

 Syntax

Visual Basic for Applications (VBA)

Public Property PatternTreatment As [swDmDimXpertPatternTreatmentType_e](#)

ISwDMDimXpertDimensionTolerance (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertDimensionTolerance Object

Object Model

ISwDMDimXpertDimensionTolerance

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertDimensionTolerance Object Members

Public Methods

-  [GetNominalValue](#)
-  [GetPlusAndMinusTolerance](#)
-  [GetUpperAndLowerLimit](#)

Public Properties

-  [BlockToleranceDecimalPlaces](#)
-  [DimensionType](#)
-  [LimitsAndFitsCode](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

BlockToleranceDecimalPlaces Property (ISwDMDimXpertDimensionTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Property BlockToleranceDecimalPlaces As Long
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

DimensionType Property (ISwDMDimXpertDimensionTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Property DimensionType As swDmDimXpertDimensionToleranceType\_e
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalValue Method (ISwDMDimXpertDimensionTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalValue() As Double
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetPlusAndMinusTolerance Method (ISwDMDimXpertDimensionTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPlusAndMinusTolerance( _  
    ByRef Plus As Double, _  
    ByRef Minus As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetUpperAndLowerLimit Method (ISwDMDimXpertDimensionTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetUpperAndLowerLimit( _  
    ByRef Upper As Double, _  
    ByRef Lower As Double _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

LimitsAndFitsCode Property (ISwDMDimXpertDimensionTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Property LimitsAndFitsCode As String
```

ISwDMDimXpertDistanceBetweenDimTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ISwDMDimXpertDistanceBetweenDimTol Object

Object Model

ISwDMDimXpertDistanceBetweenDimTol

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ISwDMDimXpertDistanceBetweenDimTol Object Members

Public Methods

 [GetDirectionVector](#)

 [GetFeature](#)

 [GetOriginFeature](#)

Public Properties

 [PatternTreatment](#)

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

GetDirectionVector Method (ISwDMDimXpertDistanceBetweenDimTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDirectionVector( _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

GetFeature Method (ISwDMDimXpertDistanceBetweenDimTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFeature( _  
    ByRef Feature As SwDMDimXpertFeature, _  
    ByRef FosUsage As swDmDimXpertDistanceFosUsage\_e _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

GetOriginFeature Method (ISwDMDimXpertDistanceBetweenDimTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetOriginFeature( _  
    ByRef Feature As SwDMDimXpertFeature, _  
    ByRef FosUsage As swDmDimXpertDistanceFosUsage\_e _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

PatternTreatment Property (ISwDMDimXpertDistanceBetweenDimTol)

Syntax

Visual Basic for Applications (VBA)


ISwDMDimXpertExtrudeFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertExtrudeFeature Object

Object Model



SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertExtrudeFeature Object Members

Public Methods

	GetBottomBlends
	GetBottomFeature
	GetReferenceFeature
	GetSubFeatureCount
	GetSubFeatures
	GetTopBlends
	IGetSubFeatures

Public Properties

	Blind
---	-----------------------

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

Blind Property (ISwDMDimXpertExtrudeFeature)

Syntax

Visual Basic for Applications (VBA)
Public Property Blind As Boolean

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetBottomBlends Method (ISwDMDimXpertExtrudeFeature)

Syntax

Visual Basic for Applications (VBA)
Public Function GetBottomBlends() As SwDMDimXpertFeature

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetBottomFeature Method (ISwDMDimXpertExtrudeFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetBottomFeature() As SwDMDimXpertFeature
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetReferenceFeature Method (ISwDMDimXpertExtrudeFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetReferenceFeature() As SwDMDimXpertFeature
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetSubFeatureCount Method (ISwDMDimXpertExtrudeFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSubFeatureCount() As Long
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetSubFeatures Method (ISwDMDimXpertExtrudeFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSubFeatures() As Variant
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetTopBlends Method (ISwDMDimXpertExtrudeFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTopBlends() As SwDMDimXpertFeature
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IGetSubFeatures Method (ISwDMDimXpertExtrudeFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetSubFeatures( _  
    ByVal Count As Long _  
) As SwDMDimXpertFeature
```

ISwDMDimXpertFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertFeature Object

Object Model

ISwDMDimXpertFeature

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertFeature Object Members

Public Methods

 [GetCadIdentifierCount](#)

 [GetCadIdentifiers](#)

 [IGetCadIdentifiers](#)

 [IsSuppressed](#)

Public Properties

 [Name](#)

 [Type](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetCadIdentifierCount Method (ISwDMDimXpertFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCadIdentifierCount() As Long
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetCadIdentifiers Method (ISwDMDimXpertFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCadIdentifiers() As Variant
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IGetCadIdentifiers Method (ISwDMDimXpertFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetCadIdentifiers( _  
    ByVal Count As Long _  
) As String
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IsSuppressed Method (ISwDMDimXpertFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsSuppressed() As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

Name Property (ISwDMDimXpertFeature)



Visual Basic for Applications (VBA)

Public Property Name As String

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

type Property (ISwMDimXpertFeature)



Visual Basic for Applications (VBA)

Public Property type As [swDmDimXpertFeatureType_e](#)

ISwDMDimXpertFilletFeature (Type)

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
ISwDMDimXpertFilletFeature Object	

 Object Model

ISwDMDimXpertFilletFeature

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
ISwDMDimXpertFilletFeature Object Members	
	

 Public Properties

 Inner
 Radius

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
Inner Property (ISwDMDimXpertFilletFeature)	

 Syntax

Visual Basic for Applications (VBA)
Public Property Inner As Boolean

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
Radius Property (ISwDMDimXpertFilletFeature)	

 Syntax

Visual Basic for Applications (VBA)
Public Property Radius As Double

ISwDMDimXpertFlatnessGeoTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ISwDMDimXpertFlatnessGeoTol Object

Object Model

ISwDMDimXpertFlatnessGeoTol

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ISwDMDimXpertFlatnessGeoTol Object Members

Public Methods

 [GetPerUnitArea](#)

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

GetPerUnitArea Method (ISwDMDimXpertFlatnessGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPerUnitArea( _  
    ByRef Enabled As Boolean, _  
    ByRef Length As Double, _  
    ByRef width As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
    ) As Boolean
```


ISwDMDimXpertGeometricTolerance (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertGeometricTolerance Object

Object Model



SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertGeometricTolerance Object Members

Public Methods

	GetPrimaryDatumCount
	GetPrimaryDatumModifiers
	GetPrimaryDatums
	GetSecondaryDatumCount
	GetSecondaryDatumModifiers
	GetSecondaryDatums
	GetTertiaryDatumCount
	GetTertiaryDatumModifiers
	GetTertiaryDatums
	IGetPrimaryDatumModifiers
	IGetPrimaryDatums
	IGetSecondaryDatumModifiers
	IGetSecondaryDatums
	IGetTertiaryDatumModifiers
	IGetTertiaryDatums

Public Properties

	Tolerance
---	---------------------------

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetPrimaryDatumCount Method (ISwDMDimXpertGeometricTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPrimaryDatumCount() As Long
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetPrimaryDatumModifiers Method (ISwDMDimXpertGeometricTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPrimaryDatumModifiers() As Variant
```

GetPrimaryDatums Method (ISwDMDimXpertGeometricTolerance) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetPrimaryDatums() As Variant
```

GetSecondaryDatumCount Method (ISwDMDimXpertGeometricTolerance) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetSecondaryDatumCount() As Long
```

GetSecondaryDatumModifiers Method (ISwDMDimXpertGeometricTolerance) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetSecondaryDatumModifiers() As Variant
```

GetSecondaryDatums Method (ISwDMDimXpertGeometricTolerance) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetSecondaryDatums() As Variant
```

GetTertiaryDatumCount Method (ISwDMDimXpertGeometricTolerance) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetTertiaryDatumCount() As Long
```

GetTertiaryDatumModifiers Method (ISwDMDimXpertGeometricTolerance) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetTertiaryDatumModifiers() As Variant
```

GetTertiaryDatums Method (ISwDMDimXpertGeometricTolerance) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetTertiaryDatums() As Variant
```

IGetPrimaryDatumModifiers Method (ISwDMDimXpertGeometricTolerance) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function IGetPrimaryDatumModifiers( _  
    ByVal Count As Long _
```

) As [swDmDimXpertMaterialConditionModifier_e](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IGetPrimaryDatums Method (ISwMDimXpertGeometricTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetPrimaryDatums( _  
    ByVal Count As Long _  
) As swDmDimXpertDatum
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IGetSecondaryDatumModifiers Method (ISwMDimXpertGeometricTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetSecondaryDatumModifiers( _  
    ByVal Count As Long _  
) As swDmDimXpertMaterialConditionModifier\_e
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IGetSecondaryDatums Method (ISwMDimXpertGeometricTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetSecondaryDatums( _  
    ByVal Count As Long _  
) As swDmDimXpertDatum
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IGetTertiaryDatumModifiers Method (ISwMDimXpertGeometricTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetTertiaryDatumModifiers( _  
    ByVal Count As Long _  
) As swDmDimXpertMaterialConditionModifier\_e
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IGetTertiaryDatums Method (ISwMDimXpertGeometricTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetTertiaryDatums( _  
    ByVal Count As Long _  
) As swDmDimXpertDatum
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

Tolerance Property (ISwMDimXpertGeometricTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Tolerance As Double
```


ISwDMDimXpertIntersectCircleFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertIntersectCircleFeature Object

Object Model



SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertIntersectCircleFeature Object Members

Public Methods

 [GetIntersectFeature](#)

 [GetNominalCircle](#)

 [GetPlaneFeature](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetIntersectFeature Method (ISwDMDimXpertIntersectCircleFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetIntersectFeature() As SwDMDimXpertFeature
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalCircle Method (ISwDMDimXpertIntersectCircleFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalCircle( _
    ByRef R As Double, _
    ByRef X As Double, _
    ByRef Y As Double, _
    ByRef Z As Double, _
    ByRef I As Double, _
    ByRef J As Double, _
    ByRef K As Double _
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetPlaneFeature Method (ISwDMDimXpertIntersectCircleFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPlaneFeature() As SwDMDimXpertFeature
```

ISwDMDimXpertIntersectLineFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertIntersectLineFeature Object

Object Model

ISwDMDimXpertIntersectLineFeature

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertIntersectLineFeature Object Members

Public Methods

 [GetNominalLine](#)

 [GetPlaneFeatures](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalLine Method (ISwDMDimXpertIntersectLineFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalLine( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetPlaneFeatures Method (ISwDMDimXpertIntersectLineFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPlaneFeatures( _  
    ByRef Feature1 As SwDMDimXpertFeature, _  
    ByRef Feature2 As SwDMDimXpertFeature _  
    ) As Boolean
```

ISwDMDimXpertIntersectPlaneFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertIntersectPlaneFeature Object

Object Model

ISwDMDimXpertIntersectPlaneFeature

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertIntersectPlaneFeature Object Members

Public Methods

 [GetFeatures](#)

 [GetNominalPlane](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetFeatures Method (ISwDMDimXpertIntersectPlaneFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFeatures( _  
    ByRef Feature1 As SwDMDimXpertFeature, _  
    ByRef Feature2 As SwDMDimXpertFeature _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalPlane Method (ISwDMDimXpertIntersectPlaneFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalPlane( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

ISwDMDimXpertIntersectPointFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertIntersectPointFeature Object

Object Model

ISwDMDimXpertIntersectPointFeature

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertIntersectPointFeature Object Members

Public Methods

- [GetFeatures](#)
- [GetNominalPoint](#)
- [GetNominalVector](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetFeatures Method (ISwDMDimXpertIntersectPointFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFeatures( _  
    ByRef Feature1 As SwDMDimXpertFeature, _  
    ByRef Feature2 As SwDMDimXpertFeature _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalPoint Method (ISwDMDimXpertIntersectPointFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalPoint( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalVector Method (ISwDMDimXpertIntersectPointFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalVector( _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
    ) As Boolean
```

ISwDMDimXpertLengthDimTol (Type)

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
ISwDMDimXpertLengthDimTol Object	

 Object Model

ISwDMDimXpertLengthDimTol

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
ISwDMDimXpertLengthDimTol Object Members	
	

ISwDMDimXpertLineProfileGeoTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertLineProfileGeoTol Object

Object Model

ISwDMDimXpertLineProfileGeoTol

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertLineProfileGeoTol Object Members

Public Methods

 [GetPlanarZoneVector](#)

Public Properties

 [OuterToleranceValue](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetPlanarZoneVector Method (ISwDMDimXpertLineProfileGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPlanarZoneVector( _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

OuterToleranceValue Property (ISwDMDimXpertLineProfileGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Property OuterToleranceValue As Double
```

ISwDMDimXpertOrientationGeoTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertOrientationGeoTol Object

Object Model

ISwDMDimXpertOrientationGeoTol

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertOrientationGeoTol Object Members

Public Methods

 GetMaxTolerance
 GetPlanarZoneVector
 GetProjectedZone
 IsTangentPlane

Public Properties

 Modifier
 ZoneType

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetMaxTolerance Method (ISwDMDimXpertOrientationGeoTol)

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function GetMaxTolerance(_ ByRef <i>IsMax</i> As Boolean, _ ByRef <i>Tolerance</i> As Double _) As Boolean</pre>

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetPlanarZoneVector Method (ISwDMDimXpertOrientationGeoTol)

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function GetPlanarZoneVector(_ ByRef <i>I</i> As Double, _ ByRef <i>J</i> As Double, _ ByRef <i>K</i> As Double _) As Boolean</pre>

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetProjectedZone Method (ISwDMDimXpertOrientationGeoTol)

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function GetProjectedZone(_ ByRef <i>Enabled</i> As Boolean, _ ByRef <i>Value</i> As Double _) As Boolean</pre>

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IsTangentPlane Method (ISwDMDimXpertOrientationGeoTol)



Visual Basic for Applications (VBA)

```
Public Function IsTangentPlane() As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

Modifier Property (ISwDMDimXpertOrientationGeoTol)



Visual Basic for Applications (VBA)

```
Public Property Modifier As swDmDimXpertMaterialConditionModifier\_e
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ZoneType Property (ISwDMDimXpertOrientationGeoTol)



Visual Basic for Applications (VBA)

```
Public Property ZoneType As swDmDimXpertOrientationZoneType\_e
```

ISwDMDimXpertParallelismGeoTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ISwDMDimXpertParallelismGeoTol Object

 Object Model

ISwDMDimXpertParallelismGeoTol

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ISwDMDimXpertParallelismGeoTol Object Members




ISwDMDimXpertPart (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertPart Object

Object Model



SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertPart Object Members

Public Methods

 [GetAnnotationCount](#)

 [GetAnnotations](#)

 [GetBlockTolerances](#)

 [GetFeatureCount](#)

 [GetFeatures](#)

 [IGetAnnotations](#)

 [IGetFeatures](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetAnnotationCount Method (ISwDMDimXpertPart)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetAnnotationCount() As Long
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetAnnotations Method (ISwDMDimXpertPart)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetAnnotations() As Variant
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetBlockTolerances Method (ISwDMDimXpertPart)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetBlockTolerances() As SwDMDimXpertBlockTolerances
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetFeatureCount Method (ISwDMDimXpertPart)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFeatureCount() As Long
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetFeatures Method (ISwMDimXpertPart)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFeatures() As Variant
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IGetAnnotations Method (ISwMDimXpertPart)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetAnnotations( _  
    ByVal Count As Long _  
) As SwMDimXpertAnnotation
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IGetFeatures Method (ISwMDimXpertPart)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetFeatures( _  
    ByVal Count As Long _  
) As SwMDimXpertFeature
```

ISwDMDimXpertPatternAngleBetweenDimTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ISwDMDimXpertPatternAngleBetweenDimTol Object

 Object Model

ISwDMDimXpertPatternAngleBetweenDimTol

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ISwDMDimXpertPatternAngleBetweenDimTol Object Members




ISwDMDimXpertPatternFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertPatternFeature Object

Object Model



SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertPatternFeature Object Members



Public Methods

- [GetSubFeatureCount](#)
- [GetSubFeatures](#)
- [IGetSubFeatures](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetSubFeatureCount Method (ISwDMDimXpertPatternFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSubFeatureCount() As Long
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetSubFeatures Method (ISwDMDimXpertPatternFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSubFeatures() As Variant
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IGetSubFeatures Method (ISwDMDimXpertPatternFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetSubFeatures( _  
    ByVal Count As Long _  
) As SwDMDimXpertFeature
```

ISwDMDimXpertPerpendicularityGeoTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ISwDMDimXpertPerpendicularityGeoTol Object

 Object Model

ISwDMDimXpertPerpendicularityGeoTol

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ISwDMDimXpertPerpendicularityGeoTol Object Members



ISwDMDimXpertPlaneFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertPlaneFeature Object

Object Model

ISwDMDimXpertPlaneFeature

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ISwDMDimXpertPlaneFeature Object Members

Public Methods

GetNominalPlane

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalPlane Method (ISwDMDimXpertPlaneFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalPlane( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```