

SOLIDWORKS Document Manager API (VB6 COM)

— Reference (5/8): SwDMCutListItem2- SwDMDimXpertCylinderFeature

SOLIDWORKS API Documentation (converted from CHM)

SwDMCutListItem2 (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMCutListItem2 Object

Object Model

SwDMCutListItem2

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMCutListItem2 Object Members

Public Methods

-  [AddCustomProperty](#)
-  [DeleteCustomProperty](#)
-  [GetCustomPropertyValue2](#)
-  [SetCustomProperty](#)

Public Properties

-  [ChildFolderName](#)
-  [IsSubFolder](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

AddCustomProperty Method (SwDMCutListItem2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function AddCustomProperty( _  
    ByVal FieldName As String, _  
    ByVal FieldType As SwDmCustomInfoType, _  
    ByVal FieldValue As String _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ChildFolderName Property (SwDMCutListItem2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property ChildFolderName As String
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

DeleteCustomProperty Method (SwDMCutListItem2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function DeleteCustomProperty( _  
    ByVal FieldName As String _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetCustomPropertyValue2 Method (SwDMCutListItem2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCustomPropertyValue2( _  
    ByVal FieldName As String, _  
    ByRef type As SwDmCustomInfoType, _  
    ByRef linkedTo As String _  
    ) As String
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IsSubFolder Property (SwDMCutListItem2)

Syntax

Visual Basic for Applications (VBA)

```
Public Property IsSubFolder As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SetCustomProperty Method (SwDMCutListItem2)

Syntax

Visual Basic for Applications (VBA)

```
Public Function SetCustomProperty( _  
    ByVal FieldName As String, _  
    ByVal newValue As String _  
    ) As Boolean
```

SwDMCutListItem3 (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMCutListItem3 Object

Object Model

SwDMCutListItem3

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMCutListItem3 Object Members

Public Methods

IsCustomPropertyEditable

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IsCustomPropertyEditable Method (SwDMCutListItem3)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsCustomPropertyEditable( _  
    ByVal FieldName As String, _  
    ByRef IsEditable As Boolean _  
) As HRESULT
```

SwDMCutListItem4 (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMCutListItem4 Object

Object Model

SwDMCutListItem4

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMCutListItem4 Object Members

Public Properties

 [CutlistType](#)

 [ExcludeFromCutlist](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

CutlistType Property (SwDMCutListItem4)

Syntax

Visual Basic for Applications (VBA)

Public Property CutlistType As [swDMCutListType_e](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ExcludeFromCutlist Property (SwDMCutListItem4)

Syntax

Visual Basic for Applications (VBA)

Public Property ExcludeFromCutlist As [swDMCutListExclusionStatus_e](#)

swDMCutListType_e (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

swDMCutListType_e Enumeration

[See Also](#)



Members

Member	Value	Description
swDMCutListType_Sheetmetal	2	
swDMCutListType_SolidBody	1	
swDMCutListType_Unknown	-1	
swDMCutListType_Weldment	3	

SwDmDesignTableDataError (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDmDesignTableDataError Enumeration

[See Also](#)



Members

Member	Value	Description
swDmDesignTableDataError_ExternalTableFound	0	
swDmDesignTableDataError_Fail	5	
swDmDesignTableDataError_InternalTable	1	
swDmDesignTableDataError_NoData	4	
swDmDesignTableDataError_NoTable	2	
swDMDesigTableDataError_ExternalTableNotFound	3	


SwDMDimXpertAngleBetweenDimTol (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertAngleBetweenDimTol Object

[Send comments on this topic.](#)

Object Model



SOLIDWORKS Document Manager Type Library

SwDMDimXpertAngleBetweenDimTol Object Members

[Send comments on this topic.](#)

Public Methods

[GetDirectionVector](#)

Public Properties

[OriginFeature](#)

[Supplement](#)

SOLIDWORKS Document Manager Type Library

GetDirectionVector Method (SwDMDimXpertAngleBetweenDimTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDirectionVector( _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

OriginFeature Property (SwDMDimXpertAngleBetweenDimTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Property OriginFeature As SwDMDimXpertFeature
```

SOLIDWORKS Document Manager Type Library

Supplement Property (SwDMDimXpertAngleBetweenDimTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Supplement As Boolean
```

SwDMDimXpertAngularityGeoTol (Type)

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
SwDMDimXpertAngularityGeoTol Object	

 Object Model

SwDMDimXpertAngularityGeoTol

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
SwDMDimXpertAngularityGeoTol Object Members	
	


SwDMDimXpertAnnotation (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertAnnotation Object

[Send comments on this topic.](#)

Object Model



SOLIDWORKS Document Manager Type Library

SwDMDimXpertAnnotation Object Members

[Send comments on this topic.](#)

Public Methods

	GetCadIdentifierCount
	GetCadIdentifiers
	IGetCadIdentifiers
	IsFreeState
	IsStatistical
	IsSuppressed
	IsToBeInspected

Public Properties

	Feature
	Name
	Type

SOLIDWORKS Document Manager Type Library

Feature Property (SwDMDimXpertAnnotation)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Feature As SwDMDimXpertFeature
```

SOLIDWORKS Document Manager Type Library

GetCadIdentifierCount Method (SwDMDimXpertAnnotation)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCadIdentifierCount() As Long
```

SOLIDWORKS Document Manager Type Library

GetCadIdentifiers Method (SwDMDimXpertAnnotation)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetCadIdentifiers() As Variant
```

SOLIDWORKS Document Manager Type Library

IGetCadIdentifiers Method (SwDMDimXpertAnnotation)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetCadIdentifiers( _  
    ByVal Count As Long _  
    ) As String
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IsFreeState Method (SwMDimXpertAnnotation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsFreeState() As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IsStatistical Method (SwMDimXpertAnnotation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsStatistical() As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IsSuppressed Method (SwMDimXpertAnnotation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsSuppressed() As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IsToBeInspected Method (SwMDimXpertAnnotation)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsToBeInspected() As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

Name Property (SwMDimXpertAnnotation)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Name As String
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

type Property (SwMDimXpertAnnotation)

Syntax

Visual Basic for Applications (VBA)

```
Public Property type As swDmDimXpertAnnotationType\_e
```

swDmDimXpertAnnotationType_e (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

swDmDimXpertAnnotationType_e Enumeration

[See Also](#)

Members

Member	Value	Description
swDmDimXpertAnnotationType_unknown	0	
swDmDimXpertDatum	150	
swDmDimXpertDimTol_AngleBetween	106	
swDmDimXpertDimTol_ChamferDimension	105	
swDmDimXpertDimTol_CompositeDistanceBetween	113	
swDmDimXpertDimTol_ConeAngle	108	
swDmDimXpertDimTol_CounterBore	102	
swDmDimXpertDimTol_CounterSinkAngle	107	
swDmDimXpertDimTol_CounterSinkDiameter	104	
swDmDimXpertDimTol_Depth	103	
swDmDimXpertDimTol_Diameter	109	
swDmDimXpertDimTol_DistanceBetween	101	
swDmDimXpertDimTol_Length	110	
swDmDimXpertDimTol_PatternAngleBetween	114	
swDmDimXpertDimTol_Radius	111	
swDmDimXpertDimTol_Width	112	
swDmDimXpertGeoTol_Angularity	210	
swDmDimXpertGeoTol_Circularity	216	
swDmDimXpertGeoTol_CircularRunout	214	
swDmDimXpertGeoTol_CompositeLineProfile	206	
swDmDimXpertGeoTol_CompositePosition	202	
swDmDimXpertGeoTol_CompositeSurfaceProfile	208	
swDmDimXpertGeoTol_Concentricity	204	
swDmDimXpertGeoTol_Cylindricity	217	
swDmDimXpertGeoTol_Flatness	215	
swDmDimXpertGeoTol_LineProfile	205	
swDmDimXpertGeoTol_Parallelism	211	
swDmDimXpertGeoTol_Perpendicularity	212	
swDmDimXpertGeoTol_Position	201	
swDmDimXpertGeoTol_Straightness	218	
swDmDimXpertGeoTol_SurfaceProfile	207	
swDmDimXpertGeoTol_Symmetry	203	
swDmDimXpertGeoTol_Tangency	219	
swDmDimXpertGeoTol_TotalRunout	213	


SwDMDimXpertBestFitPlaneFeature (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertBestFitPlaneFeature Object

[Send comments on this topic.](#)

Object Model



SOLIDWORKS Document Manager Type Library

SwDMDimXpertBestFitPlaneFeature Object Members

[Send comments on this topic.](#)

Public Methods

	GetNominalPlane
	GetSubFeatureCount
	GetSubFeatures
	IGetSubFeatures

SOLIDWORKS Document Manager Type Library

GetNominalPlane Method (SwDMDimXpertBestFitPlaneFeature)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalPlane( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

GetSubFeatureCount Method (SwDMDimXpertBestFitPlaneFeature)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSubFeatureCount() As Long
```

SOLIDWORKS Document Manager Type Library

GetSubFeatures Method (SwDMDimXpertBestFitPlaneFeature)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSubFeatures() As Variant
```

SOLIDWORKS Document Manager Type Library

IGetSubFeatures Method (SwDMDimXpertBestFitPlaneFeature)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetSubFeatures( _  
    ByVal Count As Long _  
) As SwDMDimXpertFeature
```


SwDMDimXpertBlockTolerances (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertBlockTolerances Object

Object Model

SwDMDimXpertBlockTolerances

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertBlockTolerances Object Members

Public Methods

 [GetISO2768PartType](#)

 [GetToleranceValues](#)

Public Properties

 [Type](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetISO2768PartType Method (SwDMDimXpertBlockTolerances)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetISO2768PartType( _  
    ByRef type As swDmDimXpertISO2768PartType\_e _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetToleranceValues Method (SwDMDimXpertBlockTolerances)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetToleranceValues( _  
    ByRef Linear1 As Double, _  
    ByRef Linear1Prec As Long, _  
    ByRef Linear2 As Double, _  
    ByRef Linear2Prec As Long, _  
    ByRef Linear3 As Double, _  
    ByRef Linear3Prec As Long, _  
    ByRef Angular As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

type Property (SwDMDimXpertBlockTolerances)

Syntax

Visual Basic for Applications (VBA)

```
Public Property type As swDmDimXpertBlockToleranceType\_e
```

swDmDimXpertBlockToleranceType_e (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

swDmDimXpertBlockToleranceType_e Enumeration

[See Also](#)



Members

Member	Value	Description
swDmDimXpertBlockToleranceType_ASMEInch	1	
swDmDimXpertBlockToleranceType_ISO2768	2	
swDmDimXpertBlockToleranceType_unknown	0	

swDmDimXpertChamferAngleType_e (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

swDmDimXpertChamferAngleType_e Enumeration

[See Also](#)



Members

Member	Value	Description
swDmDimXpertChamferAngleType_Concave	1	
swDmDimXpertChamferAngleType_Convex	2	
swDmDimXpertChamferAngleType_unknown	0	

swDmDimXpertChamferDimensionType_e (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

swDmDimXpertChamferDimensionType_e Enumeration

[See Also](#)



Members

Member	Value	Description
swDmDimXpertChamferDimensionType_Angle	1	
swDmDimXpertChamferDimensionType_LinearDistance1	2	
swDmDimXpertChamferDimensionType_LinearDistance2	3	
swDmDimXpertChamferDimensionType_unknown	0	

SwDMDimXpertChamferDimTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertChamferDimTol Object

Object Model

SwDMDimXpertChamferDimTol

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertChamferDimTol Object Members

Public Properties

ChamferType

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ChamferType Property (SwDMDimXpertChamferDimTol)

Syntax

Visual Basic for Applications (VBA)

Public Property ChamferType As [swDmDimXpertChamferDimensionType_e](#)

SwDMDimXpertChamferFeature (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertChamferFeature Object

[Send comments](#) on this topic.

Object Model

SwDMDimXpertChamferFeature

SOLIDWORKS Document Manager Type Library

SwDMDimXpertChamferFeature Object Members

[Send comments](#) on this topic.

Public Properties

 Angle
 AngleType
 ChamferType
 Distance1
 Distance2

SOLIDWORKS Document Manager Type Library

Angle Property (SwDMDimXpertChamferFeature)

[Send comments](#) on this topic.

Syntax

Visual Basic for Applications (VBA)

Public Property Angle As Double

SOLIDWORKS Document Manager Type Library

AngleType Property (SwDMDimXpertChamferFeature)

[Send comments](#) on this topic.

Syntax

Visual Basic for Applications (VBA)

Public Property AngleType As [swDmDimXpertChamferAngleType_e](#)

SOLIDWORKS Document Manager Type Library

ChamferType Property (SwDMDimXpertChamferFeature)

[Send comments](#) on this topic.

Syntax

Visual Basic for Applications (VBA)

Public Property ChamferType As [swDmDimXpertChamferType_e](#)

SOLIDWORKS Document Manager Type Library

Distance1 Property (SwDMDimXpertChamferFeature)

[Send comments](#) on this topic.

Syntax

Visual Basic for Applications (VBA)

Public Property Distance1 As Double

SOLIDWORKS Document Manager Type Library

Distance2 Property (SwDMDimXpertChamferFeature)

[Send comments](#) on this topic.

Syntax

Visual Basic for Applications (VBA)

Public Property Distance2 As Double

swDmDimXpertChamferType_e (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

swDmDimXpertChamferType_e Enumeration

[See Also](#)



Members

Member	Value	Description
swDmDimXpertChamferType_DistanceAngle	1	
swDmDimXpertChamferType_DistanceDistance	2	
swDmDimXpertChamferType_unknown	0	
swDmDimXpertChamferType_Vertex	3	

SwDMDimXpertCircularityGeoTol (Type)

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
SwDMDimXpertCircularityGeoTol Object	

 Object Model

SwDMDimXpertCircularityGeoTol

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
SwDMDimXpertCircularityGeoTol Object Members	
	

SwDMDimXpertCircularRunoutGeoTol (Type)

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
SwDMDimXpertCircularRunoutGeoTol Object	

 Object Model

SwDMDimXpertCircularRunoutGeoTol

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
SwDMDimXpertCircularRunoutGeoTol Object Members	
	

SwDMDimXpertCompositeDistanceBetweenDimTol (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertCompositeDistanceBetweenDimTol Object

[Send comments on this topic.](#)

Object Model

SwDMDimXpertCompositeDistanceBetweenDimTol

SOLIDWORKS Document Manager Type Library

SwDMDimXpertCompositeDistanceBetweenDimTol Object Members

[Send comments on this topic.](#)

Public Methods

	GetDirectionVector
	GetFeature
	GetIntraFeature
	GetNominalValueIntraFeature
	GetOriginFeature
	GetPlusAndMinusToleranceIntraFeature
	GetUpperAndLowerLimitIntraFeature

Public Properties

	BlockToleranceDecimalPlacesIntraFeature
	DimensionTypeIntraFeature
	LimitsAndFitsCodeIntraFeature

SOLIDWORKS Document Manager Type Library

BlockToleranceDecimalPlacesIntraFeature Property (SwDMDimXpertCompositeDistanceBetweenDimTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)
Public Property BlockToleranceDecimalPlacesIntraFeature As Long

SOLIDWORKS Document Manager Type Library

DimensionTypeIntraFeature Property (SwDMDimXpertCompositeDistanceBetweenDimTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)
Public Property DimensionTypeIntraFeature As swDmDimXpertDimensionToleranceType_e

SOLIDWORKS Document Manager Type Library

GetDirectionVector Method (SwDMDimXpertCompositeDistanceBetweenDimTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)
Public Function GetDirectionVector(_ ByRef I As Double, _ ByRef J As Double, _ ByRef K As Double _) As Boolean

SOLIDWORKS Document Manager Type Library

GetFeature Method (SwDMDimXpertCompositeDistanceBetweenDimTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFeature( _  
    ByRef Feature As SwDMDimXpertFeature, _  
    ByRef FosUsage As swDmDimXpertDistanceFosUsage\_e _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetIntraFeature Method (SwDMDimXpertCompositeDistanceBetweenDimTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetIntraFeature( _  
    ByRef Feature As SwDMDimXpertFeature, _  
    ByRef FosUsage As swDmDimXpertDistanceFosUsage\_e _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalValueIntraFeature Method (SwDMDimXpertCompositeDistanceBetweenDimTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalValueIntraFeature() As Double
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetOriginFeature Method (SwDMDimXpertCompositeDistanceBetweenDimTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetOriginFeature( _  
    ByRef Feature As SwDMDimXpertFeature, _  
    ByRef FosUsage As swDmDimXpertDistanceFosUsage\_e _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetPlusAndMinusToleranceIntraFeature Method (SwDMDimXpertCompositeDistanceBetweenDimTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPlusAndMinusToleranceIntraFeature( _  
    ByRef Plus As Double, _  
    ByRef Minus As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetUpperAndLowerLimitIntraFeature Method (SwDMDimXpertCompositeDistanceBetweenDimTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetUpperAndLowerLimitIntraFeature( _  
    ByRef Upper As Double, _  
    ByRef Lower As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

LimitsAndFitsCodeIntraFeature Property (SwDMDimXpertCompositeDistanceBetweenDimTol)

Syntax

Visual Basic for Applications (VBA)

Public Property LimitsAndFitsCodeIntraFeature As String

SwDMDimXpertCompositeLineProfileGeoTol (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertCompositeLineProfileGeoTol Object

[Send comments on this topic.](#)

Object Model

SwDMDimXpertCompositeLineProfileGeoTol

SOLIDWORKS Document Manager Type Library

SwDMDimXpertCompositeLineProfileGeoTol Object Members

Public Methods

 [GetPlanarZoneVector](#)

Public Properties

 [OuterToleranceValue](#)

 [OuterToleranceValueLowerTier](#)

 [PrimaryInLowerTier](#)

 [SecondaryInLowerTier](#)

 [TertiaryInLowerTier](#)

 [ToleranceLowerTier](#)

SOLIDWORKS Document Manager Type Library

GetPlanarZoneVector Method (SwDMDimXpertCompositeLineProfileGeoTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPlanarZoneVector( _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

OuterToleranceValue Property (SwDMDimXpertCompositeLineProfileGeoTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Property OuterToleranceValue As Double
```

SOLIDWORKS Document Manager Type Library

OuterToleranceValueLowerTier Property (SwDMDimXpertCompositeLineProfileGeoTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Property OuterToleranceValueLowerTier As Double
```

SOLIDWORKS Document Manager Type Library

PrimaryInLowerTier Property (SwDMDimXpertCompositeLineProfileGeoTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Property PrimaryInLowerTier As Boolean
```

SecondaryInLowerTier Property (SwDMDimXpertCompositeLineProfileGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Property SecondaryInLowerTier As Boolean
```

TertiaryInLowerTier Property (SwDMDimXpertCompositeLineProfileGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Property TertiaryInLowerTier As Boolean
```

ToleranceLowerTier Property (SwDMDimXpertCompositeLineProfileGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Property ToleranceLowerTier As Double
```

SwDMDimXpertCompositePositionGeoTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertCompositePositionGeoTol Object

Object Model

SwDMDimXpertCompositePositionGeoTol

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertCompositePositionGeoTol Object Members

Public Methods

 GetMaxTolerance
 GetMaxToleranceLowerTier
 GetPlanarZoneVector
 GetProjectedZone

Public Properties

 Modifier
 ModifierLowerTier
 PrimaryInLowerTier
 SecondaryInLowerTier
 TertiaryInLowerTier
 ToleranceLowerTier
 ZoneType

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetMaxTolerance Method (SwDMDimXpertCompositePositionGeoTol)

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function GetMaxTolerance(_ ByRef <i>IsMax</i> As Boolean, _ ByRef <i>Tolerance</i> As Double _) As Boolean</pre>

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetMaxToleranceLowerTier Method (SwDMDimXpertCompositePositionGeoTol)

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function GetMaxToleranceLowerTier(_ ByRef <i>IsMax</i> As Boolean, _ ByRef <i>Tolerance</i> As Double _) As Boolean</pre>

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetPlanarZoneVector Method (SwDMDimXpertCompositePositionGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPlanarZoneVector( _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetProjectedZone Method (SwDMDimXpertCompositePositionGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetProjectedZone( _  
    ByRef Enabled As Boolean, _  
    ByRef Value As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

Modifier Property (SwDMDimXpertCompositePositionGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Modifier As swDmDimXpertMaterialConditionModifier\_e
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ModifierLowerTier Property (SwDMDimXpertCompositePositionGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Property ModifierLowerTier As swDmDimXpertMaterialConditionModifier\_e
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

PrimaryInLowerTier Property (SwDMDimXpertCompositePositionGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Property PrimaryInLowerTier As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SecondaryInLowerTier Property (SwDMDimXpertCompositePositionGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Property SecondaryInLowerTier As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

TertiaryInLowerTier Property (SwDMDimXpertCompositePositionGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Property TertiaryInLowerTier As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ToleranceLowerTier Property (SwDMDimXpertCompositePositionGeoTol)

Syntax

Visual Basic for Applications (VBA)

Public Property ToleranceLowerTier As Double

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ZoneType Property (SwDMDimXpertCompositePositionGeoTol)

 **Syntax**

Visual Basic for Applications (VBA)

Public Property ZoneType As [swDmDimXpertPositionZoneType_e](#)

SwDMDimXpertCompositeSurfaceProfileGeoTol (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertCompositeSurfaceProfileGeoTol Object

[Send comments on this topic.](#)

Object Model

SwDMDimXpertCompositeSurfaceProfileGeoTol

SOLIDWORKS Document Manager Type Library

SwDMDimXpertCompositeSurfaceProfileGeoTol Object Members

Public Properties

 OuterToleranceValue
 OuterToleranceValueLowerTier
 PrimaryInLowerTier
 SecondaryInLowerTier
 TertiaryInLowerTier
 ToleranceLowerTier

SOLIDWORKS Document Manager Type Library

OuterToleranceValue Property (SwDMDimXpertCompositeSurfaceProfileGeoTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)
Public Property OuterToleranceValue As Double

SOLIDWORKS Document Manager Type Library

OuterToleranceValueLowerTier Property (SwDMDimXpertCompositeSurfaceProfileGeoTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)
Public Property OuterToleranceValueLowerTier As Double

SOLIDWORKS Document Manager Type Library

PrimaryInLowerTier Property (SwDMDimXpertCompositeSurfaceProfileGeoTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)
Public Property PrimaryInLowerTier As Boolean

SOLIDWORKS Document Manager Type Library

SecondaryInLowerTier Property (SwDMDimXpertCompositeSurfaceProfileGeoTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)
Public Property SecondaryInLowerTier As Boolean

SOLIDWORKS Document Manager Type Library

TertiaryInLowerTier Property (SwDMDimXpertCompositeSurfaceProfileGeoTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

Public Property TertiaryInLowerTier As Boolean

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

ToleranceLowerTier Property (SwDMDimXpertCompositeSurfaceProfileGeoTol)



Visual Basic for Applications (VBA)

Public Property ToleranceLowerTier As Double


SwDMDimXpertCompoundClosedSlot3dFeature (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertCompoundClosedSlot3dFeature Object

[Send comments on this topic.](#)

Object Model



SOLIDWORKS Document Manager Type Library

SwDMDimXpertCompoundClosedSlot3dFeature Object Members

[Send comments on this topic.](#)

Public Methods

	GetBottomFeature
	GetEndFeatures
	GetNominalBottomPlane
	GetNominalClosedSlot
	GetNominalTopPlane
	GetPlaneFeatures

Public Properties

	Blind
--	-----------------------

SOLIDWORKS Document Manager Type Library

Blind Property (SwDMDimXpertCompoundClosedSlot3dFeature)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)
Public Property Blind As Boolean

SOLIDWORKS Document Manager Type Library

GetBottomFeature Method (SwDMDimXpertCompoundClosedSlot3dFeature)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)
Public Function GetBottomFeature() As SwDMDimXpertFeature

SOLIDWORKS Document Manager Type Library

GetEndFeatures Method (SwDMDimXpertCompoundClosedSlot3dFeature)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)
Public Function GetEndFeatures(ByRef End1 As SwDMDimXpertFeature , ByRef End2 As SwDMDimXpertFeature) As Boolean

SOLIDWORKS Document Manager Type Library

GetNominalBottomPlane Method (SwDMDimXpertCompoundClosedSlot3dFeature)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalBottomPlane( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

GetNominalClosedSlot Method (SwDMDimXpertCompoundClosedSlot3dFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalClosedSlot( _  
    ByRef width As Double, _  
    ByRef Length As Double, _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double, _  
    ByRef LongitudeI As Double, _  
    ByRef LongitudeJ As Double, _  
    ByRef LongitudeK As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

GetNominalTopPlane Method (SwDMDimXpertCompoundClosedSlot3dFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalTopPlane( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

GetPlaneFeatures Method (SwDMDimXpertCompoundClosedSlot3dFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPlaneFeatures( _  
    ByRef Plane1 As SwDMDimXpertPlaneFeature, _  
    ByRef Plane2 As SwDMDimXpertPlaneFeature _  
) As Boolean
```


SwDMDimXpertCompoundHoleFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertCompoundHoleFeature Object

Object Model



SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertCompoundHoleFeature Object Members

Public Methods

	GetBottomFeature
	GetReferenceFeature
	GetSubFeatureCount
	GetSubFeatures
	IGetSubFeatures

Public Properties

	Blind
---	-----------------------

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

Blind Property (SwDMDimXpertCompoundHoleFeature)

Syntax

Visual Basic for Applications (VBA)
Public Property Blind As Boolean

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetBottomFeature Method (SwDMDimXpertCompoundHoleFeature)

Syntax

Visual Basic for Applications (VBA)
Public Function GetBottomFeature() As SwDMDimXpertFeature

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetReferenceFeature Method (SwDMDimXpertCompoundHoleFeature)

Syntax

Visual Basic for Applications (VBA)
Public Function GetReferenceFeature() As SwDMDimXpertFeature

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetSubFeatureCount Method (SwDMDimXpertCompoundHoleFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSubFeatureCount() As Long
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetSubFeatures Method (SwDMDimXpertCompoundHoleFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSubFeatures() As Variant
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IGetSubFeatures Method (SwDMDimXpertCompoundHoleFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetSubFeatures( _  
    ByVal Count As Long _  
) As SwDMDimXpertFeature
```

SwDMDimXpertCompoundNotchFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertCompoundNotchFeature Object

Object Model

SwDMDimXpertCompoundNotchFeature

GetBottomFeature (SwDMDimXpertFeature)

GetEndFeature (SwDMDimXpertFeature)

GetOpenSideReferenceFeature (SwDMDimXpertFeature)

GetTopReferenceFeature (SwDMDimXpertFeature)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertCompoundNotchFeature Object Members

Public Methods

- [GetBottomFeature](#)
- [GetEndFeature](#)
- [GetNominalBottomPlane](#)
- [GetNominalNotch](#)
- [GetOpenSideReferenceFeature](#)
- [GetPlaneFeatures](#)
- [GetTopReferenceFeature](#)

Public Properties

- [Blind](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

Blind Property (SwDMDimXpertCompoundNotchFeature)

Syntax

Visual Basic for Applications (VBA)

Public Property Blind As Boolean

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetBottomFeature Method (SwDMDimXpertCompoundNotchFeature)

Syntax

Visual Basic for Applications (VBA)

Public Function GetBottomFeature() As [SwDMDimXpertFeature](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetEndFeature Method (SwDMDimXpertCompoundNotchFeature)

Syntax

Visual Basic for Applications (VBA)

Public Function GetEndFeature() As [SwDMDimXpertFeature](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalBottomPlane Method (SwDMDimXpertCompoundNotchFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalBottomPlane( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

GetNominalNotch Method (SwDMDimXpertCompoundNotchFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalNotch( _  
    ByRef width As Double, _  
    ByRef Length As Double, _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double, _  
    ByRef LongitudeI As Double, _  
    ByRef LongitudeJ As Double, _  
    ByRef LongitudeK As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

GetOpenSideReferenceFeature Method (SwDMDimXpertCompoundNotchFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetOpenSideReferenceFeature() As SwDMDimXpertFeature
```

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

GetPlaneFeatures Method (SwDMDimXpertCompoundNotchFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPlaneFeatures( _  
    ByRef Plane1 As SwDMDimXpertPlaneFeature, _  
    ByRef Plane2 As SwDMDimXpertPlaneFeature _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

GetTopReferenceFeature Method (SwDMDimXpertCompoundNotchFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTopReferenceFeature() As SwDMDimXpertFeature
```

SwDMDimXpertCompoundWidthFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertCompoundWidthFeature Object

Object Model

SwDMDimXpertCompoundWidthFeature

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertCompoundWidthFeature Object Members

Public Methods

 [GetNominalCompoundWidth](#)

 [GetNominalLongitude](#)

 [GetPlaneFeatures](#)

Public Properties

 [Inner](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalCompoundWidth Method (SwDMDimXpertCompoundWidthFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalCompoundWidth( _  
    ByRef width As Double, _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalLongitude Method (SwDMDimXpertCompoundWidthFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalLongitude( _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetPlaneFeatures Method (SwDMDimXpertCompoundWidthFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPlaneFeatures( _  
    ByRef Plane1 As SwDMDimXpertPlaneFeature, _  
    ByRef Plane2 As SwDMDimXpertPlaneFeature _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.



Visual Basic for Applications (VBA)

```
Public Property Inner As Boolean
```

SwDMDimXpertConcentricityGeoTol (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertConcentricityGeoTol Object

[Send comments on this topic.](#)

 Object Model

SwDMDimXpertConcentricityGeoTol

SOLIDWORKS Document Manager Type Library

SwDMDimXpertConcentricityGeoTol Object Members

[Send comments on this topic.](#)

 Public Methods

 [GetMaxTolerance](#)

 Public Properties

 [Modifier](#)

SOLIDWORKS Document Manager Type Library

GetMaxTolerance Method (SwDMDimXpertConcentricityGeoTol)

[Send comments on this topic.](#)

 Syntax

Visual Basic for Applications (VBA)

```
Public Function GetMaxTolerance( _  
    ByRef IsMax As Boolean, _  
    ByRef Tolerance As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

Modifier Property (SwDMDimXpertConcentricityGeoTol)

[Send comments on this topic.](#)

 Syntax

Visual Basic for Applications (VBA)

```
Public Property Modifier As swDmDimXpertMaterialConditionModifier\_e
```

SwDMDimXpertConeAngleDimTol (Type)

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
SwDMDimXpertConeAngleDimTol Object	

 Object Model

SwDMDimXpertConeAngleDimTol

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
SwDMDimXpertConeAngleDimTol Object Members	
	

SwDMDimXpertConeFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertConeFeature Object

Object Model

SwDMDimXpertConeFeature

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertConeFeature Object Members

Public Methods

 [GetNominalBottomPlane](#)

 [GetNominalCone](#)

 [GetNominalTopPlane](#)

Public Properties

 [Inner](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalBottomPlane Method (SwDMDimXpertConeFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalBottomPlane( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalCone Method (SwDMDimXpertConeFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalCone( _  
    ByRef Angle As Double, _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalTopPlane Method (SwDMDimXpertConeFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalTopPlane( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _
```

```
ByRef I As Double, _  
ByRef J As Double, _  
ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

Inner Property (SwMDimXpertConeFeature)



Syntax

Visual Basic for Applications (VBA)

```
Public Property Inner As Boolean
```


SwDMDimXpertCounterBoreDimTol (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertCounterBoreDimTol Object

[Send comments on this topic.](#)

Object Model




SOLIDWORKS Document Manager Type Library

SwDMDimXpertCounterBoreDimTol Object Members

[Send comments on this topic.](#)

Public Properties



SOLIDWORKS Document Manager Type Library

ReferenceFeature Property (SwDMDimXpertCounterBoreDimTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Property ReferenceFeature As SwDMDimXpertFeature
```


SwDMDimXpertCounterSinkAngleDimTol (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertCounterSinkAngleDimTol Object

[Send comments on this topic.](#)

Object Model



SOLIDWORKS Document Manager Type Library

SwDMDimXpertCounterSinkAngleDimTol Object Members

[Send comments on this topic.](#)

Public Properties

 [ReferenceFeature](#)

SOLIDWORKS Document Manager Type Library

ReferenceFeature Property (SwDMDimXpertCounterSinkAngleDimTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

Public Property ReferenceFeature As [SwDMDimXpertFeature](#)


SwDMDimXpertCounterSinkDiameterDimTol (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertCounterSinkDiameterDimTol Object

[Send comments on this topic.](#)

Object Model




SOLIDWORKS Document Manager Type Library

SwDMDimXpertCounterSinkDiameterDimTol Object Members

[Send comments on this topic.](#)

Public Properties



SOLIDWORKS Document Manager Type Library

ReferenceFeature Property (SwDMDimXpertCounterSinkDiameterDimTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

Public Property ReferenceFeature As [SwDMDimXpertFeature](#)

SwDMDimXpertCylinderFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertCylinderFeature Object

Object Model

SwDMDimXpertCylinderFeature

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertCylinderFeature Object Members

Public Methods

 [GetNominalBottomPlane](#)

 [GetNominalCylinder](#)

 [GetNominalTopPlane](#)

 [GetThread](#)

Public Properties

 [Inner](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalBottomPlane Method (SwDMDimXpertCylinderFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalBottomPlane( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalCylinder Method (SwDMDimXpertCylinderFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalCylinder( _  
    ByRef R As Double, _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalTopPlane Method (SwDMDimXpertCylinderFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalTopPlane( _  
    ByRef X As Double, _
```

```
ByRef Y As Double, _  
ByRef Z As Double, _  
ByRef I As Double, _  
ByRef J As Double, _  
ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetThread Method (SwMDimXpertCylinderFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetThread( _  
    ByRef IsThreaded As Boolean, _  
    ByRef ThreadDesignation As String, _  
    ByRef ThreadDepth As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

Inner Property (SwMDimXpertCylinderFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Inner As Boolean
```