

SOLIDWORKS Document Manager API (VB6 COM)
— Reference (6/8):
SwDMDimXpertCylindricityGeoTol-
SwDMDimXpertWidthDimTol

SOLIDWORKS API Documentation (converted from CHM)

SwDMDimXpertCylindricityGeoTol (Type)

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
SwDMDimXpertCylindricityGeoTol Object	

 Object Model

SwDMDimXpertCylindricityGeoTol

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
SwDMDimXpertCylindricityGeoTol Object Members	
	

swDmDimXpertDatum (Type)

SOLIDWORKS Document Manager Type Library

swDmDimXpertDatum Object

[Send comments on this topic.](#)

Object Model

swDmDimXpertDatum

SOLIDWORKS Document Manager Type Library

swDmDimXpertDatum Object Members

[Send comments on this topic.](#)

Public Properties

 Identifier

SOLIDWORKS Document Manager Type Library

Identifier Property (swDmDimXpertDatum)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

Public Property Identifier As String


SwDMDimXpertDepthDimTol (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertDepthDimTol Object

[Send comments on this topic.](#)

Object Model



SOLIDWORKS Document Manager Type Library

SwDMDimXpertDepthDimTol Object Members

[Send comments on this topic.](#)

Public Methods

[IsThreadDepth](#)

Public Properties

[ReferenceFeature](#)

SOLIDWORKS Document Manager Type Library

IsThreadDepth Method (SwDMDimXpertDepthDimTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

Public Function IsThreadDepth() As Boolean

SOLIDWORKS Document Manager Type Library

ReferenceFeature Property (SwDMDimXpertDepthDimTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

Public Property ReferenceFeature As [SwDMDimXpertFeature](#)

SwDMDimXpertDiameterDimTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertDiameterDimTol Object

Object Model

SwDMDimXpertDiameterDimTol

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertDiameterDimTol Object Members

Public Properties

 [PatternTreatment](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

PatternTreatment Property (SwDMDimXpertDiameterDimTol)

Syntax

Visual Basic for Applications (VBA)

Public Property PatternTreatment As [swDmDimXpertPatternTreatmentType_e](#)

SwDMDimXpertDimensionTolerance (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertDimensionTolerance Object

Object Model

SwDMDimXpertDimensionTolerance

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertDimensionTolerance Object Members

Public Methods

-  [GetNominalValue](#)
-  [GetPlusAndMinusTolerance](#)
-  [GetUpperAndLowerLimit](#)

Public Properties

-  [BlockToleranceDecimalPlaces](#)
-  [DimensionType](#)
-  [LimitsAndFitsCode](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

BlockToleranceDecimalPlaces Property (SwDMDimXpertDimensionTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Property BlockToleranceDecimalPlaces As Long
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

DimensionType Property (SwDMDimXpertDimensionTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Property DimensionType As swDmDimXpertDimensionToleranceType\_e
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalValue Method (SwDMDimXpertDimensionTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalValue() As Double
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetPlusAndMinusTolerance Method (SwDMDimXpertDimensionTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPlusAndMinusTolerance( _  
    ByRef Plus As Double, _  
    ByRef Minus As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetUpperAndLowerLimit Method (SwDMDimXpertDimensionTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetUpperAndLowerLimit( _  
    ByRef Upper As Double, _  
    ByRef Lower As Double _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

LimitsAndFitsCode Property (SwDMDimXpertDimensionTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Property LimitsAndFitsCode As String
```

swDmDimXpertDimensionToleranceType_e (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

swDmDimXpertDimensionToleranceType_e Enumeration

[See Also](#)

Members

Member	Value	Description
swDmDimXpertDimensionToleranceType_unknown	0	
swDmDimXpertDimTolType_BlockTolerance	1	
swDmDimXpertDimTolType_BlockToleranceNoNominal	2	
swDmDimXpertDimTolType_ISOLimitsAndFits	3	
swDmDimXpertDimTolType_ISOLimitsAndFitsNoNominal	4	
swDmDimXpertDimTolType_LimitDimension	5	
swDmDimXpertDimTolType_MAXTolerance	6	
swDmDimXpertDimTolType_MINTolerance	7	
swDmDimXpertDimTolType_NoTolerance	8	
swDmDimXpertDimTolType_PlusMinusDimension	9	
swDmDimXpertDimTolType_PlusMinusNoNominal	10	

SwDMDimXpertDistanceBetweenDimTol (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertDistanceBetweenDimTol Object

[Send comments on this topic.](#)

Object Model

SwDMDimXpertDistanceBetweenDimTol

SOLIDWORKS Document Manager Type Library

SwDMDimXpertDistanceBetweenDimTol Object Members

Public Methods

-  [GetDirectionVector](#)
-  [GetFeature](#)
-  [GetOriginFeature](#)

Public Properties

-  [PatternTreatment](#)

SOLIDWORKS Document Manager Type Library

GetDirectionVector Method (SwDMDimXpertDistanceBetweenDimTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetDirectionVector( _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

GetFeature Method (SwDMDimXpertDistanceBetweenDimTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFeature( _  
    ByRef Feature As SwDMDimXpertFeature, _  
    ByRef FosUsage As swDmDimXpertDistanceFosUsage\_e _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

GetOriginFeature Method (SwDMDimXpertDistanceBetweenDimTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetOriginFeature( _  
    ByRef Feature As SwDMDimXpertFeature, _  
    ByRef FosUsage As swDmDimXpertDistanceFosUsage\_e _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

PatternTreatment Property (SwDMDimXpertDistanceBetweenDimTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

Public Property PatternTreatment As [swDimXpertPatternTreatmentType_e](#)

swDmDimXpertDistanceFosUsage_e (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

swDmDimXpertDistanceFosUsage_e Enumeration

[See Also](#)



Members

Member	Value	Description
swDmDimXpertDistanceFosUsage_Center	1	
swDmDimXpertDistanceFosUsage_MaximumSide	2	
swDmDimXpertDistanceFosUsage_MinimumSide	3	
swDmDimXpertDistanceFosUsage_unknown	0	


SwDMDimXpertExtrudeFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertExtrudeFeature Object

Object Model



SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertExtrudeFeature Object Members

Public Methods

	GetBottomBlends
	GetBottomFeature
	GetReferenceFeature
	GetSubFeatureCount
	GetSubFeatures
	GetTopBlends
	IGetSubFeatures

Public Properties

	Blind
---	-----------------------

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

Blind Property (SwDMDimXpertExtrudeFeature)

Syntax

Visual Basic for Applications (VBA)
Public Property Blind As Boolean

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetBottomBlends Method (SwDMDimXpertExtrudeFeature)

Syntax

Visual Basic for Applications (VBA)
Public Function GetBottomBlends() As SwDMDimXpertFeature

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetBottomFeature Method (SwDMDimXpertExtrudeFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetBottomFeature() As SwDMDimXpertFeature
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetReferenceFeature Method (SwDMDimXpertExtrudeFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetReferenceFeature() As SwDMDimXpertFeature
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetSubFeatureCount Method (SwDMDimXpertExtrudeFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSubFeatureCount() As Long
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetSubFeatures Method (SwDMDimXpertExtrudeFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSubFeatures() As Variant
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetTopBlends Method (SwDMDimXpertExtrudeFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetTopBlends() As SwDMDimXpertFeature
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IGetSubFeatures Method (SwDMDimXpertExtrudeFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetSubFeatures( _  
    ByVal Count As Long _  
) As SwDMDimXpertFeature
```

SwDMDimXpertFeature (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertFeature Object

[Send comments](#) on this topic.

Object Model

SwDMDimXpertFeature

SOLIDWORKS Document Manager Type Library

SwDMDimXpertFeature Object Members

[Send comments](#) on this topic.

Public Methods

	GetCadIdentifierCount
	GetCadIdentifiers
	IGetCadIdentifiers
	IsSuppressed

Public Properties

	Name
	Type

SOLIDWORKS Document Manager Type Library

GetCadIdentifierCount Method (SwDMDimXpertFeature)

[Send comments](#) on this topic.

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function GetCadIdentifierCount() As Long</pre>

SOLIDWORKS Document Manager Type Library

GetCadIdentifiers Method (SwDMDimXpertFeature)

[Send comments](#) on this topic.

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function GetCadIdentifiers() As Variant</pre>

SOLIDWORKS Document Manager Type Library

IGetCadIdentifiers Method (SwDMDimXpertFeature)

[Send comments](#) on this topic.

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function IGetCadIdentifiers(_ ByVal Count As Long _) As String</pre>

SOLIDWORKS Document Manager Type Library

IsSuppressed Method (SwDMDimXpertFeature)

[Send comments](#) on this topic.

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function IsSuppressed() As Boolean</pre>

SOLIDWORKS Document Manager Type Library

Name Property (SwDMDimXpertFeature)

[Send comments](#) on this topic.



Visual Basic for Applications (VBA)

Public Property Name As String

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

type Property (SwMDimXpertFeature)



Visual Basic for Applications (VBA)

Public Property type As [swDmDimXpertFeatureType_e](#)

swDmDimXpertFeatureType_e (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

swDmDimXpertFeatureType_e Enumeration

[See Also](#)

Members

Member	Value	Description
swDmDimXpertFeature_BestfitPlane	17	
swDmDimXpertFeature_Chamfer	6	
swDmDimXpertFeature_CompoundClosedSlot3D	10	
swDmDimXpertFeature_CompoundHole	7	
swDmDimXpertFeature_CompoundNotch	9	
swDmDimXpertFeature_CompoundWidth	8	
swDmDimXpertFeature_Cone	3	
swDmDimXpertFeature_Cylinder	2	
swDmDimXpertFeature_Extrude	4	
swDmDimXpertFeature_Fillet	5	
swDmDimXpertFeature_IntersectCircle	13	
swDmDimXpertFeature_IntersectLine	12	
swDmDimXpertFeature_IntersectPlane	14	
swDmDimXpertFeature_IntersectPoint	11	
swDmDimXpertFeature_Pattern	15	
swDmDimXpertFeature_Plane	1	
swDmDimXpertFeature_Sphere	16	
swDmDimXpertFeature_Surface	18	
swDmDimXpertFeatureType_unknown	0	

SwDMDimXpertFilletFeature (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertFilletFeature Object

[Send comments on this topic.](#)

Object Model

SwDMDimXpertFilletFeature

SOLIDWORKS Document Manager Type Library

SwDMDimXpertFilletFeature Object Members

[Send comments on this topic.](#)

Public Properties

Inner

Radius

SOLIDWORKS Document Manager Type Library

Inner Property (SwDMDimXpertFilletFeature)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

Public Property Inner As Boolean

SOLIDWORKS Document Manager Type Library

Radius Property (SwDMDimXpertFilletFeature)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

Public Property Radius As Double

SwDMDimXpertFlatnessGeoTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertFlatnessGeoTol Object

Object Model

SwDMDimXpertFlatnessGeoTol

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertFlatnessGeoTol Object Members

Public Methods

 [GetPerUnitArea](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetPerUnitArea Method (SwDMDimXpertFlatnessGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPerUnitArea( _  
    ByRef Enabled As Boolean, _  
    ByRef Length As Double, _  
    ByRef width As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```


SwDMDimXpertGeometricTolerance (Type)

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

SwDMDimXpertGeometricTolerance Object

Object Model



SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

SwDMDimXpertGeometricTolerance Object Members

Public Methods

	GetPrimaryDatumCount
	GetPrimaryDatumModifiers
	GetPrimaryDatums
	GetSecondaryDatumCount
	GetSecondaryDatumModifiers
	GetSecondaryDatums
	GetTertiaryDatumCount
	GetTertiaryDatumModifiers
	GetTertiaryDatums
	IGetPrimaryDatumModifiers
	IGetPrimaryDatums
	IGetSecondaryDatumModifiers
	IGetSecondaryDatums
	IGetTertiaryDatumModifiers
	IGetTertiaryDatums

Public Properties

	Tolerance
---	---------------------------

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

GetPrimaryDatumCount Method (SwDMDimXpertGeometricTolerance)

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function GetPrimaryDatumCount() As Long</pre>

SOLIDWORKS Document Manager Type Library

[Send comments on this topic.](#)

GetPrimaryDatumModifiers Method (SwDMDimXpertGeometricTolerance)

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function GetPrimaryDatumModifiers() As Variant</pre>

GetPrimaryDatums Method (SwDMDimXpertGeometricTolerance) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetPrimaryDatums() As Variant
```

GetSecondaryDatumCount Method (SwDMDimXpertGeometricTolerance) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetSecondaryDatumCount() As Long
```

GetSecondaryDatumModifiers Method (SwDMDimXpertGeometricTolerance) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetSecondaryDatumModifiers() As Variant
```

GetSecondaryDatums Method (SwDMDimXpertGeometricTolerance) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetSecondaryDatums() As Variant
```

GetTertiaryDatumCount Method (SwDMDimXpertGeometricTolerance) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetTertiaryDatumCount() As Long
```

GetTertiaryDatumModifiers Method (SwDMDimXpertGeometricTolerance) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetTertiaryDatumModifiers() As Variant
```

GetTertiaryDatums Method (SwDMDimXpertGeometricTolerance) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function GetTertiaryDatums() As Variant
```

IGetPrimaryDatumModifiers Method (SwDMDimXpertGeometricTolerance) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function IGetPrimaryDatumModifiers( _  
    ByVal Count As Long _
```

) As [swDmDimXpertMaterialConditionModifier_e](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IGetPrimaryDatums Method (SwMDimXpertGeometricTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetPrimaryDatums( _  
    ByVal Count As Long _  
) As swDmDimXpertDatum
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IGetSecondaryDatumModifiers Method (SwMDimXpertGeometricTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetSecondaryDatumModifiers( _  
    ByVal Count As Long _  
) As swDmDimXpertMaterialConditionModifier\_e
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IGetSecondaryDatums Method (SwMDimXpertGeometricTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetSecondaryDatums( _  
    ByVal Count As Long _  
) As swDmDimXpertDatum
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IGetTertiaryDatumModifiers Method (SwMDimXpertGeometricTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetTertiaryDatumModifiers( _  
    ByVal Count As Long _  
) As swDmDimXpertMaterialConditionModifier\_e
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IGetTertiaryDatums Method (SwMDimXpertGeometricTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetTertiaryDatums( _  
    ByVal Count As Long _  
) As swDmDimXpertDatum
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

Tolerance Property (SwMDimXpertGeometricTolerance)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Tolerance As Double
```

SwDMDimXpertIntersectCircleFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertIntersectCircleFeature Object

Object Model

SwDMDimXpertIntersectCircleFeature

GetIntersectFeature (SwDMDimXpertFeature)

GetPlaneFeature (SwDMDimXpertFeature)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertIntersectCircleFeature Object Members

Public Methods

 [GetIntersectFeature](#)

 [GetNominalCircle](#)

 [GetPlaneFeature](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetIntersectFeature Method (SwDMDimXpertIntersectCircleFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetIntersectFeature() As SwDMDimXpertFeature
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalCircle Method (SwDMDimXpertIntersectCircleFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalCircle( _  
    ByRef R As Double, _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetPlaneFeature Method (SwDMDimXpertIntersectCircleFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPlaneFeature() As SwDMDimXpertFeature
```

SwDMDimXpertIntersectLineFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertIntersectLineFeature Object

Object Model

SwDMDimXpertIntersectLineFeature

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertIntersectLineFeature Object Members

Public Methods

 [GetNominalLine](#)

 [GetPlaneFeatures](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalLine Method (SwDMDimXpertIntersectLineFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalLine( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetPlaneFeatures Method (SwDMDimXpertIntersectLineFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPlaneFeatures( _  
    ByRef Feature1 As SwDMDimXpertFeature, _  
    ByRef Feature2 As SwDMDimXpertFeature _  
    ) As Boolean
```

SwDMDimXpertIntersectPlaneFeature (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertIntersectPlaneFeature Object

[Send comments on this topic.](#)

Object Model

SwDMDimXpertIntersectPlaneFeature

SOLIDWORKS Document Manager Type Library

SwDMDimXpertIntersectPlaneFeature Object Members

[Send comments on this topic.](#)

Public Methods

GetFeatures

GetNominalPlane

SOLIDWORKS Document Manager Type Library

GetFeatures Method (SwDMDimXpertIntersectPlaneFeature)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFeatures( _  
    ByRef Feature1 As SwDMDimXpertFeature, _  
    ByRef Feature2 As SwDMDimXpertFeature _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

GetNominalPlane Method (SwDMDimXpertIntersectPlaneFeature)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalPlane( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

SwDMDimXpertIntersectPointFeature (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertIntersectPointFeature Object

[Send comments on this topic.](#)

Object Model

SwDMDimXpertIntersectPointFeature

SOLIDWORKS Document Manager Type Library

SwDMDimXpertIntersectPointFeature Object Members

[Send comments on this topic.](#)

Public Methods

 GetFeatures
 GetNominalPoint
 GetNominalVector

SOLIDWORKS Document Manager Type Library

GetFeatures Method (SwDMDimXpertIntersectPointFeature)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFeatures( _  
    ByRef Feature1 As SwDMDimXpertFeature, _  
    ByRef Feature2 As SwDMDimXpertFeature _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

GetNominalPoint Method (SwDMDimXpertIntersectPointFeature)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalPoint( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library

GetNominalVector Method (SwDMDimXpertIntersectPointFeature)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalVector( _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
    ) As Boolean
```

swDmDimXpertISO2768PartType_e (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

swDmDimXpertISO2768PartType_e Enumeration

[See Also](#)



Members

Member	Value	Description
swDmDimXpertISO2768PartType_Coarse	3	
swDmDimXpertISO2768PartType_Fine	1	
swDmDimXpertISO2768PartType_Medium	2	
swDmDimXpertISO2768PartType_unknown	0	
swDmDimXpertISO2768PartType_VeryCoarse	4	

SwDMDimXpertLengthDimTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertLengthDimTol Object

 Object Model

SwDMDimXpertLengthDimTol

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertLengthDimTol Object Members



SwDMDimXpertLineProfileGeoTol (Type)

SOLIDWORKS Document Manager Type Library
SwDMDimXpertLineProfileGeoTol Object

[Send comments](#) on this topic.

Object Model

SwDMDimXpertLineProfileGeoTol

SOLIDWORKS Document Manager Type Library
SwDMDimXpertLineProfileGeoTol Object Members

[Send comments](#) on this topic.

Public Methods

 [GetPlanarZoneVector](#)

Public Properties

 [OuterToleranceValue](#)

SOLIDWORKS Document Manager Type Library
GetPlanarZoneVector Method (SwDMDimXpertLineProfileGeoTol)

[Send comments](#) on this topic.

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPlanarZoneVector( _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
    ) As Boolean
```

SOLIDWORKS Document Manager Type Library
OuterToleranceValue Property (SwDMDimXpertLineProfileGeoTol)

[Send comments](#) on this topic.

Syntax

Visual Basic for Applications (VBA)

```
Public Property OuterToleranceValue As Double
```

swDmDimXpertMaterialConditionModifier_e (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

swDmDimXpertMaterialConditionModifier_e Enumeration

[See Also](#)

Members

Member	Value	Description
swDmDimXpertMaterialConditionModifier_unknown	0	
swDmDimXpertMCM_LMC	1	
swDmDimXpertMCM_MMC	2	
swDmDimXpertMCM_NoMCM	3	
swDmDimXpertMCM_RFS	4	

SwDMDimXpertOrientationGeoTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertOrientationGeoTol Object

Object Model

SwDMDimXpertOrientationGeoTol

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertOrientationGeoTol Object Members

Public Methods

 GetMaxTolerance
 GetPlanarZoneVector
 GetProjectedZone
 IsTangentPlane

Public Properties

 Modifier
 ZoneType

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetMaxTolerance Method (SwDMDimXpertOrientationGeoTol)

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function GetMaxTolerance(_ ByRef <i>IsMax</i> As Boolean, _ ByRef <i>Tolerance</i> As Double _) As Boolean</pre>

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetPlanarZoneVector Method (SwDMDimXpertOrientationGeoTol)

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function GetPlanarZoneVector(_ ByRef <i>I</i> As Double, _ ByRef <i>J</i> As Double, _ ByRef <i>K</i> As Double _) As Boolean</pre>

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetProjectedZone Method (SwDMDimXpertOrientationGeoTol)

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function GetProjectedZone(_ ByRef <i>Enabled</i> As Boolean, _ ByRef <i>Value</i> As Double _) As Boolean</pre>

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IsTangentPlane Method (SwDMDimXpertOrientationGeoTol)



Visual Basic for Applications (VBA)

```
Public Function IsTangentPlane() As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

Modifier Property (SwDMDimXpertOrientationGeoTol)



Visual Basic for Applications (VBA)

```
Public Property Modifier As swDmDimXpertMaterialConditionModifier\_e
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ZoneType Property (SwDMDimXpertOrientationGeoTol)



Visual Basic for Applications (VBA)

```
Public Property ZoneType As swDmDimXpertOrientationZoneType\_e
```

swDmDimXpertOrientationZoneType_e (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

swDmDimXpertOrientationZoneType_e Enumeration

[See Also](#)



Members

Member	Value	Description
swDmDimXpertOrientationZoneType_Cylindrical	1	
swDmDimXpertOrientationZoneType_Planar	2	
swDmDimXpertOrientationZoneType_unknown	0	

SwDMDimXpertParallelismGeoTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertParallelismGeoTol Object

 Object Model

SwDMDimXpertParallelismGeoTol

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertParallelismGeoTol Object Members




SwDMDimXpertPart (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertPart Object

Object Model



SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertPart Object Members

Public Methods

	GetAnnotationCount
	GetAnnotations
	GetBlockTolerances
	GetFeatureCount
	GetFeatures
	IGetAnnotations
	IGetFeatures

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetAnnotationCount Method (SwDMDimXpertPart)

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function GetAnnotationCount() As Long</pre>

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetAnnotations Method (SwDMDimXpertPart)

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function GetAnnotations() As Variant</pre>

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetBlockTolerances Method (SwDMDimXpertPart)

Syntax

Visual Basic for Applications (VBA)
<pre>Public Function GetBlockTolerances() As SwDMDimXpertBlockTolerances</pre>

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetFeatureCount Method (SwDMDimXpertPart)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFeatureCount() As Long
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetFeatures Method (SwDMDimXpertPart)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetFeatures() As Variant
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IGetAnnotations Method (SwDMDimXpertPart)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetAnnotations( _  
    ByVal Count As Long _  
) As SwDMDimXpertAnnotation
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

IGetFeatures Method (SwDMDimXpertPart)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetFeatures( _  
    ByVal Count As Long _  
) As SwDMDimXpertFeature
```

SwDMDimXpertPatternAngleBetweenDimTol (Type)

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
SwDMDimXpertPatternAngleBetweenDimTol Object	

 Object Model

SwDMDimXpertPatternAngleBetweenDimTol

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
SwDMDimXpertPatternAngleBetweenDimTol Object Members	
	


SwDMDimXpertPatternFeature (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertPatternFeature Object

[Send comments on this topic.](#)

Object Model



SOLIDWORKS Document Manager Type Library

SwDMDimXpertPatternFeature Object Members

[Send comments on this topic.](#)

Public Methods

- [GetSubFeatureCount](#)
- [GetSubFeatures](#)
- [IGetSubFeatures](#)

SOLIDWORKS Document Manager Type Library

GetSubFeatureCount Method (SwDMDimXpertPatternFeature)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSubFeatureCount() As Long
```

SOLIDWORKS Document Manager Type Library

GetSubFeatures Method (SwDMDimXpertPatternFeature)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetSubFeatures() As Variant
```

SOLIDWORKS Document Manager Type Library

IGetSubFeatures Method (SwDMDimXpertPatternFeature)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IGetSubFeatures( _  
    ByVal Count As Long _  
) As SwDMDimXpertFeature
```

swDmDimXpertPatternTreatmentType_e (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

swDmDimXpertPatternTreatmentType_e Enumeration

[See Also](#)



Members

Member	Value	Description
swDmDimXpertPatternTreatmentType_CircularPattern	1	
swDmDimXpertPatternTreatmentType_IndividualFeatures	2	
swDmDimXpertPatternTreatmentType_unknown	0	

SwDMDimXpertPerpendicularityGeoTol (Type)

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
SwDMDimXpertPerpendicularityGeoTol Object	

 Object Model

SwDMDimXpertPerpendicularityGeoTol

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
SwDMDimXpertPerpendicularityGeoTol Object Members	
	

SwDMDimXpertPlaneFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertPlaneFeature Object

Object Model

SwDMDimXpertPlaneFeature

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertPlaneFeature Object Members



Public Methods

 [GetNominalPlane](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalPlane Method (SwDMDimXpertPlaneFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalPlane( _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double, _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

SwDMDimXpertPositionGeoTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertPositionGeoTol Object

Object Model

SwDMDimXpertPositionGeoTol

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertPositionGeoTol Object Members

Public Methods

 [GetMaxTolerance](#)

 [GetPlanarZoneVector](#)

 [GetProjectedZone](#)

Public Properties

 [Modifier](#)

 [ZoneType](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetMaxTolerance Method (SwDMDimXpertPositionGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetMaxTolerance( _  
    ByRef IsMax As Boolean, _  
    ByRef Tolerance As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetPlanarZoneVector Method (SwDMDimXpertPositionGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPlanarZoneVector( _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetProjectedZone Method (SwDMDimXpertPositionGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetProjectedZone( _  
    ByRef Enabled As Boolean, _  
    ByRef Value As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

Modifier Property (SwDMDimXpertPositionGeoTol)

Syntax

Visual Basic for Applications (VBA)

Public Property Modifier As [swDmDimXpertMaterialConditionModifier_e](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ZoneType Property (SwDmDimXpertPositionGeoTol)

 **Syntax**

Visual Basic for Applications (VBA)

Public Property ZoneType As [swDmDimXpertPositionZoneType_e](#)

swDmDimXpertPositionZoneType_e (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

swDmDimXpertPositionZoneType_e Enumeration

[See Also](#)

Members

Member	Value	Description
swDmDimXpertPositionZoneType_Boundary	1	
swDmDimXpertPositionZoneType_CylindricalPosition	2	
swDmDimXpertPositionZoneType_PlanarPosition	3	
swDmDimXpertPositionZoneType_RadialPositionArc	4	
swDmDimXpertPositionZoneType_RadialPositionPlanar	5	
swDmDimXpertPositionZoneType_SphericalPosition	6	
swDmDimXpertPositionZoneType_unknown	0	

SwDMDimXpertRadiusDimTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertRadiusDimTol Object

Object Model

SwDMDimXpertRadiusDimTol

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertRadiusDimTol Object Members



Public Properties

 [PatternTreatment](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

PatternTreatment Property (SwDMDimXpertRadiusDimTol)

Syntax

Visual Basic for Applications (VBA)

Public Property PatternTreatment As [swDmDimXpertPatternTreatmentType_e](#)

SwDMDimXpertSphereFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertSphereFeature Object

Object Model

SwDMDimXpertSphereFeature

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertSphereFeature Object Members

Public Methods

 [GetNominalSphere](#)

Public Properties

 [Inner](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetNominalSphere Method (SwDMDimXpertSphereFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetNominalSphere( _  
    ByRef R As Double, _  
    ByRef X As Double, _  
    ByRef Y As Double, _  
    ByRef Z As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

Inner Property (SwDMDimXpertSphereFeature)

Syntax

Visual Basic for Applications (VBA)

```
Public Property Inner As Boolean
```

SwDMDimXpertStraightnessGeoTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertStraightnessGeoTol Object

Object Model

SwDMDimXpertStraightnessGeoTol

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertStraightnessGeoTol Object Members

Public Methods

 [GetMaxTolerance](#)

 [GetPerUnitLength](#)

 [GetPlanarZoneVector](#)

Public Properties

 [Modifier](#)

 [ZoneType](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetMaxTolerance Method (SwDMDimXpertStraightnessGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetMaxTolerance( _  
    ByRef IsMax As Boolean, _  
    ByRef Tolerance As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetPerUnitLength Method (SwDMDimXpertStraightnessGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPerUnitLength( _  
    ByRef Enabled As Boolean, _  
    ByRef Distance As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

GetPlanarZoneVector Method (SwDMDimXpertStraightnessGeoTol)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPlanarZoneVector( _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

Modifier Property (SwDMDimXpertStraightnessGeoTol)

Syntax

Visual Basic for Applications (VBA)

Public Property Modifier As [swDmDimXpertMaterialConditionModifier_e](#)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

ZoneType Property (SwDmDimXpertStraightnessGeoTol)

 **Syntax**

Visual Basic for Applications (VBA)

Public Property ZoneType As [swDmDimXpertStraightnessZoneType_e](#)

swDmDimXpertStraightnessZoneType_e (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

swDmDimXpertStraightnessZoneType_e Enumeration

[See Also](#)



Members

Member	Value	Description
swDmDimXpertStraightnessZoneType_Cylindrical	1	
swDmDimXpertStraightnessZoneType_PlanarMedian	2	
swDmDimXpertStraightnessZoneType_Surface	3	
swDmDimXpertStraightnessZoneType_unknown	0	

SwDMDimXpertSurfaceFeature (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertSurfaceFeature Object

 Object Model

SwDMDimXpertSurfaceFeature

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertSurfaceFeature Object Members



SwDMDimXpertSurfaceProfileGeoTol (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertSurfaceProfileGeoTol Object

[Send comments on this topic.](#)

Object Model

SwDMDimXpertSurfaceProfileGeoTol

SOLIDWORKS Document Manager Type Library

SwDMDimXpertSurfaceProfileGeoTol Object Members

[Send comments on this topic.](#)

Public Properties

OuterToleranceValue

SOLIDWORKS Document Manager Type Library

OuterToleranceValue Property (SwDMDimXpertSurfaceProfileGeoTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

Public Property OuterToleranceValue As Double

SwDMDimXpertSymmetryGeoTol (Type)

SOLIDWORKS Document Manager Type Library
SwDMDimXpertSymmetryGeoTol Object

[Send comments](#) on this topic.

Object Model

SwDMDimXpertSymmetryGeoTol

SOLIDWORKS Document Manager Type Library
SwDMDimXpertSymmetryGeoTol Object Members

[Send comments](#) on this topic.

Public Methods

 [GetMaxTolerance](#)

 [GetZoneDirection](#)

Public Properties

 [Modifier](#)

SOLIDWORKS Document Manager Type Library
GetMaxTolerance Method (SwDMDimXpertSymmetryGeoTol)

[Send comments](#) on this topic.

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetMaxTolerance( _  
    ByRef IsMax As Boolean, _  
    ByRef Tolerance As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library
GetZoneDirection Method (SwDMDimXpertSymmetryGeoTol)

[Send comments](#) on this topic.

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetZoneDirection( _  
    ByRef I As Double, _  
    ByRef J As Double, _  
    ByRef K As Double _  
) As Boolean
```

SOLIDWORKS Document Manager Type Library
Modifier Property (SwDMDimXpertSymmetryGeoTol)

[Send comments](#) on this topic.

Syntax

Visual Basic for Applications (VBA)

```
Public Property Modifier As swDmDimXpertMaterialConditionModifier\_e
```

SwDMDimXpertTangencyGeoTol (Type)

SOLIDWORKS Document Manager Type Library

SwDMDimXpertTangencyGeoTol Object

[Send comments on this topic.](#)

Object Model

SwDMDimXpertTangencyGeoTol

SOLIDWORKS Document Manager Type Library

SwDMDimXpertTangencyGeoTol Object Members

[Send comments on this topic.](#)

Public Methods

 [GetOriginFeature](#)

SOLIDWORKS Document Manager Type Library

GetOriginFeature Method (SwDMDimXpertTangencyGeoTol)

[Send comments on this topic.](#)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetOriginFeature( _  
    ByRef Feature As SwDMDimXpertFeature _  
) As Boolean
```

SwDMDimXpertTotalRunoutGeoTol (Type)

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
SwDMDimXpertTotalRunoutGeoTol Object	

 Object Model

SwDMDimXpertTotalRunoutGeoTol

SOLIDWORKS Document Manager Type Library	Send comments on this topic.
SwDMDimXpertTotalRunoutGeoTol Object Members	
	

SwDMDimXpertWidthDimTol (Type)

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertWidthDimTol Object

 Object Model

SwDMDimXpertWidthDimTol

SOLIDWORKS Document Manager Type Library

[Send comments](#) on this topic.

SwDMDimXpertWidthDimTol Object Members

