

SOLIDWORKS HTML Control API (VB6 COM) — Reference (1/1): SwHtmlInterface

SOLIDWORKS API Documentation (converted from CHM)

SwHtmlInterface (Type)

SOLIDWORKS HTML Control Type Library

SwHtmlInterface Object

Object Model

SwHtmlInterface

SOLIDWORKS HTML Control Type Library

SwHtmlInterface Object Members

Public Methods

	GetCommandID
	GetCurrentTODIndex
	GetFontSize
	GetInterfaceBrightnessTheme
	GetPrevTipOfTheDay
	HideBubbleTooltip
	IsBeta
	IsX64
	RunInternalCommand
	ShowBubbleTooltip
	ShowBubbleTooltipAt
	ShowBubbleTooltipForAddinToolbar
	ShowHomeIconMarker
	ShowTooltip

SOLIDWORKS HTML Control Type Library

GetCommandID Method (SwHtmlInterface)

Syntax

```
Visual Basic for Applications (VBA)

Public Function GetCommandID( _
    ByVal ClsID As String, _
    ByVal UserCmdID As Long _
) As Long
```

SOLIDWORKS HTML Control Type Library

GetCurrentTODIndex Method (SwHtmlInterface)

Syntax

```
Visual Basic for Applications (VBA)

Public Function GetCurrentTODIndex() As Long
```

SOLIDWORKS HTML Control Type Library

GetFontSize Method (SwHtmlInterface)

Syntax

```
Visual Basic for Applications (VBA)

Public Function GetFontSize() As Long
```

SOLIDWORKS HTML Control Type Library

GetInterfaceBrightnessTheme Method (SwHtmlInterface)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetInterfaceBrightnessTheme() As Long
```

SOLIDWORKS HTML Control Type Library

GetPrevTipOfTheDay Method (SwHtmlInterface)

Syntax

Visual Basic for Applications (VBA)

```
Public Function GetPrevTipOfTheDay() As String
```

SOLIDWORKS HTML Control Type Library

HideBubbleTooltip Method (SwHtmlInterface)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub HideBubbleTooltip()
```

SOLIDWORKS HTML Control Type Library

IsBeta Method (SwHtmlInterface)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsBeta() As Long
```

SOLIDWORKS HTML Control Type Library

IsX64 Method (SwHtmlInterface)

Syntax

Visual Basic for Applications (VBA)

```
Public Function IsX64() As Long
```

SOLIDWORKS HTML Control Type Library

RunInternalCommand Method (SwHtmlInterface)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub RunInternalCommand( _  
    ByVal whichCommand As Long, _  
    ByVal arg As String _  
)
```

SOLIDWORKS HTML Control Type Library

ShowBubbleTooltip Method (SwHtmlInterface)

Syntax

Visual Basic for Applications (VBA)

```
Public Sub ShowBubbleTooltip( _  
    ByVal pointAt As Long, _  
    ByVal flashButtonIDs As String, _  
    ByVal titleResID As Long, _  
    ByVal titleString As String, _  
    ByVal messageString As String _  
)
```

ShowBubbleTooltipAt Method (SwHtmlInterface) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub ShowBubbleTooltipAt( _  
    ByVal pointX As Long, _  
    ByVal pointY As Long, _  
    ByVal arrowPos As Long, _  
    ByVal titleString As String, _  
    ByVal messageString As String, _  
    ByVal urlLoc As String _  
)
```

ShowBubbleTooltipForAddinToolbar Method (SwHtmlInterface) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub ShowBubbleTooltipForAddinToolbar( _  
    ByVal addInCLSID As String, _  
    ByVal pointAt_UserID As Long, _  
    ByVal flashButton_UserIDs As String, _  
    ByVal titleResID As Long, _  
    ByVal titleString As String, _  
    ByVal messageString As String _  
)
```

ShowHomeIconMarker Method (SwHtmlInterface) **Syntax**

Visual Basic for Applications (VBA)

```
Public Function ShowHomeIconMarker() As Long
```

ShowTooltip Method (SwHtmlInterface) **Syntax**

Visual Basic for Applications (VBA)

```
Public Sub ShowTooltip( _  
    ByVal ToolbarName As String, _  
    ByVal buttonIndex As Long, _  
    ByVal mask1 As Long, _  
    ByVal mask2 As Long, _  
    ByVal titleString As String, _  
    ByVal messageString As String _  
)
```