Nama : Ahmad Bima Ahsan F.

Nim : 2402005

Kelas : TI 1A

# Laporan Tugas Sistem Operasi intalasi PROXMOX;

1

#### **Proxmox Virtual Environment (PVE)**

The Proxmox Installer automatically partitions your hard disk. It installs all required packages and makes the system bootable from the hard disk. All existing partitions and data will be lost.

Please verify the installation target The displayed hard disk will be used for the installation. Warning: All existing partitions and data will be lost.

Press the Next button to continue the installation.

- Automatic hardware detection
   The installer automatically configures your hardware.

Previous Next

2

#### **Location and Time Zone selection**

The Proxmox Installer automatically makes location-based optimizations, like choosing the nearest mirror to download files from. Also make sure to select the correct time zone and keyboard layout.

Press the Next button to continue the installation.

- Country: The selected country is used to choose nearby mirror servers. This will speed up downloads and make updates more reliable.
- Time Zone: Automatically adjust daylight saving time.
- **Keyboard Layout:** Choose your keyboard layout.



3




## **Administration Password and Email Address**

**Proxmox Virtual Environment** is a full featured, highly secure GNU/Linux system, based on Debian.

In this step, please provide the root password.

- Password: Please use a strong password. It should be at least 8 characters long, and contain a combination of letters, numbers, and symbols.
- Email: Enter a valid email address. Your Proxmox VE server will send important alert notifications to this email account (such as backup failures, high availability events, etc.).

Press the Next button to continue the installation.



Λ

## **Management Network Configuration**

Please verify the displayed network configuration. You will need a valid network configuration to access the management interface after installing.

After you have finished, press the Next button. You will be shown a list of the options that you chose during the previous steps.

- IP address (CIDR): Set the main IP address and netmask for your server in CIDR notation.
- Gateway: IP address of your gateway or firewall.
- DNS Server: IP address of your DNS server.



5



## **Summary**

**Please confirm** the displayed information. Once you press the **Install** button, the installer will begin to partition your drive(s) and extract the required files.

Option	Value
Filesystem:	ext4
Disk(s):	/dev/sda
Country:	Indonesia
Timezone:	Asia/Jakarta
Keymap:	en-us
Email:	traa55641@gmail.comSSS
Management Interface:	enp0s3
Hostname:	purbaya
IP CIDR:	182.168.1.200/24
Gateway:	192.168.1.1
DNS:	8.8.8.8

