

# **Functions within Workspaces**

In Terra to share, delete, leave, or clone a workspace:

- 1. Login to <u>anvil.terra.bio</u>
- 2. Click on the <u>icon</u> on the top left corner
- 3. Click on "Workspaces"
- 4. In the "My Workspace", "PUBLIC", or "Featured" tab click the (i) icon
- 5. Click on the function that you want to perform: ☐ Clone → Leave
  - Share



\*make sure you have the appropriate permissions to perform these functions

# **Sharing Workspaces**


To share a workspace click on the <a href="https://share.com/share-a-com/share

- enter user emails you would like to share the workspace with
- select type of permission you would like the user to have (reader, writer, owner)

# **Cloning Workspaces**

To Clone a workspace click the icon and then click on the (or *Clone*) option. There are two ways to clone a workspace: Quick Create Workspace and Create Workspace (longer format).

To quick create a cloned workspace:



## Complete Basic Information and Billing tab

Enter Workspace name Add an optional description Select the Billing Project



### Click on "Quick Create Workspace"

The cloned Workspace should now show up under your Workspaces.

To clone a workspace using the longer format:



## Complete Basic Information and Billing tab

Add user emails and permissions in Sharing tab Determine if additional security options tab settings are necessary Click "Create Workspace"

## Leaving and Deleting Workspaces

To leave a workspace click on the Leave option:

• Click the "Leave Workspace" button

To delete a workspace click on the *m Delete* option:

- Type 'Delete Workspace' in the fill in space
- <u>Note</u>: the workspace will be permanently deleted with all its data and any users it is shared with will loose access

# **Cloned Workspace Components**

### Dashboard



a README for the workspace: it should contain information to help you understand the purpose and organization of the workspace

#### Data tab



Contains all the files associated with the Workspace: data, metadata, workflow outputs, etc.

Data Tables can link to files in other Workspaces or even files that live outside of Terra.

# **Using External Data**

- To get started, find the pre-loaded data <u>using AnVIL datasets library</u> and export it into a new or existing workspace in AnVIL
- The <u>AnVIL Dataset Catalog</u> hosts NHGRI datasets (note access requirements)
  - Use data explorer to filter, search for datasets, and build your own custom dataset to export to AnVIL
- Pre-loaded data can also be found in featured and public workspaces which can be cloned for use