# COMP 122/L Lecture 6

Mahdi Ebrahimi

Slides adapted from Dr. Kyle Dewey

# Assembly

# What's in a Processor?

# Simple Language

- We have variables, integers, addition, and assignment
- Restrictions:
  - Can only assign integers directly to variables
  - Can only add variables, always two at a time

Want to say:
$$z = 5 + 7$$
;

Translation
$$x = 5;$$
 $y = 7;$ 

$$z = x + y;$$

# Implementation

• What do we need to implement this?

```
x = 5;

y = 7;

z = x + y;
```

# Core Components

- Some place to hold the statements as we operate on them
- Some place to hold which statement is next
- Some place to hold variables
- Some way to add numbers

## Back to Processors

- Amazingly, these are all the core components of a processor
  - Why is this significant?

## Back to Processors

- Amazingly, these are all the core components of a processor
  - Why is this significant?
- Processors just reads a series of statements (instructions) forever. No magic.

# Core Components

- Some place to hold the statements as we operate on them
- Some place to hold which statement is next
- Some place to hold variables
- Some way to add numbers

# Core Components

- Some place to hold the statements as we operate on them - memory
- Some place to hold which statement is next program counter
- Some place to hold variables registers
  - Behave just like variables with fixed names
- Some way to add numbers arithmetic logic unit (ALU)
- Some place to hold which statement is currently being executed – instruction register (IR)

## **Basic Interaction**

- Copy instruction from memory at wherever the program counter says into the instruction register
- Execute it, possibly involving registers and the arithmetic logic unit
- Update the program counter to point to the next instruction
- Repeat


## **Basic Interaction**

```
initialize();
while (true) {
  instruction_register =
    memory[program_counter];
  execute(instruction_register);
  program_counter++;
}
```

<sup>-</sup>initialize() will load in the initial state, and put instructions in memory

<sup>-</sup>execute(instruction\_register) will read the instruction and do what it says, potentially looking at registers, assigning things to registers, and using the arithmetic logic unit -Have this handy while going through next animation





Memory
?



Arithmetic Logic Unit -----?

-All the hardware, before initialization

```
Instruction Register
-----?
```

```
Registers

x: ?
y: ?
z: ?
```

```
Memory

0: x = 5;

1: y = 7;

2: z = x + y;
```





- -Initialization occurs. Instructions are in memory, and the program counter is set to 0.
- -In a real processor, there is some very basic initialization when it boots up, at which point the BIOS (and subsequently the OS) take over. From then on, its the responsibility of whatever is loaded in to set the contents of memory, the registers, and the program counter correctly. The operating systems class covers this stuff.

```
Registers

x: ?
y: ?
z: ?
```



```
Arithmetic Logic Unit
-----?
```

-We load instruction 0 into the instruction register

```
Memory

0: x = 5;

1: y = 7;

2: z = x + y;
```

```
Registers

x: 5

y: ?

z: ?
```



```
Arithmetic Logic Unit
-----?
```

-We execute the instruction, setting register x to 5


# Instruction Register x = 5;

# Memory 0: x = 5; 1: y = 7; 2: z = x + y;



```
Arithmetic Logic Unit
-----
0 + 1 = 1
```

-We update the program counter





```
Arithmetic Logic Unit
-----?
```

-Load in the next instruction

```
Registers

x: 5
y: 7
z: ?
```



```
Arithmetic Logic Unit
-----?
```

-We execute the instruction, setting register y to 7

# Instruction Register ----y = 7;

# Memory 0: x = 5; 1: y = 7; 2: z = x + y;



-We update the program counter






```
Arithmetic Logic Unit
-----?
```

-Load in the next instruction









- -Execute it, consulting the registers to get the values of x and y
- -This consults the ALU





-The ALU sets the result



# Why ARM?

- Incredibly popular in embedded devices
- Much simpler than Intel processors

<sup>-</sup>Embedded devices include things like phones and microwaves.

<sup>-</sup>Your computer may have an ARM processor in it even though the "main" processor is from Intel

### Original

$$x = 5;$$
  
 $y = 7;$   
 $z = x + y;$ 

### **ARM**

```
mov r0, #5
mov r1, #7
add r2, r0, r1
```

### Original

$$x = 5;$$
  
 $y = 7;$   
 $z = x + y;$ 

#### ARM

```
mov r0, #5
mov r1, #7
add r2, r0, r1
```

**mov**e: put the given value into a register

r0: register 0

### Original

$$x = 5;$$
  
 $y = 7;$   
 $z = x + y;$ 

#### **ARM**

```
mov r0, #5
mov r1, #7
add r2, r0, r1
```

**mov**e: put the given value into a register

rl: register l

### Original

$$x = 5;$$
  
 $y = 7;$   
 $z = x + y;$ 

#### ARM

```
mov r0, #5
mov r1, #7
add r2, r0, r1
```

add:add the rightmost
registers, putting the result
in the first register

r2: register 2

# Available Registers

- 17 registers in all
  - 16"general-purpose"
  - I "special-purpose"
- For the moment, we will only consider registers r0 r12

<sup>-</sup>General purpose: can put values in them and take values out as I please

<sup>-</sup>Special purpose: holding certain flags. Can manipulate this, but not in the same way as a general-purpose register

# Assembly

- The code that you see below is ARM assembly
- Assembly is \*almost\* what the machine sees. For the most part, it is a direct translation to binary from here (known as machine code)

```
mov r0, #5
mov r1, #7
add r2, r0, r1
```

<sup>-</sup>More on why I said "the most part" later. Psuedo instructions are translated to other instructions. Branches also need calculation to occur (for labels), and there are caveats about the instruction immediately after a branch

# Workflow

### **Assembly**

```
mov r0, #5
mov r1, #7
add r2, r0, r1
```

Assembler (analogous to a compiler)

Machine Code

001101...

## Machine Code

- This is what the process actually executes and accepts as input
- Each instruction is represented with 32 bits

add r2, r0, r1

<sup>-</sup>Converting to machine code is mostly one-to-one: just put the right bits in the right places

<sup>-</sup>There are some exceptions where we have to be a bit smarter, but not much smarter. Assemblers are nowhere near as complex as compilers.



```
Registers

r0: ?
r1: ?
r2: ?
```

Memory
?



Arithmetic Logic Unit
-----?

-All the hardware, before initialization

```
Instruction Register
mov r0, #5
```

```
Registers
r0: ?
r1: ?
r2: ?
```

```
Memory

0: mov r0, #5

4: mov r1, #7

8: add r2, r0, r1
```



```
Arithmetic Logic Unit
-----?
```

-We load instruction 0 into the instruction register

```
Instruction Register
mov r0, #5
```

```
Registers

r0: 5
r1: ?
r2: ?
```

```
Memory

0: mov r0, #5

4: mov r1, #7

8: add r2, r0, r1
```




```
Arithmetic Logic Unit
-----?
```

-We execute the instruction, setting register r0 to 5

### Instruction Register mov r0, #5

```
Registers

r0: 5
r1: ?
r2: ?
```





```
Arithmetic Logic Unit
-----
0 + 4 = 4
```

- -We update the program counter
- -Note that we add 4 instead of one, as instructions are four bytes long

### Instruction Register mov r1, #7

```
Registers
r0: 5
r1: ?
r2: ?
```

```
Memory

0: mov r0, #5

4: mov r1, #7

8: add r2, r0, r1
```

Program Counter
4

Arithmetic Logic Unit
-----?

-Load in the next instruction

```
Instruction Register
mov r1, #7
```

```
Registers
r0: 5
r1: 7
r2: ?
```

```
Memory

0: mov r0, #5

4: mov r1, #7


8: add r2, r0, r1
```




```
Arithmetic Logic Unit
-----?
```

-We execute the instruction, setting register r1 to 7

### Instruction Register mov r1, #7







-We update the program counter

### Instruction Register add r2, r0, r1

```
Registers
r0: 5
r1: 7
r2: ?
```

```
Memory

0: mov r0, #5

4: mov r1, #7

8: add r2, r0, r1
```




```
Arithmetic Logic Unit
-----?
```

-Load in the next instruction

## Instruction Register add r2, r0, r1

```
Registers

r0: 5
r1: 7
r2: ?
```






```
Arithmetic Logic Unit
-----
5 + 7 = 12
```


- -Execute it, consulting the registers to get the values of r0 and r1
- -This consults the ALU

### Instruction Register add r2, r0, r1

# Registers r0: 5 r1: 7 r2: 12







-The ALU sets the result

# Adding More Functionality

- We need a way to display the result
- What does this entail?

# Adding More Functionality

- We need a way to display the result
- What does this entail?
  - Input / output. This entails talking to devices, which the operating system handles
  - We need a way to tell the operating system to kick in

### Talking to the OS

- We are going to be running on an ARM simulator, ARMS im#
- We cannot directly access system libraries (they aren't even in the same machine language)
- How might we print something?

#### **ARMSim# Routines**

- ARM features a Swi instruction, which triggers a software interrupt
- Outside of a simulator, these pause the program and tell the OS to check something
- Inside the simulator, it tells the simulator to check something

#### SWİ

So we have the OS/simulator's attention. But how does it know what we want?

#### swi

- So we have the OS/simulator's attention. But how does it know what we want?
  - swi operand: integer saying what to do
  - The OS/simulator can also read the registers to get extra information as needed

<sup>-&</sup>quot;Integer saying what to do": e.g., we agree that "5" means "print something"

<sup>-</sup>With reading the registers, these could include exactly what to print

# (Finally) Printing an Integer

- For ARMS im#, the integer that says "print an integer" is  $0 \times 6B$
- Register r1 holds the integer to print
- Register r0 holds where to print it;1 means "print to standard output (screen)"

# Augmenting with Printing

```
mov r0, #5
mov r1, #7
add r2, r0, r1

mov r1, r2 ; r1: integer to print
mov r0, #1 ; r0: where to print it
swi 0x6B ; 0x6B: print integer
```

### Exiting

- If you are using ARMSim#, then you need to say when you are done as well
- How might this be done?

### Exiting

- If you are using ARMSim#, then you need to say when you are done as well
- How might this be done?
  - swi with a particular operand (specifically  $0 \times 11$ )

### Augmenting with Exiting


```
mov r0, #5
mov r1, #7
add r2, r0, r1

mov r1, r2 ; r1: integer to print
mov r0, #1 ; r0: where to print it
swi 0x6B ; 0x6B: print integer


swi 0x11 ; 0x11: exit program
```

# Making it a Full Program

- Everything is just a bunch of bits
- We need to tell the assembler which bits should be placed where in memory




- -Image source: <a href="https://en.wikipedia.org/wiki/Data\_segment">https://en.wikipedia.org/wiki/Data\_segment</a>
- -Representation of a program in memory
- -What do you recognize?



-Image source: <a href="https://en.wikipedia.org/wiki/Data\_segment">https://en.wikipedia.org/wiki/Data\_segment</a>


-You've seen these two before

-What might the rest be?



-Image source: <a href="https://en.wikipedia.org/wiki/Data\_segment">https://en.wikipedia.org/wiki/Data\_segment</a>

### Marking Code Use a . text directive to specify code section




```
.text
mov r0, #5
mov r1, #7
add r2, r0, r1
mov r1, r2
mov r0, #1
swi 0x6B
swi 0x11
```

-Directives tell the assembler to do something

#### Marking Code

Use a .data directive to specify data section



.data

string1:

.asciz "hello"

string2:

.asciz "bye"

-Directives tell the assembler to do something

# ARMSim# Demo: hello.s

#### ARMSim# Demo:

arithmetic\_ops.s

#### ARMSim# Demo:

read\_and\_print\_int.s