## Task- Add dynamic volume in windows 10 vm










Disk Management
File Action View Help
New Striped Volume
Select Disks
You can select the disks and set the disk size for this volume.
Select the disks you want to use, and then click Add.
Available:
Selected:
Disk 1 5102 MB
Disk 2 5102 MB
Add >
< Remove
< Remove All
Total volume size in megabytes (MB): 10204
Maximum available space in MB: 5102
Select the amount of space in MB: 5102
< Back
Next >
Cancel
Unallocated
Primary partition
Activate Windows
Go to Settings to activate Windows.
Type here to search
32°C Sunny
ENG
04:07
29-04-2024


Disk Management
File Action View Help
New Striped Volume
Assign Drive Letter or Path
For easier access, you can assign a drive letter or drive path to your volume.
Assign the following drive letter:
E
Mount in the following empty NTFS folder:
Browse...
Do not assign a drive letter or drive path
< Back
Next >
Cancel
Unallocated
Primary partition
Activate Windows
Go to Settings to activate Windows.
Type here to search
32°C Sunny
ENG
04:08
29-04-2024


Disk Management
File Action View Help
New Striped Volume
Format Volume
To store data on this volume, you must format it first.
Choose whether you want to format this volume, and if so, what settings you want to use.
Do not format this volume
Format this volume with the following settings:
File system: NTFS
Allocation unit size: Default
Volume label: Stripped_Vol
Perform a quick format
Enable file and folder compression
< Back
Next >
Cancel
Unallocated
Primary partition
Activate Windows
Go to Settings to activate Windows.
Type here to search
High UV
ENG
04:09
29-04-2024


Disk Management
File Action View Help
New Striped Volume
Completing the New Striped Volume Wizard
You have successfully completed the Wizard.
You selected the following settings:
Volume type: Striped
Disks selected: Disk 1, Disk 2
Volume size: 10204 MB
Drive letter or path: E:
File system: NTFS
Allocation unit size: Default
Volume label: Stripped_Vol
Quick format: No
To close this wizard, click Finish.
< Back
Finish
Cancel
Unallocated
Primary partition
Activate Windows
Go to Settings to activate Windows.
Type here to search
Earnings upcoming
ENG
04:09
29-04-2024


Disk Management
File Action View Help
Volume Layout Type File System Status Capacity Free Spa... % Free
(C:) Simple Basic NTFS Healthy (B... 59.37 GB 32.71 GB 55 %
(Disk 0 partition 1) Simple Basic Healthy (E... 100 MB 100 MB 100 %
(Disk 0 partition 4) Simple Basic Healthy (R... 530 MB 530 MB 100 %
ESD-ISO (D:) Simple Basic UDF Healthy (P... 4.46 GB 0 MB 0 %
Disk Management
The operation you selected will convert the selected basic disk(s) to dynamic disk(s). If you convert the disk(s) to dynamic, you will not be able to start installed operating systems from any volume on the disk(s) (except the current boot volume). Are you sure you want to continue?
Yes
No
Disk 1
Basic
4.98 GB
Online
4.98 GB
Unallocated
Disk 2
Basic
4.98 GB
Online
4.98 GB
Unallocated
Unallocated
Primary partition
Activate Windows
Go to Settings to activate Windows.
Type here to search
Earnings upcoming
ENG
04:10
29-04-2024


Disk Management
File Action View Help
Volume Layout Type File System Status Capacity Free Spa... % Free
(C:) Simple Basic NTFS Healthy (B... 59.37 GB 32.71 GB 55 %
(Disk 0 partition 1) Simple Basic Healthy (E... 100 MB 100 MB 100 %
(Disk 0 partition 4) Simple Basic Healthy (R... 530 MB 530 MB 100 %
ESD-ISO (D:) Simple Basic UDF Healthy (P... 4.46 GB 0 MB 0 %
Stripped_Vol (E:) Striped Dynamic NTFS Healthy 9.96 GB 9.93 GB 100 %
Disk 3
Unknown
5.00 GB
Not Initialized
5.00 GB
Unallocated
Disk 4
Unknown
5.00 GB
Not Initialized
5.00 GB
Unallocated
Disk 5
Unknown
5.00 GB
Not Initialized
5.00 GB
Unallocated
CD-ROM 0
DVD
4.46 GB
ESD-ISO (D:)
4.46 GB UDF
Unallocated
Primary partition
Striped volume
Activate Windows
Go to Settings to activate Windows.
Type here to search
32°C Sunny
ENG
04:14
29-04-2024


Disk Management
File Action View Help
Volume Layout Type File System Status Capacity Free Spa... % Free
(C:) Simple Basic NTFS Healthy (B... 59.37 GB 32.71 GB 55 %
(Disk 0 partition 1) Simple Basic Healthy (E... 100 MB 100 MB 100 %
(Disk 0 partition 4) Simple Basic Healthy (R... 530 MB 530 MB 100 %
ESD-ISO (D:) Simple Basic UDF Healthy (P... 4.46 GB 0 MB 0 %
Stripped_Vol (E:) Striped Dynamic NTFS Healthy 9.96 GB 9.93 GB 100 %
Initialize Disk
You must initialize a disk before Logical Disk Manager can access it.
Select disks:
Disk 3
Disk 4
Disk 5
Use the following partition style for the selected disks:
MBR (Master Boot Record)
GPT (GUID Partition Table)
Note: The GPT partition style is not recognized by all previous versions of Windows.
OK
Cancel
Disk 3 Unknown 5.00 GB Not Initialized
5.00 GB Unallocated
Disk 4 Unknown 5.00 GB Not Initialized
5.00 GB Unallocated
Disk 5 Unknown 5.00 GB Not Initialized
5.00 GB Unallocated
CD-ROM 0 DVD 4.46 GB
ESD-ISO (D:) 4.46 GB UDF
Unallocated Primary partition Striped volume
Activate Windows
Go to Settings to activate Windows.
Type here to search
32°C Sunny
ENG
04:14
29-04-2024


All Control Panel Items
Control Panel › All Control Panel Items
Search Control Panel
Adjust your computer's settings
View by: Large icons
Administrative Tools
AutoPlay
Backup and Restore (Windows 7)
Color Management
Credential Manager
Date and Time
Default Programs
Device Manager
Devices and Printers
Ease of Access Center
File Explorer Options
File History
Fonts
Indexing Options
Internet Options
Keyboard
Mouse
Network and Sharing Center
Phone and Modem
Power Options
Programs and Features
Recovery
Region
RemoteApp and Desktop Connections
Security and Maintenance
Sound
Speech Recognition
Storage Spaces
Sync Center
System
Taskbar and Navigation
Troubleshooting
User
Windows Defender Firewall
Work Folders
Storage Spaces
Help protect your files from drive failure.
Activate Windows
Go to Settings to activate Windows.
Type here to search
32°C Sunny
ENG
04:16
29-04-2024


Storage Spaces
Control Panel › All Control Panel Items › Storage Spaces
Search Control Panel
Control Panel Home
Create a new pool and storage space
Manage Storage Spaces
Use Storage Spaces to save files to two or more drives to help protect you from a drive failure. Storage Spaces also lets you easily add more drives if you run low on capacity. If you don't see task links, click Change settings.
Create a new pool and storage space
See also
File History
Activate Windows
Go to Settings to activate Windows.
Type here to search
32°C Sunny
ENG
04:17
29-04-2024


Storage Spaces
Control Panel › All Control Panel Items › Storage Spaces
Search Control Panel
Control Panel Home
Create a new pool and storage space
Manage Storage Spaces
Use Storage Spaces to save files to two or more drives to help protect you from a drive failure. Storage Spaces also lets you easily add more drives if you run low on capacity. If you don't see task links, click Change settings.
Change settings
Storage pool
OK
Using 4.75 GB of 13.1 GB pool capacity
Create a storage space
Add drives
Rename pool
Optimize drive usage
Storage spaces
Storage space (F:)
Two-way mirror
3.00 GB
Using 1.50 GB pool capacity
OK
View files
Change
Delete
Physical drives
See also
File History
Activate Windows
Go to Settings to activate Windows.
Type here to search
32°C Sunny
ENG
04:21
29-04-2024